

Configuring Funk RADIUS to Authenticate Cisco VPN Clients

Document ID: 13832

- Introduction**
- Before You Begin**
 - Conventions
 - Prerequisites
 - Components Used
- Configuring the VPN 3000 Concentrator**
- Configuring the RADIUS Server**
- Related Information**

Introduction

This document shows how to configure the VPN 3000 Concentrator and the Funk RADIUS server to work together to authenticate a Cisco VPN Client. After authenticating the VPN Client, the Funk RADIUS server then provides the Client with IP addresses.

Before You Begin

Conventions

For more information on document conventions, see the Cisco Technical Tips Conventions.

Prerequisites

The information presented in this document assumes that you have configured the private and public interfaces on the VPN Concentrator.

Components Used

The information in this document is based on all releases of the VPN 3000 Concentrator and applies to both the Cisco VPN 3000 Client (2.5.x) and the Cisco VPN Client (3.x).

This information was created from devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If you are working in a live network, ensure that you understand the potential impact of any command before using it.

Configuring the VPN 3000 Concentrator

Follow the steps below to configure the VPN Concentrator side.

1. Go to **Configuration > System > Servers > Authentication** and click **Add**. For the Server Type, select **Internal**, then click **Add**.
2. Go to **Configuration > System > Servers > Authentication**, click **Add**, and configure the following parameters.

- ◆ Server Type: Select **RADIUS**.
- ◆ Authentication Server: Enter the IP address or host name of the RADIUS server.
- ◆ Server Secret: Enter the exact same string as that on the RADIUS server.

When you have configured these parameters, click **Add**.

3. Go to **Configuration > System > Address Management** and check the option for **Use Address from Authentication Server**.
4. Go to **Configuration > User Management > Groups**, click **Add**, and configure the parameters for group identity, DNS, and authentication.

- ◆ On the Identity tab, set the following parameters.

- ◇ Group Name (case sensitive)
- ◇ Password (case sensitive)

- ◆ On the General tab, set the following parameters.

- ◇ Primary DNS
- ◇ Secondary DNS
- ◇ Primary WINS
- ◇ Secondary WINS

Note: The IP addresses of the two WINS servers are passed to the VPN Client upon connection.

- ◆ On the IPSec tab, set the following parameters.

- ◇ Authentication: Select **RADIUS**.

When you have configured these parameters, click **Add**.

With the release of 3.0 and later, you can configure individual Funk RADIUS servers for individual groups, as opposed to one Funk RADIUS server defined globally and used by all groups. Any groups that do not have individual Funk RADIUS servers configured will use the Funk server that is defined globally.

The example above defines one global Funk RADIUS server. You can also choose to define individual Funk RADIUS servers for each group. To do this, go to **Configuration > User Management > Groups**, highlight a group, and choose **Modify Auth Server**.

Configuring the RADIUS Server

Follow the steps below to configure the RADIUS server to communicate with the VPN Concentrator. For more complete information on the server, refer to Funk Software or Juniper Networks .

1. On the RAS Client menu, click **Add** and configure the parameters for client name, IP address and make/model.
 - ◆ Client Name: Enter the name of the VPN Concentrator.
 - ◆ IP Address: Enter the address of the interface that communicates with the RADIUS server. (The RADIUS server views the VPN Concentrator as a RADIUS client.)
 - ◆ Make/Model: Enter **VPN 3000 Concentrator**.
2. Click **Edit authentication secret** and enter the shared secret, then click **Save**.
3. On the Users menu, choose the user/group you have set up and add return–list attributes for class and framed IP address.
 - ◆ Class: Enter the Group Name you configured in Step 4 above.
 - ◆ Framed IP Address: Enter the IP address or the pool name of the VPN Concentrator.
4. Stop and restart the RADIUS Service.

Related Information

- [RADIUS in IOS Documentation](#)
 - [RADIUS Support Page](#)
 - [IPSec Support Page](#)
 - [Cisco VPN 3000 Series Concentrator Support Page](#)
 - [Cisco VPN 3000 Series Client Support Page](#)
 - [Requests for Comments \(RFCs\)](#)
 - [Technical Support & Documentation – Cisco Systems](#)
-

[Contacts & Feedback](#) | [Help](#) | [Site Map](#)

© 2008 – 2009 Cisco Systems, Inc. All rights reserved. [Terms & Conditions](#) | [Privacy Statement](#) | [Cookie Policy](#) | [Trademarks of Cisco Systems, Inc.](#)

Updated: Jan 14, 2008

Document ID: 13832
