

Configuring RADIUS Dial-Up with Livingston Server Authentication

Document ID: 8537

Introduction

Prerequisites

- Requirements
- Components Used
- Conventions

Configure

- Configuration
- Clients File on Server
- Users File on Server
- Microsoft Windows Setup for Users Lines 1 and 2
- Microsoft Windows Setup for User Line 3

Verify

Troubleshoot

- Router Troubleshooting Commands
- Server

NetPro Discussion Forums – Featured Conversations

Related Information

Introduction

This document assists the first-time RADIUS user in how to set up and debug a dial-in RADIUS configuration with authentication to a Livingston RADIUS server. It is not an exhaustive description of the Cisco IOS® Software RADIUS capabilities. Livingston documentation is available from the Lucent Technologies web site. The router configuration is the same no matter what server you use.

Cisco offers RADIUS code in Cisco Secure ACS for Windows, Cisco Secure UNIX, or Cisco Access Registrar. The router configuration in this document was developed on a router running Cisco IOS Software Release 11.3.3. Cisco IOS Software Release 12.0.5.T and later uses **group radius** instead of **radius**. Therefore, statements such as **aaa authentication login default radius enable** appear as **aaa authentication login default group radius enable**. Refer to the RADIUS information in Cisco IOS documentation for details on RADIUS router commands.

Prerequisites

Requirements

There are no specific requirements for this document.

Components Used

The information in this document is based on these software and hardware versions:

- Cisco IOS Software Release 11.3.3
- Livingston RADIUS

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

Conventions

Refer to Cisco Technical Tips Conventions for more information on document conventions.

Configure

In this section, you are presented with the information to configure the features described in this document.

Note: Use the Command Lookup Tool (registered customers only) to find more information on the commands used in this document.

Configuration

This document uses this configuration:

```
Router Configuration
!
aaa new-model
aaa authentication login default radius enable
aaa authentication ppp default if-needed radius
aaa authorization network default radius
enable password cisco
!
chat-script default "" at&fls0=1&h1&r2&c1&d2&b1e0q2 OK
!
interface Ethernet0
 ip address 10.29.1.3 255.255.255.0
!

!--- CHAP/PPP authentication user:

interface Async1
 ip unnumbered Ethernet0
 encapsulation ppp
 async mode dedicated
 peer default ip address pool async
 no cdp enable
 ppp authentication chap
!

!--- PAP/PPP authentication user:

interface Async2
 ip unnumbered Ethernet0
 encapsulation ppp
 async mode dedicated
 peer default ip address pool async
 no cdp enable
 ppp authentication pap
!

!--- Login authentication user with autocommand PPP:
```

```

interface Async3
ip unnumbered Ethernet0
encapsulation ppp
async mode interactive
peer default ip address pool async
no cdp enable
!
ip local pool async 10.6.100.101 10.6.100.103
radius-server host 171.68.118.101
radius-server timeout 10
radius-server key cisco
!
line 1
session-timeout 20
exec-timeout 120 0
script startup default
script reset default
modem Dialin
transport input all
stopbits 1
rxspeed 115200
txspeed 115200
flowcontrol hardware
!
line 2
session-timeout 20
exec-timeout 120 0
script startup default
script reset default
modem Dialin
transport input all
stopbits 1
rxspeed 115200
txspeed 115200
flowcontrol hardware
!
line 3
session-timeout 20
exec-timeout 120 0
autoselect during-login
autoselect ppp
script startup default
script reset default
modem Dialin
autocommand ppp
transport input all
stopbits 1
rxspeed 115200
txspeed 115200
flowcontrol hardware
!
end

```

Clients File on Server

Note: This assumes Livingston RADIUS.

```

# Handshake with router--router needs "radius-server key cisco":
10.29.1.3 cisco

```

Users File on Server

Note: This assumes Livingston RADIUS.

```
# User who can telnet in to configure:
admin Password = "admin"
User-Service-Type = Login-User

# ppp/chap authentication line 1 - password must be cleartext per chap rfc 1994
# address assigned from pool on router
chapuser Password = "chapuser"
User-Service-Type = Framed-User,
Framed-Protocol = PPP

# ppp/pap authentication line 2
# address assigned from pool on router
# Can also have 'Password = "UNIX" which uses /etc/passwd
papuser Password = "papuser"
User-Service-Type = Framed-User,
Framed-Protocol = PPP

# ppp/chap authentication line 1 - password must be cleartext per chap rfc 1994
# address assigned by server
chapadd Password = "chapadd"
User-Service-Type = Framed-User,
Framed-Protocol = PPP,
Framed-Address = 10.10.10.10

# ppp/pap authentication line 2
# address assigned by server
papadd Password = "papadd"
User-Service-Type = Framed-User,
Framed-Protocol = PPP,
Framed-Address = 10.10.10.11

# authentication user line 3
# address assigned from pool on router
# Can also have 'Password = "UNIX" which uses /etc/passwd
authauto = "authauto"
User-Service-Type = Login-User
```

Microsoft Windows Setup for Users Lines 1 and 2

Note: The PC configuration can vary slightly based on the operating system version you use.

1. Select **Start > Programs > Accessories > Dial-Up Networking**.
2. Select **Connections > Make New Connection** and enter a name for your connection.
3. Enter your modem-specific information. Under **Configure > General** choose the highest speed of your modem, but do not check the box below this.
4. Select **Configure > Connection**, and use **8 data bits, no parity, and 1 stop bit**. For Call preferences, select **Wait for dial tone before dialing**, and **Cancel the call if not connected after 200 seconds**.
5. Select only **Hardware Flow Control** and **Modulation Type Standard** for Advanced.
6. Under **Configure > Options** nothing should be checked except under status control. Click **OK**.
7. Enter the telephone number of the destination, then click **Next** and **Finish**.
8. Once the new connection icon appears, right-click on it and select **Properties > Server Type**.
9. Choose **PPP:WINDOWS 95, WINDOWS NT 3.5, Internet** and do not check any advanced options. Check at least **TCP/IP** under allowed network protocols.
10. Choose **Server assigned IP address, Server assigned name server addresses, and Use default**

gateway on remote network under TCP/IP settings. Click **OK**.

11. When the user double-clicks the icon to bring up the Connect To window to dial, the user must fill in the User name and Password fields, and then click **Connect**.

Microsoft Windows Setup for User Line 3

The configuration for User Line 3 (authentication user with autocommand PPP) is the same as for Users Line 1 and 2. The exception is to check **Bring up terminal window after dialing** from the **Configure > Options** window.

When you double-clicks the icon to bring up the Connect To window to dial, do *not* fill in the User name and Password fields. Click **Connect**. After the connection to the router is made, the enter the username and password in the black window that appears. Click **Continue (F7)** after authentication.

Verify

There is currently no verification procedure available for this configuration.

Troubleshoot

Router Troubleshooting Commands

The Output Interpreter Tool (registered customers only) (OIT) supports certain **show** commands. Use the OIT to view an analysis of **show** command output.

Note: Refer to Important Information on Debug Commands before you use **debug** commands.

- **terminal monitor** Displays **debug** command output and system error messages for the current terminal and session.
- **debug ppp negotiation** Displays PPP packets sent during PPP startup, where PPP options are negotiated.
- **debug ppp packet** Displays PPP packets that are sent and received. (This command displays low-level packet dumps.)
- **debug ppp chap** Displays information about whether a client passes authentication (for Cisco IOS Software Releases earlier than 11.2).
- **debug aaa authentication** Displays information on AAA/TACACS+ authentication.
- **debug aaa authorization** Displays information on AAA/TACACS+ authorization.

Server

Note: This assumes Livingston's UNIX server code.

```
radiusd -x -d <full_path_to_users_clients_dictionary>
```

NetPro Discussion Forums – Featured Conversations

Networking Professionals Connection is a forum for networking professionals to share questions, suggestions, and information about networking solutions, products, and technologies. The featured links are some of the most recent conversations available in this technology.

NetPro Discussion Forums – Featured Conversations for Security

Security: Intrusion Detection [Systems]

Security: AAA

Security: General

Security: Firewalling

Related Information

- [Configuring RADIUS with Livingston Server](#)
- [RADIUS Support Page](#)
- [RADIUS in IOS Documentation](#)
- [Requests for Comments \(RFCs\)](#)
- [Technical Support & Documentation – Cisco Systems](#)

All contents are Copyright © 2006–2007 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.

Updated: Jul 26, 2007

Document ID: 8537
