



CHAPTER 5

Uninstalling Cisco Broadband Access Center

This chapter describes how to uninstall Cisco Broadband Access Center (Cisco BAC) from the CLI.



Note

You cannot uninstall the RDU and the DPE that are installed in a same server separately. Both components are uninstalled together.

The uninstall program removes all the DPE and RDU component files under the installation directory (the default installation directory is */opt/CSCObac*) that are installed in the same server when the uninstall command is executed. It also shuts down and removes these processes if they are detected: RDU, SNMP Agent, Tomcat, Watchdog, and DPE.

The uninstallation program does not remove files that were placed outside the installation directory. For example, a component installation places the database and database transaction logs directories under */var/CSCObac*. These files must be manually removed. (Subsequent sections describe how to delete these files.) But, if you choose to install the home, data, and database transaction log directories in the same location, the uninstallation program warns you that continuing the uninstallation will remove the data and log files.

Should the program fail to uninstall Cisco BAC, error messages appear.

This chapter describes:

- [Uninstalling Cisco BAC, page 5-1](#)
- [Post-Uninstallation Task, page 5-3](#)

Uninstalling Cisco BAC

This section describes the procedures to uninstall Cisco BAC.

After uninstalling Cisco BAC, manually remove the Data and Database Transaction Logs directories (see the [Post-Uninstallation Task, page 5-3](#)).

Uninstalling from the CLI

This section describes the procedures to uninstall Cisco BAC.

After uninstalling Cisco BAC, manually remove the data and database logs directories. See Post-Uninstallation Task, page 3-68.

To uninstall Cisco BAC from the command line:

Step 1 Log in as *root*.

Step 2 Manually remove the configuration of the Cisco BAC extensions on the Cisco Network Registrar server. You can do this from any server that has nrcmd installed and connectivity with Cisco Network Registrar.

a. To uninstall the Cisco BAC extensions from your Cisco Network Registrar configuration, enter:

```
# NR_HOME/local/usrbin/nrcmd -N admin -P changeme -b <
BPR_HOME/cnr_ep/bin/bpr_cnr_disable_extpts.nrcmd
```

b. To reload your DHCP server, enter:

```
# /etc/init.d/nwreglocal stop
# /etc/init.d/nwreglocal start
```

Alternatively, enter:

```
# NR_HOME/local/usrbin/nrcmd -N admin -P changeme "dhcp reload"
```

c. To remove the Cisco BAC extensions from the Cisco Network Registrar extensions directory, enter:

```
# rm -rf NR_HOME/local/extensions/dhcp/dex/libbprextensions.so
```

Step 3 Manually remove the Cisco Access Registrar extensions on the Cisco Access Registrar server using the below command.

```
rm -rf CAR_HOME/scripts/radius/java/dpeext.jar
```

Step 4 At the CLI prompt, enter:

```
# pkgrm CSCObac
```

The following information appears:

```
The following package is currently installed:
CSCObac  Cisco BAC product
         (sparc) 3.6

Do you want to remove this package? [y,n,?,q] y
```

Step 5 Enter *y*, and press **Enter** to start uninstalling. The following message appears:

```
## Removing installed package instance <CSCObac>

This package contains scripts which will be executed with super-user
permission during the process of removing this package.

Do you want to continue with the removal of this package [y,n,?,q] y
```

Step 6 Enter **y** and press **Enter**.

When uninstalling is complete, the following message appears:

```
Removal of <CSCObac> was successful.
```

Post-Uninstallation Task

After uninstalling Cisco BAC, manually remove the data and database transaction logs directories. To remove these directories:

Step 1 Log in as *root*.

Step 2 Remove the data and the database transaction logs. (The default directory for both is */var/CSCObac*.)

For example, enter:

```
# rm -rf /var/CSCObac
```

The data and the database transaction logs directories are deleted.
