



Post Installation

- Step 1** Install the license or licenses. Collector and the web applications require a MATE license. The WAE Core modules require both a MATE and a WAE license. For information, see the [License Installation](#) chapter.
- Step 2** If you are installing, starting, or upgrading the MATE Live datastore (mld), stop the web server. For more information about the MATE Live datastore, see the *MATE Live Configuration Guide*.
- Stop the web server.

```
service wae-web-server stop
```
 - Install, start, or upgrade MATE Live datastore.
 - Install and start mld server: `mld -action install -size [DSML]`
 - Start mld server: `mld -action start`
 - Upgrade an existing mld server and start it: `mld -action upgrade`
 - Start the web server.

```
service wae-web-server start
```
- Step 3** If you are collecting flow data using `flow_manage` and `flow_get`, you must change the file capabilities for the flow collection server. This applies to all binaries in `$CARIDEN_HOME/lib/ext/pmacct/sbin`. If not, execute this command on all files in this directory.
- Example:** `setcap 'cap_net_bind_service=+ep' $CARIDEN_HOME/lib/ext/pmacct/sbin/*`
- Step 4** Both the `wae-web-server` and the `wae-collector` are automatically started. Others may have been started, depending on how you responded to the installation process. If needed, start other services now. For information, see the [Services](#) chapter.
- Step 5** The licensed features you have determines what needs to be configured. See the [Configurations](#) section for a list of these and pointers where to go for information.

Configurations

The licenses you have govern which of the following configurations are required after having installed the product.

- Configure the FlexNet Publisher license server—Applicable if administering floating licenses to MATE Design users. For information, see the [MATE Design Floating License Server](#) chapter.
- Configure the WAE platform—For information, see the *WAE Platform Configuration Guide*.
 - Configure the Collector module to collect network data and traffic. You can configure collection either using the Collector UI or using snapshot configuration files.
 - Configure other WAE platform modules, including the Deployer module.
- Configure MATE Live—For information, see the *MATE Live Configuration Guide*.
 - Install and configure the datastore—Applicable if using MATE Live Explore and Analytics components.
 - Configure MATE Live to collect the data from Collector—Applicable if using both MATE Live and Collector.
 - Customize MATE Live application for its users—Applicable if you are the administrator of MATE Live.
- Customize the MATE Design Archive application for its users—For information, see the *MATE Design Archive User and Administration Guide*.
- Configure system-wide parameters for MATE Live and MATE Design Archive users—For information, see the *System Administration Guide*.
 - Configure users and their roles.
 - If applicable, configure access to an LDAP server and mappings between LDAP groups and MATE roles.
 - Configure access to the SMTP server used for emailing MATE Live reports.
- Enhance network visualization—Lay out the network topology for the plan file template used in the MATE Live and MATE Design Archive applications. For information, see the *MATE Visualization Guide*.