



## G Commands

---

This chapter describes the Cisco NX-OS Multiprotocol Label Switching commands that begin with G.

# graceful-restart

To configure the graceful restart timer, use the **graceful-restart** command. To return to the default setting, use the **no** form of this command.

```
graceful-restart [timers { forwarding-holding seconds | max-recovery seconds | neighbor-liveness seconds }]
```

```
no graceful-restart [timers { forwarding-holding seconds | max-recovery seconds | neighbor-liveness seconds }]
```

Syntax Description	timers	(Optional) Specifies VPN routing.
	<b>forwarding-holding</b> <i>seconds</i>	Specifies the forwarding state holding time. The range is from 30 to 600 seconds.
	<b>max-recovery</b> <i>seconds</i>	Specifies the maximum recovery time. The range is from 15 to 600 seconds.
	<b>neighbor-liveness</b> <i>seconds</i>	Specifies the neighbor lifetime. The range is from 5 to 300 seconds.

**Defaults** Enable

**Command Modes** LDP configuration mode

**Supported User Roles** network-admin  
vdc-admin

Command History	Release	Modification
	5.2(1)	This command was introduced.

**Usage Guidelines** You must configure the MPLS VPN and VRFs before creating VRF-aware static labels. This command requires the MPLS Services license.

**Examples** This example shows how to configure the graceful restart timer:

```
switch(config-ldp)# configure terminal
switch(config)# mpls ldp configuration
switch(config-ldp)# graceful-restart timers forwarding-holding 30
switch(config-ldp)#
```

**Related Commands**

<b>Command</b>	<b>Description</b>
<b>mpls ldp configuration</b>	Configures the Multiprotocol Label Switching (MPLS) Label Distribution Protocol (LDP).

