



O Commands

This chapter describes the Cisco NX-OS system management commands that begin with the letter O.

■ **option exporter-stats timeout**

option exporter-stats timeout

To configure the NetFlow exporter resend timer, use the **option exporter-stats timeout** command. To remove the NetFlow exporter resend timer, use the **no** form of this command.

option exporter-stats timeout *time*

no option exporter-stats timeout

Syntax Description	<i>time</i> Time in seconds. The range is from 1 to 86400.				
Defaults	None				
Command Modes	NetFlow exporter version 9 configuration (config-flow-exporter-version-9)				
SupportedUserRoles	network-admin vdc-admin				
Command History	<table border="1"> <thead> <tr> <th>Release</th><th>Modification</th></tr> </thead> <tbody> <tr> <td>4.0(1)</td><td>This command was introduced.</td></tr> </tbody> </table>	Release	Modification	4.0(1)	This command was introduced.
Release	Modification				
4.0(1)	This command was introduced.				
Usage Guidelines	This command does not require a license.				
Examples	<p>This example shows how to configure the NetFlow exporter resend timer:</p> <pre>switch(config)# flow exporter Custom-Flow-Exporter-1 switch(config-flow-exporter)# version 9 switch(config-flow-exporter-version-9)# option exporter-stats timeout 1200 switch(config-flow-exporter-version-9)# </pre> <p>This example shows how to remove the NetFlow exporter resend timer configuration:</p> <pre>switch(config-flow-exporter-version-9)# no option exporter-stats timeout switch(config-flow-exporter-version-9)# </pre>				
Related Commands	<table border="1"> <thead> <tr> <th>Command</th><th>Description</th></tr> </thead> <tbody> <tr> <td>show flow exporter</td><td>Displays information about NetFlow exporters.</td></tr> </tbody> </table>	Command	Description	show flow exporter	Displays information about NetFlow exporters.
Command	Description				
show flow exporter	Displays information about NetFlow exporters.				

option interface-table timeout

To configure the NetFlow exporter interface-table timer, use the **option interface-table timeout** command. To remove the interface-table timer, use the **no** form of this command.

option interface-table timeout *time*

no option interface-table timeout [*time*]

Syntax Description	<i>time</i> Time in seconds. The range is from 1 to 86400.				
Defaults	None				
Command Modes	NetFlow exporter version 9 configuration (config-flow-exporter-version-9)				
SupportedUserRoles	network-admin vdc-admin				
Command History	<table border="1"> <thead> <tr> <th>Release</th><th>Modification</th></tr> </thead> <tbody> <tr> <td>4.0(1)</td><td>This command was introduced.</td></tr> </tbody> </table>	Release	Modification	4.0(1)	This command was introduced.
Release	Modification				
4.0(1)	This command was introduced.				
Usage Guidelines	This command does not require a license.				
Examples	<p>This example shows how to configure the NetFlow exporter interface-table timer:</p> <pre>switch(config)# flow exporter Custom-Flow-Exporter-1 switch(config-flow-exporter)# version 9 switch(config-flow-exporter-version-9)# option interface-table timeout 1200 switch(config-flow-exporter-version-9)# </pre> <p>This example shows how to remove the NetFlow exporter interface-table timer configuration:</p> <pre>switch(config-flow-exporter-version-9)# no option interface-table timeout</pre>				
Related Commands	<table border="1"> <thead> <tr> <th>Command</th><th>Description</th></tr> </thead> <tbody> <tr> <td>show flow exporter</td><td>Displays information about the NetFlow exporters.</td></tr> </tbody> </table>	Command	Description	show flow exporter	Displays information about the NetFlow exporters.
Command	Description				
show flow exporter	Displays information about the NetFlow exporters.				

 ■ **option sampler-table timeout**

option sampler-table timeout

To configure the NetFlow exporter sampler-table timer, use the **option sampler-table timeout** command. To remove the sampler-table timer, use the **no** form of this command.

option sampler-table timeout *time*

no option sampler-table timeout [*time*]

Syntax Description	<i>time</i> Time in seconds. The range is from 1 to 86400.				
Defaults	None				
Command Modes	NetFlow exporter version 9 configuration (config-flow-exporter-version-9)				
SupportedUserRoles	network-admin vdc-admin				
Command History	<table border="1"> <thead> <tr> <th>Release</th><th>Modification</th></tr> </thead> <tbody> <tr> <td>4.0(1)</td><td>This command was introduced.</td></tr> </tbody> </table>	Release	Modification	4.0(1)	This command was introduced.
Release	Modification				
4.0(1)	This command was introduced.				
Usage Guidelines	This command does not require a license.				
Examples	<p>This example shows how to configure the NetFlow exporter sampler-table timer:</p> <pre>switch(config)# flow exporter Custom-Flow-Exporter-1 switch(config-flow-exporter)# version 9 switch(config-flow-exporter-version-9)# option sampler-table timeout 1200 switch(config-flow-exporter-version-9)# </pre> <p>This example shows how to remove the sampler-table timer configuration:</p> <pre>switch(config)# no option sampler-table timeout switch(config)# </pre>				
Related Commands	<table border="1"> <thead> <tr> <th>Command</th><th>Description</th></tr> </thead> <tbody> <tr> <td>show flow exporter</td><td>Displays information about NetFlow exporters.</td></tr> </tbody> </table>	Command	Description	show flow exporter	Displays information about NetFlow exporters.
Command	Description				
show flow exporter	Displays information about NetFlow exporters.				