



# Installing the Cisco VSG

---

This chapter contains the following sections:

- [Information About the Cisco VSG, page 1](#)
- [Prerequisites for Installing the Cisco VSG Software, page 3](#)
- [Obtaining the Cisco VSG Software, page 3](#)
- [Installing the Cisco VSG Software, page 4](#)
- [Configuring Initial Settings, page 10](#)
- [Verifying the Cisco VSG Configuration, page 12](#)
- [Where to Go Next, page 13](#)

## Information About the Cisco VSG

This section describes how to install and complete the basic configuration of the Cisco VSG for VMware vSphere software.

- [Host and VM Requirements, on page 1](#)
- [Cisco VSG and Supported Cisco Nexus 1000V Series Device Terminology, on page 2](#)

## Host and VM Requirements

The Cisco VSG has the following requirements:

- ESX or ESXi platform running VMware software release 4.1, 5.0, or 5.1 and requiring a minimum of 4-GB physical RAM to host a Cisco VSG VM
- Virtual Machine (VM)
  - 32-bit VM is required and “Other 2.6.x (32-bit) Linux” is a recommended VM type.
  - 2 processors (1 processor is optional.)
  - 2-GB RAM

- 3 NICs (1 of type VMXNET3 and 2 of type E1000)
  - Minimum 3-GB SCSI hard disk with LSI Logic Parallel adapter (default)
  - Minimum CPU speed of 1 GHz
- There is no dependency on the VM hardware version, so the VM hardware version can be upgraded if required.

## Cisco VSG and Supported Cisco Nexus 1000V Series Device Terminology

The following table lists the terminology is used in the Cisco VSG implementation.

Term	Description
Distributed Virtual Switch (DVS)	Logical switch that spans one or more VMware ESX servers. It is controlled by one VSM instance.
ESX/ESXi	Virtualization platform used to create the virtual machines as a set of configuration and disk files. The package that contains the following files used to describe a virtual machine and saved in a single archive using .TAR packaging;that together perform all the functions of a physical machine.
NIC	Network interface card.
Open Virtual Appliance or Application (OVA) file	Package that contains the following files used to describe a virtual machine and saved in a single archive using .TAR packaging: <ul style="list-style-type: none"> <li>• Descriptor file (.OVF)</li> <li>• Manifest (.MF) and certificate files (optional)</li> </ul>
Open Virtual Machine Format (OVF)	Platform-independent method of packaging and distributing Virtual Machines (VMs).
vCenter Server	Service that acts as a central administrator for VMware ESX/ESXi hosts that are connected on a network. vCenter Server directs actions on the VMs and the VM hosts (the ESX/ESXi hosts).
Virtual Ethernet Module (VEM)	Part of the Cisco Nexus 1000V Series switch that switches data traffic. It runs on a VMware ESX host. Up to 64 VEMs are controlled by one VSM. All the VEMs that form a switch domain should be in the same virtual data center as defined by the VMware vCenter Server.
Virtual Machine (VM)	Virtualized x86 PC environment in which a guest operating system and associated application software can run. Multiple VMs can operate on the same host system concurrently.

Term	Description
VMotion	Practice of migrating virtual machines live from server to server. (The Cisco VSGs cannot be moved by VMotion.)
vPath	Component in the Cisco Nexus 1000V Series switch with a VEM that directs the appropriate traffic to the Cisco VSG for policy evaluation. It also acts as fast path and can short circuit part of the traffic without sending it to the Cisco VSG.
Virtual Security Gateway (VSG)	Cisco software that secures virtual networks and provides firewall functions in virtual environments using the Cisco Nexus 1000V Series switch by providing network segmentation.
Virtual Supervisor Module (VSM)	Control software for the Cisco Nexus 1000V Series distributed virtual device that runs on a virtual machine (VM) and is based on Cisco NX-OS.
vSphere Client	User interface that enables users to connect remotely to the vCenter Server or ESX/ESXi from any windows PC. The primary interface for creating, managing, and monitoring VMs, their resources, and their hosts. It also provides console access to VMs.

## Prerequisites for Installing the Cisco VSG Software

The following components must be installed and configured:

- On the Cisco Nexus 1000V Series switch, configure two VLANs, a service VLAN, and an HA VLAN on the switch uplink ports. (The VLAN does not need to be the system VLAN.)
- On the Cisco Nexus 1000V Series switch, configure two port profiles for the Cisco VSG: one for the service VLAN and the other for the HA VLAN. (You will be configuring the Cisco VSG IP address on the Cisco VSG so that the Cisco Nexus 1000V Series switch can communicate with it.)

Details about configuring VLANs and port profiles on the Cisco Nexus 1000V Series switch are available in the Cisco Nexus 1000V Series switch documentation.

## Obtaining the Cisco VSG Software

You can obtain the Cisco VSG software files at this URL:

<http://www.cisco.com/en/US/products/ps13095/index.html>

# Installing the Cisco VSG Software

You can install the Cisco VSG software on a VM by using an open virtual appliance (OVA) file or an ISO image file from the CD. Depending upon the type of file that you are installing, use one of the installation methods described in the following topics

- [Installing the Cisco VSG Software from an OVA File, on page 4](#)
- [Installing the Cisco VSG Software from an ISO File, on page 7](#)

## Installing the Cisco VSG Software from an OVA File

To install the Cisco VSG software from an OVA file, obtain the OVA file and either install it directly from the URL or copy the file to the local disk from where you connect to the vCenter Server.

### Before You Begin

- Specify a name for the new Cisco VSG that is unique within the inventory folder and has up to 80 characters.
- Know the name of the host where the Cisco VSG will be installed in the inventory folder.
- Know the name of the datastore in which the VM files will be stored.
- Know the names of the network port profiles used for the VM.
- Know the Cisco VSG IP address.
- Know the mode in which you will be installing the Cisco VSG:
  - Standalone
  - HA Primary
  - HA Secondary
  - Manual Installation

## SUMMARY STEPS

1. Choose the host on which to deploy the Cisco VSG VM.
2. Choose **File > Deploy OVF Template**. The **Deploy OVF Template—Source** window opens.
3. In the **Deploy OVF Template—Source** window, do the following:
4. In the **Deploy OVF Template—OVF Template Details** window, review the product information including the size of the file and the VM disk.
5. Click **Next**.
6. In the **Deploy OVF Template—End User License Agreement** window, do the following:
7. In the **Deploy OVF Template—Name and Location** window, do the following:
8. In the **Deploy OVF Template—Deployment Configuration** window, do the following:
9. In the **Disk Format** dialog box, choose the radio button for the selected format and click **Next**. The **Host or Cluster** window opens.
10. In the **Host or Cluster** window, choose the host where the Cisco VSG will be installed.
11. Click **Next**. The **Datastore** dialog box opens.
12. From the **Select a datastore** field in which to store the VM files pane, choose your datastore.
13. Click **Next**. The **Network Mapping** dialog box opens.
14. Click the drop-down arrows for Data (Service), Management, and HA to associate port profiles.
15. Click **Next**. The **Deploy OVF Template—Properties** window opens.
16. In the **Deploy OVF Template—Properties** window, do the following:
17. Click **Next**. The **Ready to Complete** window opens.
18. In the **Ready to Complete** window, review the deployment settings information.
19. Click **Finish**. The **Deploying Nexus 1000VSG** dialog box opens.
20. Wait and click **Close** after the progress indicator shows that the deployment is completed successfully.
21. Power on the Cisco VSG VM.
22. If you chose the Standalone mode for installation earlier, you now see the Cisco VSG login prompt. Log in with your Cisco VSG administration password. You may now proceed with configuring the Cisco Virtual Security Gateway. For details, see the *Cisco Virtual Security Gateway for Nexus 1000V Series Switch Configuration Guide*.
23. If you chose the manual installation in the Configuration field earlier, see [Configuring Initial Settings, on page 10](#) to configure the initial settings on the Cisco VSG.

## DETAILED STEPS

- 
- Step 1** Choose the host on which to deploy the Cisco VSG VM.
- Step 2** Choose **File > Deploy OVF Template**. The **Deploy OVF Template—Source** window opens.
- Step 3** In the **Deploy OVF Template—Source** window, do the following:
- a) Browse to the path to the Cisco VSG OVA file in the **Deploy from a file or URL** field.

b) Click **Next**. The **Deploy OVF Template—OVF Template Details** window opens.

**Step 4** In the **Deploy OVF Template—OVF Template Details** window, review the product information including the size of the file and the VM disk.

**Step 5** Click **Next**.

**Step 6** In the **Deploy OVF Template—End User License Agreement** window, do the following:

- a) Review the end user license agreement and click **Accept**.
- b) Click **Next**. The **Name and Location** window.

**Step 7** In the **Deploy OVF Template—Name and Location** window, do the following:

- a) In the **Name** field, enter a name for the Cisco VSG that is unique within the inventory folder and has up to 80 characters.
- b) In the **Inventory Location** pane, choose the location that you would like to use for hosting the Cisco VSG.
- c) Click **Next**. The **Deploy OVF Template—Deployment Configuration** window opens.

**Step 8** In the **Deploy OVF Template—Deployment Configuration** window, do the following:

- a) From the **Configuration** drop-down list, choose **Standalone**.
- b) Click **Next**. The **Disk Format** dialog box opens.

**Note** The Standalone Installation for this document is an example in this publication. If you chose Manual Installation mode, you would choose the default values for the following steps. In Standalone mode, be sure to fill in all the fields indicated (they will be indicated on the GUI with red type).

**Step 9** In the **Disk Format** dialog box, choose the radio button for the selected format and click **Next**. The **Host or Cluster** window opens.

**Step 10** In the **Host or Cluster** window, choose the host where the Cisco VSG will be installed.

**Step 11** Click **Next**. The **Datastore** dialog box opens.

**Step 12** From the **Select a datastore** field in which to store the VM files pane, choose your datastore.

**Step 13** Click **Next**. The **Network Mapping** dialog box opens.

**Step 14** Click the drop-down arrows for Data (Service), Management, and HA to associate port profiles.

**Step 15** Click **Next**. The **Deploy OVF Template—Properties** window opens.

**Step 16** In the **Deploy OVF Template—Properties** window, do the following:

- a) In the **HaId** field, enter the high-availability identification number for a Cisco VSG pair (value from 1 through 4095).
- b) In the **Password** field, enter a password that contains at least one uppercase letter, one lowercase letter, and one number.
- c) In the **ManagementIPv4** field, enter the IP address for the Cisco VSG.
- d) In the **ManagementIPv4 Subnet** field, enter the subnet mask.
- e) In the **Gateway** field, enter the gateway name.
- f) In the **VnmcIPv4** field, enter the IP address of the Cisco VNMC.
- g) In the **SharedSecret** field, enter the shared secret password defined during the Cisco VNMC installation.
- h) In the **ImageName** field, enter the VSG VNM-PA image name (vnmc-vsgpa.2.1.1b.bin).

**Note** In the following step, make sure that red text messages do not appear before you click **Next**. If you do not want to enter valid information in the red-indicated fields, use null values to fill those fields. If those fields are left empty or filled with invalid null values, the application does not power on. Ignore the VNMC Restore fields.

**Step 17** Click **Next**. The **Ready to Complete** window opens.

**Step 18** In the **Ready to Complete** window, review the deployment settings information.

**Note** Review the IP/mask/gateway information carefully because any discrepancies might cause the VM to have bootup issues.

- Step 19** Click **Finish**. The **Deploying Nexus 1000VSG** dialog box opens. The progress bar in the **Deploying Nexus 1000VSG** dialog box shows how much of the deployment task is completed before the Cisco VNMC is deployed.
- Step 20** Wait and click **Close** after the progress indicator shows that the deployment is completed successfully.
- Step 21** Power on the Cisco VSG VM.
- Step 22** If you chose the Standalone mode for installation earlier, you now see the Cisco VSG login prompt. Log in with your Cisco VSG administration password. You may now proceed with configuring the Cisco Virtual Security Gateway. For details, see the *Cisco Virtual Security Gateway for Nexus 1000V Series Switch Configuration Guide*.
- Step 23** If you chose the manual installation in the Configuration field earlier, see [Configuring Initial Settings, on page 10](#) to configure the initial settings on the Cisco VSG.
- Note** If you are installing high availability (HA), you must configure the software on the primary Cisco VSG before installing the software on the secondary Cisco VSG.
- 

## Installing the Cisco VSG Software from an ISO File

You can install the Cisco VSG from an ISO file.

### Before You Begin

- Specify a name for the new Cisco VSG that is unique within the inventory folder and has up to 80 characters.
- Know the name of the host where the Cisco VSG will be installed in the inventory folder.
- Know the name of the datastore in which the VM files will be stored.
- Know the names of the network port profiles used for the VM.
- Know the Cisco VSG IP address.

## SUMMARY STEPS

1. Upload the Cisco Virtual Security Gateway ISO image to the vCenter datastore.
2. From the data center in the vSphere Client menu, choose your ESX host where you want to install the Cisco VSG and choose **New Virtual Machine**. The **Create New Virtual Machine** dialog box opens.
3. In the **Create New Virtual Machine** dialog box, do the following:
4. In the **Create New Virtual Machine** dialog box, do the following:
5. In the **Datastore** dialog box, choose your datastore from the **Select a datastore**. Click **Next**.
6. In the **Virtual Machine Version** dialog box, click the **Virtual Machine Version**. The **Guest Operating System** dialog box opens.
7. In the **Guest Operating System** dialog box, do the following:
8. For CPUs, choose 1 socket with 2 cores or 2 sockets each with one core. Click **Next**.
9. In the **Memory** dialog box, choose **2 GB** memory size and click **Next**. The **Create Network Connectors** dialog box opens.
10. In the **Create Network Connectors** dialog box, do the following:
11. Click **Next**. The **SCSI Controller** dialog box opens.
12. Click **Next**. The **Select a Disk** dialog box opens.
13. Click **Next**. The **Create a Disk** dialog box opens.
14. Click **Next**. The **Advanced Options** dialog box opens.
15. Click **Next**. The **Ready to Complete** dialog box opens.
16. Review your settings in the **Settings for the new virtual machine** area.
17. Check the **Edit the virtual machine before completion** check box and click **Continue** to open a dialog box with the device details.
18. In the Work pane, choose your **New CD/DVD (adding)** in the **Hardware** area.
19. Click **Datastore ISO File**, and select your ISO file from the drop-down list.
20. In the work pane, check the **Connect at power on** check box and click **Finish**. The **Summary tab** window opens.
21. From the **vSphere Client** menu, choose your recently installed VM.
22. In the work pane, click **Power on the virtual machine**.
23. Click the **Console** tab to view the VM console. Wait for the Install Virtual Firewall and bring up the new image to boot.

## DETAILED STEPS

- 
- Step 1** Upload the Cisco Virtual Security Gateway ISO image to the vCenter datastore.
- Step 2** From the data center in the vSphere Client menu, choose your ESX host where you want to install the Cisco VSG and choose **New Virtual Machine**. The **Create New Virtual Machine** dialog box opens.  
For VM requirements, see the [Host and VM Requirements, on page 1](#).  
For detailed information about how to create a VM, see the VMware documentation.
- Step 3** In the **Create New Virtual Machine** dialog box, do the following:
- a) Click **Custom** to create a virtual machine.



b) Click **Next**.

- Step 4** In the **Create New Virtual Machine** dialog box, do the following:
- In the **Name** field, add a name for the Cisco VSG.  
The Cisco VSG name must be a unique name within the inventory folder and should be up to 80 characters.
  - In the **Inventory Location** field, choose your data center and click **Next**. The **Datastore** dialog box opens.
- Step 5** In the **Datastore** dialog box, choose your datastore from the **Select a datastore**. Click **Next**.
- Step 6** In the **Virtual Machine Version** dialog box, click the **Virtual Machine Version**. The **Guest Operating System** dialog box opens.
- Note** Keep the selected virtual machine version.
- Step 7** In the **Guest Operating System** dialog box, do the following:
- Click the **Linux** radio button.
  - In the **Version** field, choose **Other 2.6x Linux (32-bit)** from the drop-down list and click **Next**. The **CPUs** dialog box opens.
- Step 8** For CPUs, choose 1 socket with 2 cores or 2 sockets each with one core. Click **Next**.  
By default, the Cisco VSG virtual machine deployed with OVA has only one vCPU. You can choose 2 vCPUs. For an older version of the ESX hosts, you can directly select the number of vCPUs. The **Memory** dialog box opens.
- Step 9** In the **Memory** dialog box, choose **2 GB** memory size and click **Next**. The **Create Network Connectors** dialog box opens.
- Step 10** In the **Create Network Connectors** dialog box, do the following:
- In the **How many NICs do you want to connect?** field, choose **3** from the drop-down list.
  - In the Network area, choose **service**, **management**, and **HA** port profiles in that sequence for the NIC 1, NIC 2, and NIC 3 from the drop-down list. Choose **VMXNET3** for the adapter type for NIC 1. Choose **E1000** for the adapter type for NIC 2 and NIC 3.
- Step 11** Click **Next**. The **SCSI Controller** dialog box opens.  
The radio button for the default SCSI controller is chosen.
- Step 12** Click **Next**. The **Select a Disk** dialog box opens.  
The radio button for the default disk is chosen.
- Step 13** Click **Next**. The **Create a Disk** dialog box opens.  
The default virtual disk size and policy is chosen.
- Step 14** Click **Next**. The **Advanced Options** dialog box opens.  
The default options are chosen.
- Step 15** Click **Next**. The **Ready to Complete** dialog box opens.
- Step 16** Review your settings in the **Settings for the new virtual machine** area.
- Step 17** Check the **Edit the virtual machine before completion** check box and click **Continue** to open a dialog box with the device details.
- Step 18** In the Work pane, choose your **New CD/DVD (adding)** in the **Hardware** area.
- Step 19** Click **Datastore ISO File**, and select your ISO file from the drop-down list.
- Step 20** In the work pane, check the **Connect at power on** check box and click **Finish**. The **Summary tab** window opens.

The **Create virtual machine status** completes.

- Step 21** From the **vSphere Client** menu, choose your recently installed VM.
- Step 22** In the work pane, click **Power on the virtual machine**.
- Step 23** Click the **Console** tab to view the VM console. Wait for the Install Virtual Firewall and bring up the new image to boot. See the **Configuring Initial Settings** section to configure the initial settings on the Cisco VSG.
- Note** To allocate additional RAM, right-click the **VM** icon to power off the VM and then choose **Power > Power Off** from the dialog box. After the VM is powered down, edit the configuration settings on the VM for controlling memory resources.

## Configuring Initial Settings

This section describes how to configure the initial settings on the Cisco VSG and configure a standby Cisco VSG with its initial settings. For configuring a standby Cisco VSG, see [Configuring Initial Settings on a Standby Cisco VSG, on page 12](#) section.

When you power on the Cisco VSG for the first time, depending on which mode you used to install your Cisco VSG, you might be prompted to log in to the Cisco VSG to configure initial settings at the console on your vSphere Client. For details about installing Cisco VSG, see [Installing the Cisco VSG Software, on page 4](#) in this chapter.

### Before You Begin

The following table determines if you must configure the initial settings as described in this section.

Your Cisco Virtual Security Gateway Software Installation Method	Do You Need to Proceed with “Configuring Initial Settings”?
Installing an OVA file and choosing <b>Manually Configure Nexus 1000 VSG</b> in the configuration field during installation.	Yes. Proceed with configuring initial settings described in this section.
Installing an OVA file and choosing any of the options other than the manual method in the configuration field during installation.	No. You have already configured the initial settings during the OVA file installation.
Installing an ISO file.	Yes. Proceed with configuring initial settings described in this section.

- Step 1** Navigate to the **Console** tab in the VM.

Cisco Nexus 1000V Series switch opens the **Console** window and boots the Cisco VSG software.

**Step 2** At the `Enter the password for "admin"` prompt, enter the password for the admin account and press **Enter**.

**Step 3** At the prompt, confirm the admin password and press **Enter**.

**Step 4** At the `Enter HA role[standalone/primary/secondary]` prompt, enter the HA role you want to use and press **Enter**.

This can be one of the following:

- standalone
- primary
- secondary

**Step 5** At the `Enter the ha id(1-4095)` prompt, enter the HA ID for the pair and press **Enter**.

**Note** If you entered secondary in the earlier step, the HA ID for this system must be the same as the HA ID for the primary system.

**Step 6** If you want to perform basic system configuration, at the `Would you like to enter the basic configuration dialog (yes/no)` prompt, enter **yes** and press **Enter**, then complete the following steps.

a) At the `Create another login account (yes/no) [n]` prompt, do one of the following:

- To create a second login account, enter **yes** and press **Enter**.
- Press **Enter**.

b) (Optional) At the `Configure read-only SNMP community string (yes/no) [n]` prompt, do one of the following:

- To create an SNMP community string, enter **yes** and press **Enter**.
- Press **Enter**.

c) At the `Enter the Virtual Security Gateway (VSG) name` prompt, enter **VSG-demo** and press **Enter**.

**Step 7** At the `Continue with Out-of-band (mgmt0) management configuration? (yes/no) [y]` prompt, enter **yes** and press **Enter**.

**Step 8** At the `Mgmt IPv4 address:` prompt, enter **10.10.10.11** and press **Enter**.

**Step 9** At the `Mgmt IPv4 netmask` prompt, enter **255.255.255.0** and press **Enter**.

**Step 10** At the `Configure the default gateway? (yes/no) [y]` prompt, enter **yes** and press **Enter**.

**Step 11** At the `Enable the telnet service? (yes/no) [y]` prompt, enter **no** and press **Enter**.

**Step 12** At the `Enable the telnet service? (yes/no) [y]` prompt, enter **no**.

**Step 13** At the `Configure the ntp server? (yes/no) [n]` prompt, enter **no** and press **Enter**.

The following configuration will be applied:

```
Interface mgmt0
ip address 10.10.10.11 255.255.255.0
no shutdown
vrf context management
ip route 0.0.0.0/10.10.11.1
no telnet server enable
ssh key rsa 768 force
ssh server enable
```

```
no feature http-server
ha-pair id 25
```

- Step 14** At the `Would you like to edit the configuration? (yes/no) [n]` prompt, enter `n` and press **Enter**.
- Step 15** At the `Use this configuration and save it? (yes/no) [y]` prompt, enter `y` and press **Enter**.
- Step 16** At the `VSG login` prompt, enter the name of the admin account you want to use and press **Enter**.  
The default account name is `admin`.
- Step 17** At the `Password` prompt, enter the name of the password for the admin account and press **Enter**.  
You are now at the Cisco VSG node.

## Configuring Initial Settings on a Standby Cisco VSG

You can add a standby Cisco VSG by logging in to the Cisco VSG you have identified as secondary and using the following procedure to configure a standby Cisco VSG with its initial settings.

- Step 1** Navigate to the **Console** tab in the VM.  
Cisco Nexus 1000V Series switch opens the **Console** window and boots the Cisco VSG software.
- Step 2** At the `Enter the password for "admin"` prompt, enter the password for the admin account and press **Enter**.
- Step 3** At the prompt, confirm the admin password and press **Enter**.
- Step 4** At the `Enter HA role[standalone/primary/secondary]` prompt, enter the secondary HA role and press **Enter**.
- Step 5** At the `Enter the ha id(1-4095)` prompt, enter `25` for the HA pair id and press **Enter**.  
**Note** The HA ID uniquely identifies the two Cisco VSGs in an HA pair. If you are configuring Cisco VSGs in an HA pair, make sure that the ID number you provide is identical to the other Cisco VSG in the pair.
- Step 6** At the `VSG login` prompt, enter the name of the admin account you want to use and press **Enter**.  
The default account name is `admin`.
- Step 7** At the `Password` prompt, enter the name of the password for the admin account and press **Enter**.  
You are now at the Cisco VSG node.

## Verifying the Cisco VSG Configuration

To display the Cisco VSG configuration, perform one of the tasks:

Command	Purpose
<code>show interface brief</code>	Displays brief status and interface information.

Command	Purpose
<code>show vsg</code>	Displays the Cisco VSG and system-related information.

This example shows how to verify the Cisco VSG configurations:

```
vsg# show interface brief
```

```
-----  
Port      VRF      Status IP Address      Speed  MTU  
-----  
mgmt0     --       up      10.193.77.217   1000  1500
```

```
vsg# show vsg
```

```
Model: VSG
```

```
HA ID: 3437
```

```
VSG Software Version: 4.2(1)VSG1(1) build [4.2(1)VSG1(0.399)]
```

```
VNMC IP: 10.193.75.73
```

## Where to Go Next

After installing and completing the initial configuration of the Cisco VSG, you can configure firewall policies on the Cisco VSG through the Cisco VNMC.

