



## Member Configuration

---

- [Installation and Configuration for Member Node, on page 1](#)
- [Complete Configuration for Member Node, on page 1](#)

## Installation and Configuration for Member Node



---

**Note** All configured nodes in a cluster must be up and running before you install a new Member node.

---



---

**Note** To add a member node in a Live Data only deployment, see *Live Data Standalone Installation*, in the Cisco Unified Contact Center Enterprise Installation and Upgrade Guide  
<https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-installation-guides-list.html>

---



---

**Note** To add a member node in a IdS only deployment, see *Install Cisco Identity Service Standalone Deployment*, in the Cisco Unified Contact Center Enterprise Features Guide  
<https://www.cisco.com/c/en/us/support/customer-collaboration/unified-contact-center-enterprise/products-feature-guides-list.html>

---

## Complete Configuration for Member Node

### Procedure

---

- Step 1** Install the member node following the steps in *Preparation for Unified Intelligence Center Installation on a Virtual Machine*, under sections:
- *Deploy Unified Intelligence Center Open Virtualization Format/Open Virtual Appliance (OVF/OVA) Template*
  - *Specify Location of Unified Intelligence Center Installable, on page 9*

- *Install Cisco Unified Intelligence Center on Virtual Machine, on page 10*

**Step 2** At the **First Node Configuration Screen**, select **No**.

The First Node Configuration Warning screen opens. This screen advises you that you must configure the server on the first node before you can proceed. You completed this configuration in [Chapter 4](#).

**Step 3** Select **OK** at the screen.

**Step 4** In the **Network Connectivity Test Configuration** screen, you can verify the connection of this node to the first node (the Controller).

**Note** The **Network Connectivity Test Configuration** screen refers to the first node as the *publisher*, in reference to its role in database replication. The first node *publishes* or replicates, the databases to the Member nodes, which are referred to as *subscribers* of the database replication. Select **No** to open the First Node Access Configuration screen.

**Step 5** In the **First Node Access Configuration** screen, enter connection values *for the first node (the Controller)*:

- Host Name *of the Controller*
- IP Address *of the Controller*
- Security Password (enter and confirm)
- Select **OK** to open the SMTP Host Configuration screen.

**Step 6** In the **SMTP Host Configuration** screen, select whether you want to configure an SMTP host to receive platform-level emails; for example, emails about certificate expiration. This field is optional. You configure email for report scheduling in the Administration console.

If	Then
You want to configure an SMTP Host.	Select <b>Yes</b> to open the second SMTP screen. Proceed to Step 7.
You do not want to configure an SMTP Host.	Select <b>No</b> to open the Platform Configuration Confirmation screen. Proceed to Step 8.

**Step 7** In the second **SMTP Host Configuration** screen:

- Enter the hostname or IP address for the SMTP server.
- Select **OK** to open the Platform Configuration Confirmation screen.

**Step 8** In the **Platform Configuration Confirmation** screen:

If	Then
You want to proceed.	Select <b>OK</b> . The installation begins.
You want to revisit screens to modify the configuration.	Select <b>Back</b> .

**Related Topics**

[Define Member Node in Administration Console](#)

