



# Configuring RTP Header Compression

---

**First Published: January 30, 2006**

**Last Updated: March 2, 2009**

Header compression is a mechanism that compresses the header in a packet before the packet is transmitted. RTP header compression reduces network overhead and speeds up the transmission of Real-Time Transport Protocol (RTP) packets.

## Finding Feature Information

For the latest feature information and caveats, see the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the [“Feature Information for Configuring RTP Header Compression” section on page 12](#).

Use Cisco Feature Navigator to find information about platform support and Cisco IOS XE Software image support. To access Cisco Feature Navigator, go to <http://www.cisco.com/go/cfn>. An account on Cisco.com is not required.

## Contents

- [Prerequisites for Configuring RTP Header Compression, page 2](#)
- [Information About Configuring RTP Header Compression, page 2](#)
- [How to Configure RTP Header Compression, page 4](#)
- [Configuration Examples for RTP Header Compression, page 9](#)
- [Additional References, page 10](#)
- [Feature Information for Configuring RTP Header Compression, page 12](#)
- [Glossary, page 13](#)



---

**Americas Headquarters:**

**Cisco Systems, Inc., 170 West Tasman Drive, San Jose, CA 95134-1706 USA**

## Prerequisites for Configuring RTP Header Compression

- Before configuring RTP header compression, read the information in the “[Header Compression](#)” module.
- You must configure RTP header compression on both ends of the network.

## Information About Configuring RTP Header Compression

Before configuring RTP header compression, you should understand the following concepts:

- [Configurable RTP Header-Compression Settings, page 2](#)
- [RTP Header-Compression Keywords, page 2](#)

## Configurable RTP Header-Compression Settings

With RTP header compression, you can configure the maximum size of the compressed header, the maximum time between transmitting full-header packets, and the maximum number of compressed packets between full headers. These settings are configured using the following three commands:

- **ip header-compression max-header**
- **ip header-compression max-time**
- **ip header-compression max-period**

The **ip header-compression max-header** command allows you to define the maximum size of the header of a packet to be compressed. Any packet with an header that exceeds the maximum size is sent uncompressed.

The **ip header-compression max-time** command allows you to specify the maximum time between transmitting full-header packets, and the **ip header-compression max-period** command allows you to specify the maximum number of compressed packets between full headers. With the **ip header-compression max-time** and **ip header-compression max-period** commands, the full-header packet is transmitted at the specified time period or when the maximum number of packets is reached, respectively. The counters for both the time period and the number of packets sent are reset after the full-header packet is sent.

For more information about these commands, see the [Cisco IOS Quality of Service Solutions Command Reference](#).

## RTP Header-Compression Keywords

When you configure RTP header compression, you can specify the circumstances under which the RTP packets are compressed and the format that is used when the packets are compressed. These circumstances and formats are defined by the following keywords:

- **passive**
- **iphc-format**
- **ietf-format**
- **cisco**

These keywords (described below) are available with many of the quality of service (QoS) commands used to configure RTP header compression, such as the **ip rtp header-compression** command. For more information about the **ip rtp header-compression** command, these keywords, and the other QoS commands, see the [Cisco IOS Quality of Service Solutions Command Reference](#).

#### The **passive** Keyword

By default, the **ip rtp header-compression** command compresses outgoing RTP traffic. If you specify the **passive** keyword, outgoing RTP traffic is compressed only if *incoming* RTP traffic on the *same* interface is compressed. If you do not specify the **passive** keyword, *all* outgoing RTP traffic is compressed.

The **passive** keyword is ignored on PPP interfaces.

#### The **iphc-format** Keyword

The **iphc-format** keyword indicates that the IP Header Compression (IPHC) format of header compression will be used. For PPP and HDLC interfaces, when the **iphc-format** keyword is specified, TCP header compression is also enabled. Since both RTP and TCP header compression are enabled, both UDP and TCP packets are compressed.

The **iphc-format** keyword includes checking whether the destination port number is even and is in the ranges of 16,385 to 32,767 (for Cisco audio) or 49,152 to 65,535 (for Cisco video). Valid RTP packets that meet the criteria (that is, the port number is even and is within the specified range) are compressed using the compressed RTP packet format. Otherwise, packets are compressed using the less-efficient compressed non-TCP packet format.

The **iphc-format** keyword is not available for interfaces that use Frame Relay encapsulation.



#### Note

---

The header compression format (in this case, IPHC) must be the same at *both* ends of the network. That is, if you specify the **iphc-format** keyword on the local router, you must also specify the **iphc-format** keyword on the remote router.

---

#### The **ietf-format** Keyword

The **ietf-format** keyword indicates that the Internet Engineering Task Force (IETF) format of header compression will be used. For HDLC interfaces, the **ietf-format** keyword compresses both TCP and UDP packets. UDP and TCP packets are compressed separately. For PPP interfaces, when the **ietf-format** keyword is specified, TCP header compression is also enabled. Since both RTP header compression and TCP header compression are enabled, both UDP packets and TCP packets are compressed.

With the **ietf-format** keyword, any even destination port number higher than 1024 can be used. Valid RTP packets that meet the criteria (that is, the port number is even and is higher than 1024) are compressed using the compressed RTP packet format. Otherwise, packets are compressed using the less-efficient compressed non-TCP packet format.

The **ietf-format** keyword is not available for interfaces that use Frame Relay encapsulation.



#### Note

---

The header compression format (in this case, IETF) must be the same at *both* ends of the network. That is, if you specify the **ietf-format** keyword on the local router, you must also specify the **ietf-format** keyword on the remote router.

---

**The cisco Keyword**

The **cisco** keyword indicates that the Cisco-proprietary or “original” format of header compression will be used.

RTP header-compression using the cisco format supports even-numbered UDP destination ports in the Cisco audio range of 16384 to 32767 or in the video range of 49152 to 65535.

The **cisco** keyword is only available on interfaces that use Frame Relay or HDLC encapsulation.

## How to Configure RTP Header Compression

- [Enabling RTP Header Compression on an Interface, page 4](#) (required)
- [Specifying the Header-Compression Settings, page 5](#) (optional)
- [Changing the Number of Header-Compression Connections, page 6](#) (optional)
- [Displaying Header-Compression Statistics, page 8](#) (optional)

## Enabling RTP Header Compression on an Interface

To enable RTP header compression on an interface, perform the following steps.

### SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface** *type number* [*name-tag*]
4. **encapsulation** *encapsulation-type*
5. **ip address** *ip-address mask* [**secondary**]
6. **ip rtp header-compression** [**passive** | **iphc-format** | **ietf-format** | **cisco**] [**periodic-refresh**]
7. **end**

### DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>  <b>Example:</b> Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
Step 2	<b>configure terminal</b>  <b>Example:</b> Router# configure terminal	Enters global configuration mode.
Step 3	<b>interface</b> <i>type number</i> [ <i>name-tag</i> ]  <b>Example:</b> Router(config)# interface serial0	Configures an interface type and enters interface configuration mode. <ul style="list-style-type: none"> <li>• Enter the interface type and the interface number.</li> </ul>

	Command or Action	Purpose
Step 4	<b>encapsulation</b> <i>encapsulation-type</i>  <b>Example:</b> Router(config-if)# encapsulation ppp	Sets the encapsulation method used by the interface. <ul style="list-style-type: none"> <li>Enter the encapsulation method.</li> </ul>
Step 5	<b>ip address</b> <i>ip-address mask [secondary]</i>  <b>Example:</b> Router(config-if)# ip address 209.165.200.225 255.255.255.224	Sets a primary or secondary IP address for an interface. <ul style="list-style-type: none"> <li>Enter the IP address and mask for the associated IP subnet.</li> </ul>
Step 6	<b>ip rtp header-compression</b> [ <i>passive   iphc-format   ietf-format   cisco</i> ] [ <i>periodic-refresh</i> ]  <b>Example:</b> Router(config-if)# ip rtp header-compression	Enables RTP header compression.
Step 7	<b>end</b>  <b>Example:</b> Router(config-if)# end	(Optional) Exits interface configuration mode.

## Specifying the Header-Compression Settings

With RTP header compression, you can configure the maximum size of the compressed header, the time period for an automatic resend of full-header packets, and the number of packets transmitted before a new full-header packet is sent.

To specify these header-compression settings, perform the following steps.

### SUMMARY STEPS

- enable**
- configure terminal**
- interface** *type number [name-tag]*
- ip header-compression max-header** *max-header-size*  
or  
**ip header-compression max-time** *length-of-time*  
or  
**ip header-compression max-period** *number-of-packets*
- end**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>  <b>Example:</b> Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> <li>Enter your password if prompted.</li> </ul>
Step 2	<b>configure terminal</b>  <b>Example:</b> Router# configure terminal	Enters global configuration mode.
Step 3	<b>interface</b> <i>type number</i> [ <i>name-tag</i> ]  <b>Example:</b> Router(config)# interface serial0	Configures an interface type and enters interface configuration mode. <ul style="list-style-type: none"> <li>Enter the interface type and the interface number.</li> </ul>
Step 4	<b>ip header-compression max-header</b> <i>max-header-size</i>  <b>Example:</b> Router(config-if)# ip header-compression max-header 100	Specifies the maximum size of the compressed IP header. <ul style="list-style-type: none"> <li>Enter the maximum size of the compressed IP header, in bytes.</li> </ul>
	OR	
	<b>ip header-compression max-time</b> <i>length-of-time</i>  <b>Example:</b> Router(config-if)# ip header-compression max-time 30	Specifies the maximum amount of time to wait before the compressed IP header is refreshed. <ul style="list-style-type: none"> <li>Enter the amount of time, in seconds.</li> </ul>
	OR	
	<b>ip header-compression max-period</b> <i>number-of-packets</i>  <b>Example:</b> Router(config-if)# ip header-compression max-period 160	Specifies the maximum number of compressed packets between full headers. <ul style="list-style-type: none"> <li>Enter the maximum number of compressed packets between full headers.</li> </ul>
Step 5	<b>end</b>  <b>Example:</b> Router(config-if)# end	(Optional) Exits interface configuration mode.

## Changing the Number of Header-Compression Connections

For PPP and HDLC interfaces, the default is 16 compression connections.

To change the default number of header-compression connections, perform the following steps.

## Implications of Changing the Number of Header-Compression Connections

Each header-compression connection sets up a compression cache entry, so you are in effect specifying the maximum number of cache entries and the size of the cache. Too few cache entries for the specified interface can lead to degraded performance, and too many cache entries can lead to wasted memory. Choose the number of header-compression connections according to the network requirements.

## Restrictions

### Header-Compression Connections on HDLC Interfaces

For HDLC interfaces, the number of header-compression connections on *both sides* of the network must match. That is, the number configured for use on the local router must match the number configured for use on the remote router.

### Header-Compression Connections on PPP Interfaces

For PPP interfaces, if the header-compression connection numbers on both sides of the network do not match, the number used is “autonegotiated.” That is, any mismatch in the number of header-compression connections between the local router and the remote router will be automatically negotiated to the lower of the two numbers. For example, if the local router is configured to use 128 header-compression connections, and the remote router is configured to use 64 header-compression connections, the negotiated number will be 64.



---

**Note** This autonegotiation function applies to PPP interfaces *only*. For HDLC interfaces, no autonegotiation occurs.

---

## SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **interface** *type number [name-tag]*
4. **ip rtp compression-connections** *number*
5. **end**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>  <b>Example:</b> Router> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"><li>Enter your password if prompted.</li></ul>
Step 2	<b>configure terminal</b>  <b>Example:</b> Router# configure terminal	Enters global configuration mode.
Step 3	<b>interface</b> <i>type number</i> [ <i>name-tag</i> ]  <b>Example:</b> Router(config)# interface serial0	Configures an interface type and enters interface configuration mode. <ul style="list-style-type: none"><li>Enter the interface type and the interface number.</li></ul>
Step 4	<b>ip rtp compression-connections</b> <i>number</i>  <b>Example:</b> Router(config-if)# ip rtp compression-connections 150	Specifies the total number of RTP header-compression connections that can exist on an interface. <ul style="list-style-type: none"><li>Enter the number of compression connections.</li></ul> <b>Note</b> This command can be used for PPP interfaces and HDLC interfaces.
Step 5	<b>end</b>  <b>Example:</b> Router(config-if)# end	(Optional) Exits interface configuration mode.

## Displaying Header-Compression Statistics

You can display header-compression statistics, such as the number of packets sent, received, and compressed, by using the **show ip rtp header-compression** command.

To display header-compression statistics, perform the following steps.

## SUMMARY STEPS

- enable**
- show ip rtp header-compression** [*interface-type interface-number*]
- end**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>  <b>Example:</b> Router> enable	Enables privileged EXEC mode.  • Enter your password if prompted.
Step 2	<b>show ip rtp header-compression</b> [ <i>interface-type</i> <i>interface-number</i> ]  <b>Example:</b> Router# show ip rtp header-compression	Displays RTP header-compression statistics for one or all interfaces.
Step 3	<b>end</b>  <b>Example:</b> Router# end	(Optional) Exits privileged EXEC mode.

## Configuration Examples for RTP Header Compression

- [Example: Enabling RTP Header Compression on an Interface, page 9](#)
- [Example: Specifying the Header-Compression Settings, page 9](#)
- [Example: Changing the Number of Header-Compression Connections, page 10](#)
- [Example: Displaying Header-Compression Statistics, page 10](#)

### Example: Enabling RTP Header Compression on an Interface

In the following example, RTP header compression is enabled on serial interface 0.

```
Router> enable
Router# configure terminal
Router(config)# interface serial0
Router(config-if)# encapsulation ppp
Router(config-if)# ip address 209.165.200.225 255.255.255.224
Router(config-if)# ip rtp header-compression
Router(config-if)# end
```

### Example: Specifying the Header-Compression Settings

In the following example, the maximum size of the compressed IP header (100 bytes) has been specified by using the **ip header-compression max-header** command.

```
Router> enable
Router# configure terminal
Router(config)# interface serial0
Router(config-if)# ip header-compression max-header 100
Router(config-if)# end
```

## Example: Changing the Number of Header-Compression Connections

In the following example, the number of header-compression connections has been changed to 150 by using the **ip rtp compression-connections** command.

```
Router> enable
Router# configure terminal
Router(config)# interface serial0
Router(config-if)# ip rtp compression-connections 150
Router(config-if)# end
```

## Example: Displaying Header-Compression Statistics

You can use the **show ip rtp header-compression** command to display header-compression statistics such as the number of packets received, sent, and compressed. The following is sample output from the **show ip rtp header-compression** command.

```
Router# show ip rtp header-compression serial0

RTP/UDP/IP header compression statistics:
Interface Serial0 (compression on, IETF)
  Rcvd:   1473 total, 1452 compressed, 0 errors, 0 status msgs
         0 dropped, 0 buffer copies, 0 buffer failures
  Sent:   1234 total, 1216 compressed, 0 status msgs, 379 not predicted
         41995 bytes saved, 24755 bytes sent
         2.69 efficiency improvement factor
  Connect: 16 rx slots, 16 tx slots,
          6 misses, 0 collisions, 0 negative cache hits, 13 free contexts
          99% hit ratio, five minute miss rate 0 misses/sec, 0 max
```

## Additional References

The following sections provide references related to configuring RTP header compression.

### Related Documents

Related Topic	Document Title
Cisco IOS commands	<a href="#">Cisco IOS Master Commands List, All Releases</a>
QoS commands: complete command syntax, command modes, command history, defaults, usage guidelines, and examples	<a href="#">Cisco IOS Quality of Service Solutions Command Reference</a>
Header compression overview	“Header Compression” module

### Standards

Standard	Title
No new or modified standards are supported, and support for existing standards has not been modified.	—

## MIBs

MIB	MIBs Link
No new or modified MIBs are supported, and support for existing MIBs has not been modified.	To locate and download MIBs for selected platforms, Cisco IOS XE Software releases, and feature sets, use Cisco MIB Locator found at the following URL: <a href="http://www.cisco.com/go/mibs">http://www.cisco.com/go/mibs</a>

## RFCs

RFC	Title
RFC 2507	<i>IP Header Compression</i>
RFC 2508	<i>Compressing IP/UDP/RTP Headers for Low-Speed Serial Links</i>
RFC 3544	<i>IP Header Compression over PPP</i>

## Technical Assistance

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	<a href="http://www.cisco.com/cisco/web/support/index.html">http://www.cisco.com/cisco/web/support/index.html</a>

# Feature Information for Configuring RTP Header Compression

Table 1 lists the features in this module and provides links to specific configuration information.

Use Cisco Feature Navigator to find information about platform support and software image support. Cisco Feature Navigator enables you to determine which Cisco IOS XE Software images support a specific software release, feature set, or platform. To access Cisco Feature Navigator, go to <http://www.cisco.com/go/cfn>. An account on Cisco.com is not required.


**Note**

Table 1 lists only the Cisco IOS XE Software release that introduced support for a given feature in a given Cisco IOS XE Software release train. Unless noted otherwise, subsequent releases of that Cisco IOS XE Software release train also support that feature.

**Table 1** Feature Information for Configuring RTP Header Compression

Feature Name	Releases	Feature Information
Express RTP and TCP Header Compression	Cisco IOS XE Release 2.1	<p>This feature was introduced on Cisco ASR 1000 Series Routers.</p> <p>The following section provides information about this feature:</p> <ul style="list-style-type: none"> <li>• <a href="#">Information About Configuring RTP Header Compression, page 2</a></li> <li>• <a href="#">How to Configure RTP Header Compression, page 4</a></li> </ul>
RTP Header Compression	Cisco IOS XE Release 2.1	<p>This feature was introduced on Cisco ASR 1000 Series Routers.</p> <p>The following section provides information about this feature:</p> <ul style="list-style-type: none"> <li>• <a href="#">Information About Configuring RTP Header Compression, page 2</a></li> <li>• <a href="#">How to Configure RTP Header Compression, page 4</a></li> </ul>

# Glossary

**compression**—The running of a data set through an algorithm that reduces the space required to store the data set or the bandwidth required to transmit the data set.

**context**—The state that the compressor uses to compress a header and that the decompressor uses to decompress a header. The context is the uncompressed version of the last header sent and includes other information used to compress and decompress the packet.

**context-state packet**—A special packet sent from the decompressor to the compressor to communicate a list of (TCP or NON\_TCP/RTP) context identifiers (CIDs) for which synchronization has been lost. This packet is sent only over a single link, so it requires no IP header.

**DLCI**—data-link connection identifier. A value that specifies a permanent virtual circuit (PVC) or switched virtual circuit (SVC) in a Frame Relay network. In the basic Frame Relay specification, DLCIs are locally significant (connected devices might use different values to specify the same connection). In the Local Management Interface (LMI) extended specification, DLCIs are globally significant (DLCIs specify individual end devices).

**encapsulation**—A method of wrapping data in a particular protocol header. For example, Ethernet data is wrapped in a specific Ethernet header before network transit. Also, when dissimilar networks are bridged, the entire frame from one network is simply placed in the header used by the data link layer protocol of the other network.

**full header (header refresh)**—An uncompressed header that updates or refreshes the context for a packet stream. It carries a CID that will be used to identify the context. Full headers for non-TCP packet streams also carry the generation of the context that they update or refresh.

**HDLC**—High-Level Data Link Control. A bit-oriented synchronous data link layer protocol developed by the International Organization for Standardization (ISO). Derived from Synchronous Data Link Control (SDLC), HDLC specifies a data encapsulation method on synchronous serial links using frame characters and checksums.

**header**—A chain of subheaders.

**IETF**—Internet Engineering Task Force. A task force that consists of over 80 working groups responsible for developing Internet standards.

**IPHC**—IP Header Compression. A protocol capable of compressing both TCP and UDP headers.

**ISDN**—Integrated Services Digital Network. A communication protocol offered by telephone companies that permits telephone networks to carry data, voice, and other source traffic.

**lossy serial links**—Links in a network that are prone to lose packets.

**packet stream**—The sequence of packets whose headers are similar and share context. For example, headers in an RTP packet stream have the same source and final destination address and the same port numbers in the RTP header.

**PPP**—Point-to-Point Protocol. A protocol that provides router-to-router and host-to-network connections over synchronous and asynchronous circuits.

**regular header**—A normal, uncompressed header. A regular header does not carry a context identifier (CID) or generation association.

**RTP**—Real-Time Transport Protocol. A protocol that is designed to provide end-to-end network transport functions for applications that transmit real-time data, such as audio, video, or simulation data, over unicast or multicast network services. RTP provides such services as payload type identification, sequence numbering, timestamping, and delivery monitoring to real-time applications.

**subheader**—An IPv6 base header, an IPv6 extension header, an IPv4 header, a UDP header, an RTP header, or a TCP header.

Cisco and the Cisco Logo are trademarks of Cisco Systems, Inc. and/or its affiliates in the U.S. and other countries. A listing of Cisco's trademarks can be found at [www.cisco.com/go/trademarks](http://www.cisco.com/go/trademarks). Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1005R)

Any Internet Protocol (IP) addresses used in this document are not intended to be actual addresses. Any examples, command display output, and figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

© 2006–2009 Cisco Systems, Inc. All rights reserved.