



## E Commands

---

This chapter describes the Cisco NX-OS unicast routing commands that begin with the letter E.

### eigrp graceful-restart

To enable graceful restart for the Enhanced Interior Gateway Routing Protocol (EIGRP), use the **eigrp graceful-restart** command. To reset to default, use the **no** form of this command.

**eigrp graceful-restart**

**no eigrp graceful restart**

---

**Syntax Description** This command has no arguments or keywords.

---

**Defaults** Enabled

---

**Command Modes** Address-family configuration  
Router configuration  
Router VRF configuration

---

**SupportedUserRoles** network-admin  
vdc-admin

---

Command History	Release	Modification
	4.0(1)	This command was introduced.
	4.0(3)	Replaced by <b>graceful-restart</b> command.

---

---

**Usage Guidelines** Use the **eigrp graceful-restart** command to allow EIGRP to remain in the data forwarding path through a process restart. This command is the same as the **nsf** command.

***Send document comments to [nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)***

This command requires the Enterprise Services license.

---

**Examples**

The following example shows how to enable graceful restart:

```
switch(config)# router eigrp 1  
switch(config-router)# eigrp graceful-restart
```

---

**Related Commands**

Command	Description
<b>graceful-restart</b>	Enables graceful restart.
<b>timers nsf</b>	Configures timers for nonstop forwarding and graceful restart.

*Send document comments to [nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)*

## eigrp log-neighbor-changes

To enable the logging of changes in Enhanced Interior Gateway Routing Protocol (EIGRP) neighbor adjacencies, use the **eigrp log-neighbor-changes** command. To disable the logging of changes in EIGRP neighbor adjacencies, use the **no** form of this command.

**eigrp log-neighbor-changes**

**no eigrp log-neighbor-changes**

**Syntax Description** This command has no arguments or keywords.

**Command Default** Adjacency changes are logged.

**Command Modes** Address-family configuration  
Router configuration  
Router VRF configuration

**Supported User Roles** network-admin  
vdc-admin

Command History	Release	Modification
	4.0(1)	This command was introduced.
	4.0(3)	Replaced by <b>log-neighbor-changes</b> command.

**Usage Guidelines** Use the **eigrp log-neighbor-changes** command to log neighbor adjacency changes to monitor the stability of the routing system and to detect problems. Logging is enabled by default. To disable the logging of neighbor adjacency changes, use the **no** form of this command.

This command requires the Enterprise Services license.

**Examples** The following example shows how to enable logging of neighbor changes for EIGRP process 209:

```
switch(config)# router eigrp 209
switch(config-router)# eigrp log-neighbor-changes
```

Related Commands	Command	Description
	<b>log-neighbor-changes</b>	Enables logging of EIGRP neighbor changes.
	<b>log-neighbor-warnings</b>	Enables logging of EIGRP neighbor warnings.
	<b>log-adjacency-changes</b>	Enables logging of EIGRP adjacency state changes.

[Send document comments to nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)

## eigrp log-neighbor-warnings

To enable the logging of Enhanced Interior Gateway Routing Protocol (EIGRP) neighbor warning messages, use the **eigrp log-neighbor-warnings** command. To disable the logging of EIGRP neighbor warning messages, use the **no** form of this command.

**eigrp log-neighbor-warnings** [*seconds*]

**no eigrp log-neighbor-warnings**

<b>Syntax Description</b>	<i>seconds</i>	(Optional) Time interval (in seconds) between repeated neighbor warning messages. The range of seconds is from 1 to 65535.
---------------------------	----------------	----------------------------------------------------------------------------------------------------------------------------

**Command Default** Neighbor warning messages are logged.

**Command Modes** Address-family configuration  
Router configuration  
Router VRF configuration

**SupportedUserRoles** network-admin  
vdc-admin

<b>Command History</b>	<b>Release</b>	<b>Modification</b>
	4.0(1)	This command was introduced.
	4.0(3)	Replaced by <b>log-neighbor-warnings</b> command.

**Usage Guidelines** Use the **eigrp log-neighbor-warnings** command to enable neighbor warning messages and to configure the interval between repeated neighbor warning messages.

This command requires the Enterprise Services license.

**Examples** The following example shows how to log neighbor warning messages for EIGRP process 209 and to repeat the warning messages in 5-minute (300 seconds) intervals:

```
switch(config)# router eigrp 209
switch(config-router)# eigrp log-neighbor-warnings 30
```

<b>Related Commands</b>	<b>Command</b>	<b>Description</b>
	<b>log-neighbor-changes</b>	Enables logging of EIGRP neighbor changes.

***Send document comments to [nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)***

<b>Command</b>	<b>Description</b>
<b>log-neighbor-warnings</b>	Enables logging of EIGRP neighbor warnings.
<b>log-adjacency-changes</b>	Enables logging of EIGRP adjacency state changes.

[Send document comments to nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)

## eigrp router-id

To set the router ID used by the Enhanced Interior Gateway Routing Protocol (EIGRP) when communicating with its neighbors, use the **eigrp router-id** command. To remove the configured router ID, use the **no** form of this command.

**eigrp router-id** *ip-address*

**no eigrp router-id** *ip-address*

### Syntax Description

<i>ip-address</i>	Router ID in dotted decimal notation.
-------------------	---------------------------------------

### Command Default

EIGRP automatically selects an IP address to use as the router ID when an EIGRP process is started. The highest local IP address is selected and loopback interfaces are preferred. The router ID is not changed unless the EIGRP process is removed with the **no router eigrp** command or if the router ID is manually configured with the **eigrp router-id** command.

### Command Modes

Address-family configuration  
Router configuration  
Router VRF configuration

### Supported User Roles

network-admin  
vdc-admin

### Command History

Release	Modification
4.0(1)	This command was introduced.
4.0(3)	Replaced by <b>router-id</b> command.

### Usage Guidelines

Use the **eigrp router-id** command to manually configure the router ID for EIGRP. The router ID is used to identify the originating router for external routes. If an external route is received with the local router ID, the route is discarded. The router ID can be configured with any IP address with two exceptions; 0.0.0.0 and 255.255.255.255 are not legal values and cannot be entered. You should configure unique value for each router.

This command requires the Enterprise Services license.

### Examples

The following example shows how to configure 172.16.1.3 as a fixed router ID:

```
switch(config)# router eigrp 209
switch(config-router)# eigrp router-id 172.16.1.3
```

[Send document comments to nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)

## eigrp stub

To configure a router as a stub using the Enhanced Interior Gateway Routing Protocol (EIGRP), use the **eigrp stub** command. To disable the EIGRP stub routing feature, use the **no** form of this command.

**eigrp stub** [**direct** | **leak-map** *map-name* | **receive-only** | **redistributed**]

**no eigrp stub** [**direct** | **leak-map** *map-name* | **receive-only** | **redistributed**]

### Syntax Description

<b>direct</b>	(Optional) Advertises directly connected routes.
<b>leak-map</b> <i>map-name</i>	(Optional) Allows dynamic prefixes based on the leak map.
<b>receive-only</b>	(Optional) Sets the router as a receive-only neighbor.
<b>redistributed</b>	(Optional) Advertises redistributed routes from other protocols and autonomous systems.

### Command Default

Disabled

### Command Modes

Address-family configuration  
Router configuration  
Router VRF configuration

### Supported User Roles

network-admin  
vdc-admin

### Command History

Release	Modification
4.0(1)	This command was introduced.
4.0(3)	Replaced by <b>stub</b> command.

### Usage Guidelines

Use the **eigrp stub** command to configure a router as a stub where the router directs all IP traffic to a distribution router.

The **direct** keyword permits EIGRP stub routing to advertise connected routes. This option is enabled by default.

The **receive-only** keyword restricts the router from sharing any of its routes with any other router in that EIGRP autonomous system, and the **receive-only** keyword does not permit any other option to be specified because it prevents any type of route from being sent.

The **redistributed** keyword permits the EIGRP Stub Routing feature to send other routing protocols and autonomous systems. Without the configuration of this option, EIGRP will not advertise redistributed routes.

If you use any of these four keywords (**direct**, **leak-map**, **receive-only**, **redistributed**) with the **eigrp stub** command, only the route types specified by the particular keyword(s) are advertised.

***Send document comments to [nexus7k-docfeedback@cisco.com](mailto:nexus7k-docfeedback@cisco.com)***

This command requires the Enterprise Services license.

---

**Usage Guidelines**

The following example shows how to configure the router as a receive-only neighbor:

```
switch(config)# router eigrp 1  
switch(config-router)# eigrp stub receive-only
```