

# Sample Configuration Using the ip nat outside source static Command

Document ID: 13773

---

## Introduction

### Prerequisites

Requirements

Components Used

Conventions

### Configure

Network Diagram

Configurations

### Verify

### Troubleshoot

### Summary

[NetPro Discussion Forums – Featured Conversations](#)

### Related Information

---

## Introduction

This document provides a sample configuration with the use of the **ip nat outside source static** command and includes a brief description of what happens to the IP packet during the NAT process. Consider the network topology in this document as an example.

## Prerequisites

### Requirements

Ensure that you meet these requirements before you attempt this configuration:

- How NAT Works
- NAT: Local and Global Definitions.

See the Related Information section of this document for further information.

### Components Used

The information in this document is based on Cisco 2500 Series Routers on Cisco IOS® Software Release 12.2(27) .

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, make sure that you understand the potential impact of any command.

### Conventions

Refer to Cisco Technical Tips Conventions for more information on document conventions.


# Configure

This section presents you with the information to configure the features this document describes.

**Note:** Use the Command Lookup Tool (registered customers only) to find additional information on the commands that this document uses.

## Network Diagram

This document uses this network setup.



When you issue a ping sourced from Router 2514W's Loopback1 interface destined to Router 2501E's Loopback0 interface, this is what happens:

On the outside interface (S1) of Router 2514X, the ping packet shows up with a Source Address (SA) of 172.16.89.32 and a Destination Address (DA) of 171.68.1.1. NAT translates the SA to the Outside Local Address 171.68.16.5 (according to the **ip nat outside source static** command configured on Router 2514X). Router 2514X then checks its routing table for a route to 171.68.1.1. If the route does not exist, Router 2514X drops the packet. In this case, Router 2514X has a route to 171.68.1.1 through the static route to 171.68.1.0. It forwards the packet to the destination. Router 2501E sees the packet on its incoming interface (E0) with an SA of 171.68.16.5, and a DA of 171.68.1.1. It responds by sending an Internet Control Message Protocol (ICMP) echo reply to 171.68.16.5. If it does not have a route, it drops the packet. However, in this case it has the (default) route. Therefore, it sends a reply packet to Router 2514X, using an SA of 171.68.1.1, and a DA of 171.68.16.5. Router 2514X sees the packet and checks for a route to the 171.68.16.5 address. If it does not have one, it responds with an ICMP unreachable reply. In this case, it has a route to 171.68.16.5 (due to the static route). It therefore translates the packet back to the 172.16.89.32 address, and forwards it out its outside interface (S1).

## Configurations

This document uses these configurations:

- Router 2514W
- Router 2514X
- Router 2501E

Router 2514W
<pre>hostname 2514W !</pre>

```

!--- Output suppressed.

interface Loopback1
 ip address 172.16.89.32 255.255.255.0
!
interface Ethernet1
 no ip address
 no ip mroute-cache
!
interface Serial0
 ip address 172.16.191.254 255.255.255.252
 no ip mroute-cache
!

!--- Output suppressed.

ip classless
ip route 0.0.0.0 0.0.0.0 172.16.191.253

!--- Default route to forward packets to 2514X.

!

!--- Output suppressed.

```

### Router 2514X

```

hostname 2514X
!

!--- Output suppressed.

ip nat outside source static 172.16.89.32 171.68.16.5

!--- Outside local address.

!

!--- Output suppressed.

interface Ethernet1
 ip address 171.68.192.202 255.255.255.0
 ip nat inside

!--- Defines Ethernet 1 as a NAT inside interface.

 no ip mroute-cache
 no ip route-cache
!
interface Serial1
 ip address 172.16.191.253 255.255.255.252
 no ip route-cache
 ip nat outside

!--- Defines Serial 1 as a NAT outside interface.

clockrate 2000000

```

```

!

!--- Output suppressed.

ip classless
ip route 171.68.1.0 255.255.255.0 171.68.192.201
ip route 171.68.16.0 255.255.255.0 172.16.191.254

!--- Static routes for reaching the loopback interfaces

!--- on 2514E and 2514W.

!

!--- Output suppressed.

```

### Router 2501E

```

hostname rp-2501E
!

!--- Output suppressed.

interface Loopback0
 ip address 171.68.1.1 255.255.255.0
!
interface Ethernet0
 ip address 171.68.192.201 255.255.255.0
!

!--- Output suppressed.

ip classless
ip route 0.0.0.0 0.0.0.0 171.68.192.202

!--- Default route to forward packets to 2514X.

!

!--- Output suppressed.

```

## Verify

Use this section to confirm that your configuration works properly.

The Output Interpreter Tool (registered customers only) (OIT) supports certain **show** commands. Use the OIT to view an analysis of **show** command output.

Use the **show ip nat translations** command to check the translation entries, as this output shows.

```

2514X#show ip nat translations
Pro Inside global      Inside local      Outside local      Outside global
--- ---                ---                ---                ---
                171.68.16.5      171.16.89.32

```

## Troubleshoot

This example uses the NAT translation debugging and IP packet debugging to demonstrate the NAT process.

**Note:** Because the **debug** commands generate a significant amount of output, use them only when traffic on the IP network is low so that other activity on the system is not adversely affected.

**Note:** Refer to Important Information on Debug Commands before you use **debug** commands.

This output is the result of running the **debug ip packet** and **debug ip nat** commands simultaneously on Router 2514X, while pinging from the Router 2514W loopback1 interface address (172.16.89.32) to the Router 2501E loopback0 interface address (171.68.1.1)

This output shows the first packet arriving on the outside interface of Router 2514X. The source address of 172.16.89.32 gets translated to 171.68.16.5. The ICMP packet is forwarded toward the destination out the Ethernet1 interface.

```
5d17h: NAT: s=172.16.89.32->171.68.16.5, d=171.68.1.1 [171]
5d17h: IP: tableid=0, s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), routed
via RIB
5d17h: IP: s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), g=171.68.192.201,
len 100, forward
5d17h:      ICMP type=8, code=0
```

This output shows the return packet sourced from 171.68.1.1 with a destination address of 171.68.16.5, which gets translated to 172.16.89.32. The resulting ICMP packet gets forwarded out the Serial1 interface.

```
5d17h: IP: tableid=0, s=171.68.1.1 (Ethernet0), d=171.68.16.5 (Serial0), routed
via RIB
5d17h: NAT: s=171.68.1.1, d=171.68.16.5->172.16.89.32 [171]
5d17h: IP: s=171.68.1.1 (Ethernet0), d=172.16.89.32 (Serial0), g=172.16.191.254,
len 100, forward
5d17h:      ICMP type=0, code=0
```

The exchange of ICMP packets continues. The NAT process for this debug output is the same as the previous output.

```
5d17h: NAT: s=172.16.89.32->171.68.16.5, d=171.68.1.1 [172]
5d17h: IP: tableid=0, s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), routed
via RIB
5d17h: IP: s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), g=171.68.192.201,
len 100, forward
5d17h:      ICMP type=8, code=0
5d17h: IP: tableid=0, s=171.68.1.1 (Ethernet0), d=171.68.16.5 (Serial0), routed
via RIB
5d17h: NAT: s=171.68.1.1, d=171.68.16.5->172.16.89.32 [172]
5d17h: IP: s=171.68.1.1 (Ethernet0), d=172.16.89.32 (Serial0), g=172.16.191.254,
len 100, forward
5d17h:      ICMP type=0, code=0
5d17h: NAT: s=172.16.89.32->171.68.16.5, d=171.68.1.1 [173]
5d17h: IP: tableid=0, s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), routed
via RIB
5d17h: IP: s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), g=171.68.192.201,
len 100, forward
5d17h:      ICMP type=8, code=0
5d17h: IP: tableid=0, s=171.68.1.1 (Ethernet0), d=171.68.16.5 (Serial0), routed
via RIB
5d17h: NAT: s=171.68.1.1, d=171.68.16.5->172.16.89.32 [173]
```

```

5d17h: IP: s=171.68.1.1 (Ethernet0), d=172.16.89.32 (Serial0), g=172.16.191.254,
len 100, forward
5d17h: ICMP type=0, code=0
5d17h: NAT: s=172.16.89.32->171.68.16.5, d=171.68.1.1 [174]
5d17h: IP: tableid=0, s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), routed
via RIB
5d17h: IP: s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), g=171.68.192.201,
len 100, forward
5d17h: ICMP type=8, code=0
5d17h: IP: tableid=0, s=171.68.1.1 (Ethernet0), d=171.68.16.5 (Serial0), routed
via RIB
5d17h: NAT: s=171.68.1.1, d=171.68.16.5->172.16.89.32 [174]
5d17h: IP: s=171.68.1.1 (Ethernet0), d=172.16.89.32 (Serial0), g=172.16.191.254,
len 100, forward
5d17h: ICMP type=0, code=0
5d17h: NAT: s=172.16.89.32->171.68.16.5, d=171.68.1.1 [175]
5d17h: IP: tableid=0, s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), routed
via RIB
5d17h: IP: s=171.68.16.5 (Serial0), d=171.68.1.1 (Ethernet0), g=171.68.192.201,
len 100, forward
5d17h: ICMP type=8, code=0
5d17h: IP: tableid=0, s=171.68.1.1 (Ethernet0), d=171.68.16.5 (Serial0), routed
via RIB
5d17h: NAT: s=171.68.1.1, d=171.68.16.5->172.16.89.32 [175]
5d17h: IP: s=171.68.1.1 (Ethernet0), d=172.16.89.32 (Serial0), g=172.16.191.254,
len 100, forward
5d17h: ICMP type=0, code=0

```

## Summary

When the packet travels from outside to inside, translation occurs first, and then the routing table is checked for the destination. When the packet travels from inside to outside, the routing table is checked for the destination first, and then translation occurs. Refer to NAT Order of Operation for further information.

It is important to note which part of the IP packet gets translated when using each of the commands this document discusses. This table contains a guideline:

Command	Action
<b>ip nat outside source static</b>	<ul style="list-style-type: none"> <li>• Translates the source of the IP packets that travel outside to inside.</li> <li>• Translates the destination of the IP packets that travel inside to outside.</li> </ul>
<b>ip nat inside source static</b>	<ul style="list-style-type: none"> <li>• Translates the source of IP packets that travel inside to outside.</li> <li>• Translates the destination of the IP packets that travel outside to inside.</li> </ul>

These guidelines indicate that there is more than one way to translate a packet. Based on your specific needs, you should determine how to define the NAT interfaces (inside or outside) and what routes the routing table should contain before or after translation. Keep in mind that the portion of the packet that is translated depends upon the direction the packet travels, and how you configure NAT.

# NetPro Discussion Forums – Featured Conversations

Networking Professionals Connection is a forum for networking professionals to share questions, suggestions, and information about networking solutions, products, and technologies. The featured links are some of the most recent conversations available in this technology.

NetPro Discussion Forums – Featured Conversations for RP
Service Providers: MPLS
Virtual Private Networks: Services
Virtual Private Networks: Security

---

## Related Information

- [Sample Configuration Using the ip nat outside source list Command](#)
- [Configuring Network Address Translation: Getting Started](#)
- [NAT Support Page](#)
- [Technical Support & Documentation – Cisco Systems](#)

---

All contents are Copyright © 2006–2007 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.

---

Updated: Jun 01, 2006

Document ID: 13773

---