ISE 2.1- und AnyConnect 4.3-Status-USB-Prüfung konfigurieren

Inhalt

Einführung Voraussetzungen Anforderungen Verwendete Komponenten Konfigurieren Netzwerkdiagramm **ASA** ISE Schritt 1: Netzwerkgerät konfigurieren Schritt 2: Konfigurieren der Statusbedingungen und -richtlinien Schritt 3: Konfiguration von Client-Bereitstellungsressourcen und Richtlinien Schritt 4: Autorisierungsregeln konfigurieren Überprüfen Einrichtung von VPN-Sitzungen Einrichtung von VPN-Sitzungen **Client-Bereitstellung** Statusprüfung und CoA Fehlerbehebung Referenzen

Einführung

In diesem Dokument wird beschrieben, wie die Cisco Identity Services Engine (ISE) so konfiguriert wird, dass der uneingeschränkte Zugriff auf das Netzwerk nur möglich ist, wenn USB-Massenspeichergeräte getrennt werden.

Voraussetzungen

Anforderungen

Cisco empfiehlt, über Kenntnisse in folgenden Bereichen zu verfügen:

- Grundkenntnisse der CLI-Konfiguration der Adaptive Security Appliance (ASA) und der SSL-VPN-Konfiguration (Secure Socket Layer)
- Grundkenntnisse der Remote-Access-VPN-Konfiguration auf der ASA
- Grundkenntnisse der ISE und Statusservices

Verwendete Komponenten

Cisco Identity Services Engine (ISE) Version 2.1 unterstützt zusammen mit AnyConnect Secure Mobility Client 4.3 USB Mass Storage Check und Remediation. Die Informationen in diesem Dokument basieren auf den folgenden Softwareversionen:

- Cisco ASA Software Version 9.2(4) und höher
- Microsoft Windows 7 mit Cisco AnyConnect Secure Mobility Client Version 4.3 und höher
- Cisco ISE, Version 2.1 und höher

Konfigurieren

Netzwerkdiagramm



Der Fluss ist der folgende:

- Der Benutzer ist noch nicht mit dem VPN verbunden, das private USB-Massenspeichergerät ist angeschlossen, und der Benutzer kann Inhalte nutzen.
- Vom AnyConnect-Client initiierte VPN-Sitzung wird über ISE authentifiziert. Der Status des Endpunkts ist nicht bekannt, die Regel "Posture_Unknown" (Status unbekannt) wird getroffen, und die Sitzung wird an die ISE umgeleitet.
- Die USB-Pr
 üfungen f
 ühren eine neue Klasse von Pr
 üfungen des AC ISE-Status ein, da sie den Endpunkt kontinuierlich
 überwachen, solange er sich im selben ISE-gesteuerten Netzwerk befindet. Die einzige m
 ögliche logische Gegenma
 ßnahme besteht darin, das/die USB-Ger
 ät(e) zu blockieren, das/die durch den Laufwerkbuchstaben identifiziert wird/werden.
- VPN-Sitzung auf der ASA wird aktualisiert, die Umleitung der ACL wird entfernt und der vollständige Zugriff wird gewährt

Die VPN-Sitzung wurde als Beispiel vorgestellt. Die Statusfunktion funktioniert auch für andere Zugriffstypen gut.

ASA

ASA wird für den Remote-SSL VPN-Zugriff mithilfe der ISE als AAA-Server konfiguriert. Radius CoA muss zusammen mit der Umleitungszugriffskontrollliste konfiguriert werden:

```
aaa-server ISE21 protocol radius
authorize-only
interim-accounting-update periodic 1
dynamic-authorization
aaa-server ISE21 (outside) host 10.48.23.88
key cisco
```

tunnel-group RA type remote-access tunnel-group RA general-attributes address-pool POOL authentication-server-group ISE21 accounting-server-group ISE21 default-group-policy GP-SSL tunnel-group RA webvpn-attributes group-alias RA enable

webvpn enable outside anyconnect image disk0:/anyconnect-win-4.3.00520-k9.pkg 1 anyconnect enable tunnel-group-list enable error-recovery disable group-policy GP-SSL internal group-policy GP-SSL attributes dns-server value 10.62.145.72 vpn-tunnel-protocol ssl-client

```
access-list ACL_WEBAUTH_REDIRECT extended deny udp any any eq domain
access-list ACL_WEBAUTH_REDIRECT extended deny ip any host 10.48.23.88
access-list ACL_WEBAUTH_REDIRECT extended deny icmp any any
access-list ACL_WEBAUTH_REDIRECT extended permit tcp any any
Weitere Informationen finden Sie unter:
```

Konfigurationsbeispiel für die Integration von AnyConnect 4.0 in ISE Version 1.3

ISE

Schritt 1: Netzwerkgerät konfigurieren

Von Administration > Network Resources > Network Devices > Add ASA

dentity Services Engine	Home Context Directory Operations Policy Administration Work Centers
System Identity Management	▼Network Resources → Device Portal Management pxGrid Services → Feed Service → PassiveID → Threat Centric NAC
Network Devices Network Device C	Groups Network Device Profiles External RADIUS Servers RADIUS Server Sequences NAC Managers External MDM + Location Services
0	
Network devices	Network Devices
Default Device	* Name BCNC.ACA5515.11
	* IP Address: 10.48.66.202 / 32
	* Device Profile ditto Cisco 💌 🕀
	Model Name
	Software Version
	* Network Device Group
	Device Type All Device Types 📀 Set To Default
	Location All Locations 📀 Set To Default
	✓ RADIUS Authentication Settings
	Enable Authentication Settings
	Protocol RADIUS
	Shared Secret Show
	Enable KeyWrap
	Key Encryption Key Show
	* Message Authenticator Code Key Show
	Key Input Format ASCII HEXADECIMAL
	CoA Port 1700 Set To Default

Schritt 2: Konfigurieren der Statusbedingungen und -richtlinien

Stellen Sie sicher, dass die Statusbedingungen aktualisiert werden: Verwaltung > System > Einstellungen > Status > Updates > Option Jetzt aktualisieren.

ISE 2.1 enthält eine vorkonfigurierte USB-Bedingung, die überprüft, ob ein USB-Massenspeichergerät angeschlossen ist.

Von **Richtlinien > Richtlinienelemente > Bedingungen > Status > USB-Zustand** überprüfen Sie den vorhandenen Zustand:

cisco	Identit	y Services En	gine	Home	Context	Directory	 Operations 	- Policy	Administration	Work Centers
Authe	ntication	Authorization	Profili	ng Posture	Client	Provisioning		nts		
Diction	naries	- Conditions	Results	6						
			G							
► Authe	enticatio	n			Name	USB_Check	c			
► Autho	orization	1		[Description	Cisco Prede	fined Check: Che	ecks if USB	mass storage device is	connected.
Profiling	I			Operati	ng System	Windows Al	I			
- Postu	Ire			Complian	ce Module	4.x or later (D			
Anti-	Malware	Condition								
Anti-	Spyware	Condition								
Anti-	Virus Co	ndition								
Appl	ication C	ondition								
Com	pound C	ondition								
Disk	Encrypti	on Condition								
File	Conditior	ı								
Patc	h Manag	ement Condition								
Regi	stry Con	dition								
Serv	ice Cond	lition								
USB	Conditio	n								
Dicti	onary Sir	mple Condition								
Dicti	onary Co	mpound Condition	on							
+ Gues	t									
► Comr	non									

Unter **Richtlinien > Richtlinienelemente > Ergebnisse > Status > Anforderungen** überprüfen Sie die vorkonfigurierte Anforderung, die diese Bedingung verwendet.

	Home Context Directory	► Operations	Administration Work Centers		
Authentication Authorization Profiling	Posture Client Provisioning				
Dictionaries + Conditions - Results					
G					
► Authentication	Requirements				
	Name	Operating Systems	Compliance Module	Conditions	Remediation Actions
Authorization	USB_Block	for Windows All	using 4.x or later	met if USB_Check	then USB_Block
Profiling					
▼ Posture					
- Remediation Actions					
Requirements					
► Client Provisioning					

Fügen Sie unter **Richtlinie > Status** eine Bedingung hinzu, dass alle Windows diese Anforderung verwenden:

cisco	Identity	/ Services Engine	Home	Context Directory	 Operations 	- Policy	 Administration 	 Work Centers 			
Auth	entication	Authorization Pro	filing Posture	Client Provisioning	Policy Element	ents					
Postu Define	the Polic	y re Policy by configuring	rules based on c	operating system and/or	r other conditions.						
•											
	Status	Rule Name	ld	lentity Groups	Operating Sys	stems	Compliance Mod	ule	Other Conditions	Requirem	ients
	~	Windows 7 USB check	k If A	ny	and Windows 7	(All)	and 4.x or later		and	then USB.	_Block

Von Richtlinien > Richtlinienelemente > Ergebnisse > Status > Remediation Actions > USB Remediations (Aktionen zur Problembehebung > USB-Remediations) überprüfen Sie vorkonfigurierte Behebungsmaßnahmen, um USB-Speichergeräte zu blockieren:

cisco Identity Services Engine	Home	► Operations	Administration Work Centers
Authentication Authorization Profiling	ng Posture Client Provisioning	- Policy Elements	
Dictionaries Conditions - Results			
G			
► Authentication	USB Remediations		
Authorization	/ Edit + Add Duplicate	XDelete	
▶ Profiling	Name	Description	Туре
	USB_Block	Cisco Predefined Reme	ediation: Automatic
- Posture			
- Remediation Actions			
Anti-Malware Remediations			
Anti-Spyware Remediations			
Anti-Virus Remediations			
File Remediations			
Launch Program Remediations			
Link Remediations			
Patch Management Remedia			
USB Remediations			
Windows Server Update Ser			
Windows Update Remediations			
Requirements			
Client Provisioning			

Schritt 3: Konfiguration von Client-Bereitstellungsressourcen und Richtlinien

Von **Richtlinien > Richtlinienelemente > Client Provisioning > Ressourcen** laden Sie Compliance-Modul von Cisco.com herunter und laden Sie das AnyConnect 4.3-Paket manuell hoch:

Services Engine Home Context Directory > Operations - Policy > Administration >	Work Centers
Authorization Profiling Posture Client Provisioning Policy Elements	
Conditions - Results	
0	
Resources	
✓ Edit + Add ▼ I Duplicate X Delete	
Name Type Version	Last Update Description
AnyConnectDesktopWindows 4.3.520.0 AnyConnectDesktopWindows 4.3.520.0	2016/03/11 11:10:47 AnyConnect Secure Mobility Clie
AnyConnectComplianceModuleWind AnyConnectComplianceMo 4.2.330.0	0 2016/03/11 11:11:16 AnyConnect Windows Complian
WinSPWizard 2.1.0.50 WinSPWizard 2.1.0.50	2016/03/07 17:50:37 Supplicant Provisioning Wizard f
Ing AnyConnect Configuration AnyConnectConfig Not Applic	icable 2016/03/11 11:12:42
MacOsXSPWizard 2.1.0.39 MacOsXSPWizard 2.1.0.39	2016/03/07 17:50:37 Supplicant Provisioning Wizard f
Cisco-ISE-NSP Native Supplicant Profile Not Applic	icable 2016/03/07 17:50:37 Pre-configured Native Supplicant
Cisco-ISE-Chrome-NSP Native Supplicant Profile Not Applic	icable 2016/03/07 17:50:37 Pre-configured Native Supplicant
Anyconnect_Posture_Profile AnyConnectProfile Not Applic	icable 2016/03/11 14:39:03
Resources Image: Fedit ==Add * Image: Duplicate *	Last Update Description 0 2016/03/11 11:10:47 AnyConnect Secure Mobility O 0 2016/03/11 11:11:16 AnyConnect Windows Complia 2016/03/07 17:50:37 Supplicant Provisioning Wizar icable 2016/03/07 17:50:37 Supplicant Provisioning Wizar icable 2016/03/07 17:50:37 Supplicant Provisioning Wizar icable 2016/03/07 17:50:37 Pre-configured Native Supplic icable 2016/03/07 17:50:37 Pre-configured Native Supplic icable 2016/03/07 11:4:39:03 Pre-configured Native Supplic

Erstellen Sie mit **Add > NAC Agent oder AnyConnect Posture Profile** ein AnyConnect-Statusprofil (Name: *AnyConnect_Posture_Profile*) mit Standardeinstellungen.

Fügen Sie mithilfe von **Add > AnyConnect Configuration** eine AnyConnect-Konfiguration hinzu (Name: AnyConnect-Konfiguration):

cisco	Identit	y Services En	igine	Home	Context Directory	 Operations 	- Policy	Administration	 Work Centers 	
Authe	entication	Authorization	n Profilin	g Posture	Client Provisioning	✓ Policy Element	ents			
Dictio	naries	Conditions	- Results							
			Ø							
+ Auth	enticatio	n		AnyConne	ct Configuration > AnyC	Connect Configura	ation			
► Auth	orization				•s	elect AnyConnect	Package: A	nvConnectDesktopWind	ows 4,3.520.0 👻	1
▶ Profi	ling					* Configurat	ion Name: A	nyConnect Configuration	1	
► Post	ure					D	escription:			
- Clien	t Provisi	oning				De * Complian	escriptionVa	lue	oduloWindows 4 2 220 0 -	Notes
Res	ources					Compilan		nyconnectcompliancem	0000ewindows 4.2.550.0 +]
				AnyConne	ect Module Selection	IS	E Posture			
							VPN			
						Network Access We	b Security			
						AM	IP Enabler			
						AS	A Posture			
						Start Bef	ore Logon			
					Di	agnostic and Rep	orting Tool			
				Profile Se	lection	* 10	E Docture	warment Desture Dest	71-	1
						13		nyconnect_Posture_Proi	The *	,
						Network Access	s Manager		· · · · · · · · · · · · · · · · · · ·	1
						We	b Security		.	1
						AM	IP Enabler		*	
						Netwo	rk Visibility		.	
						Customer	Feedback		*]

Erstellen Sie unter **Richtlinie > Client Provisioning** eine neue Richtlinie (Windows_Posture) für Windows, um die AnyConnect-Konfiguration zu verwenden:

cis	ilii co	Identity	Services Engir	ne Ho	me	Context Director	iry	Operations	- Policy	•	Administration	Work Centers		
A	uthen	tication	Authorization	Profiling	Posture	Client Provisio	oning	Policy Element	ents					
Clic Defi For	lient Provisioning Policy efine the Client Provisioning Policy to determine what users will receive upon login and user session initiation: or Agent Configuration: version of agent, agent profile, agent compliance module, and/or agent customization package.													
For	Nativ	e Supplic	ant Configuration	: wizard profi	ile and/o	r wizard. Drag and	d drop n	ules to change the	he order.		0			
•			Rule Name			Identity Groups		Operating Sys	tems		Other Conditions			Results
	(0	DS		lf	Any	and	Apple iOS All	а	Ind	Condition(s)		then	Cisco-ISE-NSP
	(Ø 4	ndroid		lf	Any	and	Android	а	ind	Condition(s)		then	Cisco-ISE-NSP
	(Ø V	Vindows		lf	Any	and	Windows All	а	Ind	Condition(s)		then	WinSPWizard 2.1.0.50 And Cisco-ISE-NSP
	I	V	Vindows_Posture		lf	Any	and	Windows All	а	Ind	Condition(s)		then	AnyConnect Configuration
	(Ø N	IAC OS		lf	Any	and	Mac OSX	а	Ind	Condition(s)		then	MacOsXSPWizard 2.1.0.39 And Cisco- ISE-NSP
	(0	hromebook		lf	Any	and	Chrome OS A	M a	Ind	Condition(s)		then	Cisco-ISE-Chrome-NSP

Schritt 4: Autorisierungsregeln konfigurieren

Von **Richtlinien > Richtlinienelemente > Ergebnisse > Autorisierung** Autorisierungsprofil hinzufügen (Name: Posture_Redirect), die zu einem Standard-Client-Bereitstellungsportal umgeleitet wird:

cisco Identity Services Engine	Home	Operations Policy	Administration	Work Centers
Authentication Authorization Profili	ng Posture Client Provisioning	✓ Policy Elements		
Dictionaries + Conditions - Result	5			
0				
Authentication	Authorization Profiles > Posture_R	ledirect		
- Authorization	* Name Post	ure_Redirect		
Authorization Profiles	Description			
Downloadable ACLs	* Access Type ACCE	ESS_ACCEPT		
▶ Profiling	Network Device Profile	Disco 💌 🕀		
Posture	Service Template			
Client Provisioning	Track Movement (i)			
-	Passive Identity Tracking			
	✓ Common Tasks			
	O Voice Domain Permission			
	Web Redirection (CWA, MI)	dm, NSP, CPP) 👔		
	Client Provisioning (Posture	e) 👻 ACL ACL_WEBAUT	H_REDIRECT	Value Client Provisioning Portal (defa •

Hinweis: ACL_WEBAUTH_REDIRECT ACL ist auf ASA definiert.

Erstellen Sie unter **Richtlinien > Autorisierung** eine Autorisierungsregel für die Umleitung. Eine Autorisierungsregel für konforme Geräte ist auf der ISE vorkonfiguriert:

cisco	Identity	Services Engin	e Home	 Contex 	t Directory	 Operations 	- Policy	Administration	Work Centers	
Auther	ntication	Authorization	Profiling Po	osture Clien	t Provisioning	Policy Element	ents			
Author Define th For Polic First Ma	rization ne Authori cy Export atched Ru	Policy ization Policy by cc go to Administratio	onfiguring rules on > System > E v	based on iden Backup & Resto	tity groups and ore > Policy Ex	l/or other condition cport Page	ns. Drag and c	Irop rules to change th	ne order.	
Stan	dard	(0)								
	Status	Rule Name			Conditions (id	dentity groups and	other condition	ons)	Pe	ermissions
	~	Compliant_Dev	vices_Access	if	(Network_A	ccess_Authentica	tion_Passed /	AND Compliant_Devic	then	PermitAccess
	~	Posture_Unkno	wn	if	Session:Po	stureStatus NOT_	EQUALS Con	npliant	then	Posture_Redirect

Wenn der Endpunkt den Vorgaben entspricht, wird umfassender Zugriff bereitgestellt. Wenn der Status unbekannt oder nicht konform ist, wird eine Umleitung für die Client-Bereitstellung zurückgegeben.

Überprüfen

Einrichtung von VPN-Sitzungen

USB-Gerät angeschlossen, und der Inhalt ist für den Benutzer verfügbar.



Einrichtung von VPN-Sitzungen

Während der Authentifizierung gibt die ISE im Rahmen des Status_Redirect Authorization Profile (Status_Redirect-Autorisierungsprofils) die Umleitungsliste zurück und leitet die URL um.

cisco Ider	tity Services Engine	Home	▸ Cont	ext Directory	 Operations 	Policy	Administration	 Work Centers 			Li	cense Warning 🔺	Q	0	. \$
▼RADIUS	TC-NAC Live Logs + T	ACACS	Legacy D	ashboard Re	eports + Trouble	eshoot 🕨 A	daptive Network Contro	4							
Live Logs	Live Sessions														
	Misconfigur	ed Suppl	icants 🕄	Misconf	igured Network D	evices 🟮	RADIUS Dro	ops 🛈	Client St	opped Responding 🕄	Re	epeat Counter 1			
		0			0		6			0		0			
									Refresh	Every 1 minute	Show Latest	20 records 🗾 W	lithin La	ast 5 minute:	s -
${\cal C}$ Refresh	Reset Repeat Counts	<u>⊿</u> ∋	kport To 🔻											▼ Filter -	۰.
Time		Sta	Details	Identity	Endpoint ID	Auth	nentication Policy	Authorizatio	on Policy	Authorization Pr	IP Address	Network De	Postur	e Status	Server
Mar 1	1, 2016 03:57:40.126 PM	0	0	cisco	00:0C:29:C9:	Defa	ult >> Default >> Defau	It Default >> Po	osture_Un	Posture_Redirect	10.10.10		Pending	9	ISE21-1
Mar 1	1, 2016 03:57:39.598 PM		0	cisco	00:0C:29:C9:	Defa	ult >> Default >> Defau	It Default >> Po	osture_Un	Posture_Redirect		BSNS-ASA55	Pending	9	ISE21-1

Nach Einrichtung der VPN-Sitzung wird der ASA-Datenverkehr vom Client entsprechend der

Umleitungsliste umgeleitet:

BSNS-ASA5515-11# sh vpn-sessiondb detail anyconnect

Session Type: AnyConnect Detailed

```
: 29
Username
          : cisco
                                   Index
Assigned IP : 10.10.10.10
                                  Public IP : 10.229.16.34
Protocol : AnyConnect-Parent SSL-Tunnel DTLS-Tunnel
License : AnyConnect Premium
Encryption : AnyConnect-Parent: (1)none SSL-Tunnel: (1)AES128 DTLS-Tunnel: (1)AES128
Hashing : AnyConnect-Parent: (1)none SSL-Tunnel: (1)SHA1 DTLS-Tunnel: (1)SHA1
          : 14696
Bytes Tx : 146
Pkts Tx : 20
                                  Bytes Rx : 18408
                                              : 132
                                  Pkts Rx
Pkts Tx Drop : 0
                                  Pkts Rx Drop : 0
Group Policy : GP-SSL
                                  Tunnel Group : RA
Login Time : 15:57:39 CET Fri Mar 11 2016
           : 0h:07m:22s
Duration
Inactivity : 0h:00m:00s
VLAN Mapping : N/A
                                  VLAN
                                          : none
Audt Sess ID : 0a3042ca0001d00056e2dce3
Security Grp : none
AnyConnect-Parent Tunnels: 1
SSL-Tunnel Tunnels: 1
DTLS-Tunnel Tunnels: 1
AnyConnect-Parent:
Tunnel ID : 29.1
Public IP : 10.229.16.34
Encryption : none
                                  Hashing
                                              : none
TCP Src Port : 61956
                                   TCP Dst Port : 443
Auth Mode : userPassword
Idle Time Out: 30 Minutes
                                   Idle TO Left : 22 Minutes
Client OS : win
Client OS Ver: 6.1.7601 Service Pack 1
Client Type : AnyConnect
Client Ver : Cisco AnyConnect VPN Agent for Windows 4.3.00520
           : 6701
Bytes Tx
                                   Bytes Rx : 774
          : 5
                                   Pkts Rx
                                              : 1
Pkts Tx
Pkts Tx Drop : 0
                                   Pkts Rx Drop : 0
SSL-Tunnel:
Tunnel ID : 29.2
Assigned IP : 10.10.10.10
                                  Public IP : 10.229.16.34
Encryption : AES128
                                  Hashing
                                              : SHA1
                                  TCP Src Port : 61957
Encapsulation: TLSv1.0
                                  Auth Mode : userPassword
TCP Dst Port : 443
                                  Idle TO Left : 22 Minutes
Idle Time Out: 30 Minutes
Client OS : Windows
Client Type : SSL VPN Client
Client Ver : Cisco AnyConnect VPN Agent for Windows 4.3.00520
                                   Bytes Rx : 1245
           : 6701
Bytes Tx
Pkts Tx : 5
                                   Pkts Rx : 5
Pkts Tx Drop : 0
                                   Pkts Rx Drop : 0
DTLS-Tunnel:
Tunnel ID : 29.3
Assigned IP : 10.10.10.10
                                  Public IP : 10.229.16.34
Encryption : AES128
                                  Hashing
                                              : SHA1
Encapsulation: DTLSv1.0
                                  UDP Src Port : 55708
                                   Auth Mode : userPassword
UDP Dst Port : 443
```

Idle Time Out:	30 Minutes	Idle TO Left	: 26 Minutes
Client OS :	Windows		
Client Type :	DTLS VPN Client		
Client Ver :	Cisco AnyConnect VPN Ag	gent for Windo	bws 4.3.00520
Bytes Tx :	1294	Bytes Rx	: 16389
Pkts Tx :	10	Pkts Rx	: 126
Pkts Tx Drop :	0	Pkts Rx Drop	: 0
ISE Posture:			
Redirect URL	: https://ISE21-		
<pre>lek.example.com</pre>	:8443/portal/gateway?se	ssionId=0a3042	ca0001d00056e2dce3&portal=2b1ba210-e
Redirect ACL	: ACL_WEBAUTH_REDIRECT		

Client-Bereitstellung

In dieser Phase wird der Webbrowser-Datenverkehr des Endgeräts zur Client-Bereitstellung an die ISE umgeleitet:

Security Check × +	
+ A https://ise21-1ek.example.com:8443/portal/PortalSetup.action?portal=2b1ba210-e486-11e5-9980-005056bf55e0&session C & C & C	☆ 自 🛡 -
Client Provisioning Portal	
Device Security Check Your computer requires security software to be installed before you can connect to the network. Start	

Bei Bedarf wird AnyConnect zusammen mit dem Status- und Compliance-Modul aktualisiert.

Statusprüfung und CoA

Statusmodul wird ausgeführt, ISE wird ermittelt (es kann erforderlich sein, dass DNS A-Eintrag für enroll.cisco.com vorhanden ist, um erfolgreich zu sein), Statusbedingungen heruntergeladen und überprüft, neue OPSWAT v4-Block USB-Geräteaktion. Die konfigurierte Nachricht wird für den Benutzer angezeigt:



Sobald die Meldung bestätigt wurde, ist das USB-Gerät für den Benutzer nicht mehr verfügbar:



ASA entfernt Umleitungszugriffskontrolllisten, die vollständigen Zugriff ermöglichen. AnyConnect meldet Compliance:



Darüber hinaus können detaillierte Berichte zur ISE bestätigen, dass die erforderlichen Bedingungen erfüllt wurden.

Statusüberprüfung nach Bedingung:

dentity Services Engine Home	Context Directory Op	erations	Policy	Administration	Work Centers									
► RADIUS TC-NAC Live Logs ► TACACS L	Legacy Dashboard Reports	► Troub	eshoot + /	Adaptive Network Control										
Report Selector	Posture Assessment	Posture Assessment by Condition												
Favorites	From 00/44/0046 40:00:0	From 03/11/2016 12-00-00 000 AM to 03/11/2016 04:37-13 253 PM												
ISE Reports														
Audit 10 reports														
Device Administration	Logged At	Posture	Identity	Endpoint ID	IP Address	Location	Endpoint OS	Policy	Enforcement Type	Condition Status	Condition name			
4 reports	2016-03-11 16:06:24.974		cisco	00:0C:29:C9:D9:37	10.48.66.202	All Locations	Windows 7 Ultim	Windows 7 USB check	Mandatory	Passed	USB_Check			
 Diagnostics 10 reports 	2016-03-11 11:31:53.456		cisco	00:0C:29:C9:D9:37	10.48.66.202	All Locations	Windows 7 Ultim	Windows 7 USB check	Mandatory	Passed	USB_Check			
▼ Endpoints and Users	2016-03-11 11:26:57.007	~	cisco	00:0C:29:C9:D9:37	10.48.66.202	All Locations	Windows 7 Ultim	Windows 7 USB check	Mandatory	Passed	USB_Check			
Authentication Summary	2016-03-11 11:16:33.483	~	cisco	00:0C:29:C9:D9:37	10.48.66.202	All Locations	Windows 7 Ultim	Windows 7 USB check	Mandatory	Passed	USB_Check			
Client Provisioning														
Current Active Sessions														
External Mobile Device Management														
Manual Certificate Provisioning														
PassiveID														
Posture Assessment by Condition														
* Time Range Today ~														

Statusüberprüfung nach Endpunkt:

1	Induity Services Engine Home	Context Directory	Operations	Policy	Administra	ation 🕨 W	ork Centers						
	► RADIUS TC-NAC Live Logs ► TACACS	Legacy Dashboard Report	ts + Troubl	eshoot	Adaptive Netwo	rk Control							
	Report Selector	Posture Assessment by Endpoint											
	Favorites												
	ISE Reports	From 03/11/2016 12:00	0:00.000 AM t	o 03/11/20	16 04:33:39.111 P	M							
	Audit 10 reports												
	Device Administration	Logged At	Status	Details	PRA Action Id	entity	Endpoint ID	IP Address	Endpoint OS	Agent	Message		
	4 reports	2016-03-11 16:06:24.974	4 🔽	0	N/A cis	sco	00:0C:29:C9:D9:37	10.48.66.202	Windows 7 Ultim	AnyConnect P	Received a posture report from an endpoint		
	Diagnostics 10 reports	2016-03-11 11:31:53.456	6 🔽	Q	N/A cis	SCO	00:0C:29:C9:D9:37	10.48.66.202	Windows 7 Ultim	AnyConnect P	Received a posture report from an endpoint		
	▼ Endpoints and Users	2016-03-11 11:26:57.007	7 🔽	ò	logoff cis	SCO	00:0C:29:C9:D9:37	10.48.66.202	Windows 7 Ultim	AnyConnect P	Posture service received a USB-check report from an endpoint		
	Authentication Summary	2016-03-11 11:16:33.483	3 🔽	ò	N/A cis	SCO	00:0C:29:C9:D9:37	10.48.66.202	Windows 7 Ultim	AnyConnect P	Received a posture report from an endpoint		
	Client Provisioning												
	Current Active Sessions												
	External Mobile Device Management												
	Manual Certificate Provisioning												
	PassiveID												
	Posture Assessment by Condition												
	Posture Assessment by Endpoint $$$\earrow$$ Filters $$\earrow$$												
	* Time Range Today ~												

Details zum Endpunktbericht:

Posture More I	Detail Asses	ssment												
Time Range: Fro	ne Range: From 03/11/2015 12-00:00.000 AM to 03/11/2015 04:34:03-706 PM													
Generated At: 20	016-03-11 16:34:0	03.708												
Username:		cisco												
Mac Address:		00:0C:2	9:C9:D9:37											
IP address:		10.48.6	6.202											
Location:		All Loca	tions											
Session ID:		0a3042	ca0001d00056e2dce3											
Client Operating	System:	Window	s 7 Ultimate 64-bit											
Client NAC Agent	t:	AnyCon	nect Posture Agent fo	r Windows	\$ 4.3.00520									
PRA Enforcement	t:	0												
CoA:		Receive	d a posture report fro	m an end;	point									
PRA Grace Time:		0												
PRA Interval:		0												
PRA Action:		N/A												
User Agreement	Status:	NotEnal	oled											
System Name:		WIN7-P	с											
System Domain:		n/a												
System User:		Win7	Win7											
User Domain:		Win7-P0	0											
AV Installed:														
AS Installed:														
AM Installed:		Window	s Defender;6.1.7600.	16385;1.2	15.699.0;03/09/2016	;								
Posture Report														
Posture Status:		Complia												
Logged At:		2016-03	3-11 16:06:24.974											
Posture Policy De	etails													₩ -
Policy	Na	me	Enforcement Type	Status	Passed Conditions	Failed Conditions	Skipped Conditions							
Windows 7 USB	check US	B_Block	Mandatory		USB_Check									

Fehlerbehebung

Die ISE kann Einzelheiten zu den ausgefallenen Bedingungen mitteilen. Daher sollten entsprechende Maßnahmen ergriffen werden.

Referenzen

- Konfigurieren eines externen Servers für die Benutzerautorisierung der Sicherheitsappliance
- Konfigurationsleitfaden für die CLI der Cisco ASA-Serie 9.1
- Administratoranleitung für Cisco Identity Services Engine, Version 2.0
- <u>Technischer Support und Dokumentation Cisco Systems</u>