

Register a Device with a FireSIGHT Management Center



Document ID: 118596

Contributed by Nazmul Rajib and John Groetzinger, Cisco TAC Engineers.

Oct 09, 2014

Contents

Introduction

Configuration

Step 1: Add a FireSIGHT Management Center to Your Managed Device

Using the Web User Interface of FirePOWER Appliance

Using the Command Line Interface (CLI)

Step 2: Add a Device to the FireSIGHT Management Center

Related Articles

Introduction

When you reimage or purchase a new FireSIGHT Management Center, you need to register it with a device that will be inspecting traffic. You can register a FireSIGHT Management Center with FirePOWER appliances, NGIPS Virtual appliances, ASA running FirePOWER services, etc. This article describes how to register a device with a FireSIGHT Management Center.

Configuration

Step 1: Add a FireSIGHT Management Center to Your Managed Device

Using the Web User Interface of FirePOWER Appliance

Note: There is no web interface available on an NGIPS virtual device, or on the FirePOWER Services running on ASA. A web user interface is available on a FireSIGHT Management Center and on the FirePOWER Appliances. If you have a virtual device or ASA with FirePOWER Service, follow the instructions for adding a manager from the CLI.

1. Navigate to *System > Local > Registration*.
2. Click on the *Add Manager* button at the top right of the screen.
3. In the *Management Host* field, enter the IP address or the hostname of the Management Center that is going to manage the device. Enter a unique alphanumeric *Registration Key* you want to use to register this device.
4. After filling out the information, click *Save*.

Using the Command Line Interface (CLI)

1. Connect to the CLI of the device that you want register with FireSIGHT Management Center.

Tip: On ASA 5512–X through ASA 5555–X, you can open a console session to the module from the ASA CLI using the session sfr console command. In multiple context mode, session from the system execution space.

2. Log in with the username admin or another username that has the CLI configuration (Administrator) access level.

3. At the prompt, register the device to a FireSIGHT Management Center using the configure manager add command.

Note: A unique alphanumeric registration key is always required to register a device to a FireSIGHT Management Center. This is a simple key that you specify, and is not the same as a license key.

The command has the following syntax:

```
> configure manager add <hostname | IPv4_address | IPv6_address | DONTRESOLVE>  
  reg_key <nat_id>
```

In the above syntax,

- <hostname | IPv4_address | IPv6_address | DONTRESOLVE> specifies either the fully qualified host name or IP address of the FireSIGHT Management Center. If the FireSIGHT Management Center is not directly addressable, use DONTRESOLVE.
- reg_key is a unique alphanumeric registration key required to register a device to the FireSIGHT Management Center.
- nat_id is an optional alphanumeric string used during the registration process between the FireSIGHT Management Center and the device. It is required if the hostname is set to DONTRESOLVE.

In most cases, you must provide the FireSIGHT Management Center's hostname or the IP address along with the registration key, for example:

```
> configure manager add DC_IP_Address my_reg_key
```

However, if the device and the FireSIGHT Management Center are separated by a NAT device, enter a unique NAT ID along with the registration key, and specify DONTRESOLVE instead of the hostname, for example:

```
configure manager add DONTRESOLVE my_reg_key my_nat_id
```

In the following example, there is no NAT boundary between the FireSIGHT Management Center and the managed device, and **123456** is used as a registration key.

```
> configure manager add 192.0.2.2 123456  
Manager successfully configured.
```


Step 2: Add a Device to the FireSIGHT Management Center

1. Log into the web user interface of the Management Center. Click the **Devices** tab at the top of the page.



2. Click **Add** which is located at the top right. A drop down list appears. Click **Add Device**. A window pops up

in the middle of the screen requesting the device information.



3. In the **Host** field, enter the IP address of the device.

4. In the **Registration Key** field, enter the one-time registration key that you specified earlier.

5. Set the rest of the options to your preference. If you used a NAT ID, click on **Advanced** to expand it and enter the same NAT ID in the **Unique NAT ID** field.

A screenshot of a dialog box titled 'Add Device' in red text. The dialog box has a close button (X) and a help button (?) in the top right corner. It contains several input fields and checkboxes. The 'Host' field contains '192.0.2.3'. The 'Registration Key' field contains '123456'. The 'Group' dropdown menu is set to 'None'. The 'Access Control Policy' dropdown menu is set to 'Default Intrusion Prevention'. Below these fields is a section titled 'Licensing' in red, which contains five checkboxes: 'Protection:', 'Control:', 'Malware:', 'URL Filtering:', and 'VPN:', all of which are currently unchecked. Below the 'Licensing' section is an expanded section titled 'Advanced' in red, which contains two fields: 'Unique NAT ID:' with an empty text box, and 'Transfer Packets:' with a checked checkbox. At the bottom of the dialog box are two buttons: 'Register' and 'Cancel'.

6. Click **Register**. You should now be able to manage your device from the FireSIGHT Management Center.

Related Articles

- [Initial Configuration Steps of FireSIGHT Systems](#)

Updated: Oct 09, 2014

Document ID: 118596
