# **Renew RCM Kubernetes Certificates**

### Contents

Introduction Prerequisite Check if the certificates are expired Renew the certificates Check again if the certificates are renewed Modify kubelet.conf Copy admin.conf Reboot the system Make sure if kubectl command works

### Introduction

This document describes the procedure to renew Kubernetes certificates in Cisco 5G RCM(Redundancy Configuration Manager).

# Prerequisite

If it is RCM High Availability setup, the procedure must be executed on standby RCM first, then perform a switchover, and run the procedure on new standby RCM. If no RCM High Availability is available, UP redundancy is not available during RCM reboot which is part of certificates renewal process.

# Check if the certificates are expired

To make sure if certificates are expired, run sudo kubeadm alpha certs check-expiration.

ubuntu@rcm:~\$ sudo kubeadm alpha certs check-expiration CERTIFICATE EXPIRES RESIDUAL TIME EXTERNALLY MANAGED admin.conf Oct 31, 2024 03:34 UTC <invalid> no apiserver Oct 31, 2024 03:34 UTC <invalid> no apiserver-etcd-client Oct 31, 2024 03:34 UTC <invalid> no apiserver-kubelet-client Oct 31, 2024 03:34 UTC <invalid> no controller-manager.conf Oct 31, 2024 03:34 UTC <invalid> no etcd-healthcheck-client Oct 31, 2024 03:34 UTC <invalid> no etcd-peer Oct 31, 2024 03:34 UTC <invalid> no etcd-server Oct 31, 2024 03:34 UTC <invalid> no scheduler.conf Oct 31, 2024 03:34 UTC <invalid> no

# **Renew the certificates**

Run sudo kubeadm alpha certs renew all to renew the certificates.

ubuntu@rcm:~\$ sudo kubeadm alpha certs renew all certificate embedded in the kubeconfig file for the admin to use and for kubeadm itself renewed certificate for serving the Kubernetes API renewed certificate the apiserver uses to access etcd renewed certificate for the API server to connect to kubelet renewed certificate embedded in the kubeconfig file for the controller manager to use renewed certificate for liveness probes to healtcheck etcd renewed certificate for etcd nodes to communicate with each other renewed certificate for serving etcd renewed certificate for the front proxy client renewed certificate embedded in the kubeconfig file for the scheduler manager to use renewed

### Check again if the certificates are renewed

Run sudo kubeadm alpha certs check-expiration to check if the certificates are renewed.

ubuntu@rcm:~\$ sudo kubeadm alpha certs check-expiration CERTIFICATE EXPIRES RESIDUAL TIME EXTERNALLY MANAGED admin.conf Nov 01, 2025 03:34 UTC 364d no apiserver Nov 01, 2025 03:34 UTC 364d no apiserver-etcd-client Nov 01, 2025 03:34 UTC 364d no controller-manager.conf Nov 01, 2025 03:34 UTC 364d no etcd-healthcheck-client Nov 01, 2025 03:34 UTC 364d no etcd-peer Nov 01, 2025 03:34 UTC 364d no etcd-server Nov 01, 2025 03:34 UTC 364d no front-proxy-client Nov 01, 2025 03:34 UTC 364d no scheduler.conf Nov 01, 2025 03:34 UTC 364d no

#### Modify kubelet.conf

Prior to kubeadm version 1.17, there is a need to manually modify kubelet.conf. Replace clientcertificate-data and client-key-data with this.

/etc/kubernetes/kubelet.conf

```
client-certificate:/var/lib/kubelet/pki/kubelet-client-current.pem
client-key: /var/lib/kubelet/pki/kubelet-client-current.pem
```

### Copy admin.conf

Copy admin.conf to overwrite .kube/config.

sudo cp /etc/kubernetes/admin.conf ~/.kube/config

#### Reboot the system

sudo reboot

#### Make sure if kubectl command works

After the reboot, make sure if kubectl command works fine.

ubuntu@rcm:~\$ kubectl get node NAME STATUS ROLES AGE VERSION rcm Ready master,oam 16d v1.15.12