



## **Cisco SCMS SM DHCP Lease Query LEG Reference Guide**

Release 3.1.5

March 9, 2009

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

Customer Order Number:  
Text Part Number: OL-12486-03

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

CCDE, CCENT, Cisco Eos, Cisco HealthPresence, the Cisco logo, Cisco Lumin, Cisco Nexus, Cisco StadiumVision, Cisco TelePresence, Cisco WebEx, DCE, and Welcome to the Human Network are trademarks; Changing the Way We Work, Live, Play, and Learn and Cisco Store are service marks; and Access Registrar, Aironet, AsyncOS, Bringing the Meeting To You, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, CCVP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Collaboration Without Limitation, EtherFast, EtherSwitch, Event Center, Fast Step, Follow Me Browsing, FormShare, GigaDrive, HomeLink, Internet Quotient, IOS, iPhone, iQuick Study, IronPort, the IronPort logo, LightStream, Linksys, MediaTone, MeetingPlace, MeetingPlace Chime Sound, MGX, Networkers, Networking Academy, Network Registrar, PCNow, PIX, PowerPanels, ProConnect, ScriptShare, SenderBase, SMARTnet, Spectrum Expert, StackWise, The Fastest Way to Increase Your Internet Quotient, TransPath, WebEx, and the WebEx logo are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0812R)

Any Internet Protocol (IP) addresses used in this document are not intended to be actual addresses. Any examples, command display output, and figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

*Cisco SCMS SM DHCP Lease Query LEG Reference Guide*  
© 2009 Cisco Systems, Inc. All rights reserved.



# CONTENTS

## **Preface**   iii

- Document Revision History   iii
- Organization   iv
- Related Publications   v
- Conventions   v
- Obtaining Documentation and Submitting a Service Request   vi

---

## **CHAPTER 1**

### **About the DHCP Lease Query LEG**   1-1

- Information About the DHCP Lease Query LEG   1-1
  - DHCP Lease Query LEG Operation   1-1
  - Terms and Concepts   1-3
    - LEG (Login Event Generator)   1-3
    - Cable/Satellite Modem   1-3
    - CPE (Customer Premise Equipment)   1-3
    - DHCP Lease Query Transaction   1-3
    - Subscriber Mappings   1-4
    - Pull-request   1-4
    - Subscriber Domain   1-4
    - Subscriber Package   1-4
- Information About DHCP Lease Query LEG Functionality   1-4
  - DHCP Lease Query LEG Process   1-5
  - DHCP Lease Query Transaction   1-5
  - Installation and Usage   1-5
  - Package Contents   1-6

---

## **CHAPTER 2**

### **Subscriber Manager Integration**   2-1

- How to Install, Uninstall, and Upgrade the DHCP Lease Query LEG   2-1
  - Installing the DHCP Lease Query LEG on the SM   2-1
  - Uninstalling the DHCP Lease Query LEG from the SM Server   2-2
  - Upgrading the DHCP Lease Query LEG   2-2

---

## **CHAPTER 3**

### **Subscriber Manager Integration - Configuration**   3-1

- Information About Configuring the DHCP Lease Query LEG   3-1
  - Configuring the DHCP Lease Query LEG   3-1

- Configuring Policy Association 3-4
  - Dynamic Assignment of Policy Information 3-4
  - Dynamic Assignment of Policy Information Example 3-6
  - Static Assignment of Policy Information 3-7
- Information About the DHCP Lease Query LEG CLU 3-7
  - Viewing the DHCP Lease Query LEGStatus 3-8
  - Viewing the DHCP Lease Query LEG Statistics 3-8
  - Viewing the DHCP Lease Query LEG Version 3-8

**CHAPTER 4**

**SCE Integration 4-1**

- How to Install, Uninstall, and Upgrade the DHCP Lease Query LEG 4-1
  - Installing the DHCP Lease Query LEG on the SCE 4-1
  - Uninstalling the DHCP Lease Query LEG from the SCE Device 4-2
  - Upgrading the DHCP Lease Query LEG 4-2

**CHAPTER 5**

**SCE Integration - Configuration 5-1**

- Configuring the DHCP Lease Query LEG on the SCE 5-1
- Information About the DHCP Lease Query LEG CLI 5-1
  - Configuration CLI 5-1
  - Show CLI 5-2

**APPENDIX A**

**DHCP Forwarder Application A-1**

- Installing the DHCP Forwarder A-1
- Uninstalling the DHCP Forwarder A-2
- DHCP Forwarder VCS Agent A-2
  - Adding a DHCP Forwarder Resource A-2
  - Removing a DHCP Forwarder Resource A-4



## Preface

---

This document describes the concept of a DHCP Login Event Generator (LEG) and explains how to install and configure it on the SCMS Subscriber Manager (SM) platform and on a Service Control Engine.



**Note**

---

This document assumes a basic familiarity with the Cisco SCMS Subscriber Management, subscriber integration concepts, and the DHCP protocol.

---

For complete information about Cisco's SCMS subscriber integration concept, see the *Cisco SCMS Subscriber Manager User Guide*.

This document is intended for system administrators and system integrators who are familiar with DHCP Lease Query concepts and the Cisco Service Control Subscriber Management and Subscriber Integration concepts.

## Document Revision History

Cisco Service Control Release	Part Number	Publication Date
Release 3.1.5	OL-12486-03	March 9, 2009

Description of Changes

- Updated the Preface boiler plate information

Cisco Service Control Release	Part Number	Publication Date
Release 3.1.5	OL-12486-02	November, 2007

Description of Changes

- Updated for 3.1.5 release.

Cisco Service Control Release	Part Number	Publication Date
Release 3.1.0	OL-12486-01	May, 2007

## Description of Changes

- Reorganization of chapters to separate coverage of installation on an SM and on an SCE. See [Organization, page iv](#), [Subscriber Manager Integration, page 1](#), and [SCE Integration, page 1](#).
- The LEG now supports multiple policies. See [Dynamic Assignment of Policy Information, page 4](#).

Cisco Service Control Release	Part Number	Publication Date
Release 3.0.5	OL-7808-04	November, 2006

## Description of Changes

- Changes in how to dynamically assign package information. See [Dynamic Assignment of Policy Information, page 4](#).

Cisco Service Control Release	Part Number	Publication Date
Release 3.0.3	OL-7808-03	May, 2006

## Description of Changes

- Updated documentation for release 3.0.3.

Cisco Service Control Release	Part Number	Publication Date
Release 3.0	OL-7808-02	December, 2005

## Description of Changes

- Reorganization of documentation. No major changes or new features were added to this revision.

Cisco Service Control Release	Part Number	Publication Date
Release 2.5.7	OL-7808-01	May, 2005

## Description of Changes

- This is the first version of this document.

## Organization

The major sections of this guide are as follows:

Chapter	Title	Description
Chapter 1	<a href="#">About the DHCP Lease Query LEG, page 1</a>	Describes the Subscriber Manager DHCP Lease Query LEG software module and the terms and concepts used in this guide. It also provides a description of the DHCP Lease Query LEG process and transactions
Chapter 2	<a href="#">Subscriber Manager Integration, page 1</a>	Details the procedures for installing, uninstalling, and upgrading the software on the Subscriber Manager.
Chapter 3	<a href="#">Subscriber Manager Integration - Configuration, page 1</a>	Details the procedures for configuring and using the software on the Subscriber Manager. It also describes the command-line utility.
Chapter 4	<a href="#">SCE Integration, page 1</a>	Details the procedures for installing, uninstalling, and upgrading the software on an SCE device.
Chapter 5	<a href="#">SCE Integration - Configuration, page 1</a>	Details the procedures for configuring and using the software on an SCE device. It also describes the CLI.
Appendix A	<a href="#">DHCP Forwarder Application, page 1</a>	Describes the DHCP Forwarder application, installation instructions, and adding and removing a resource.

## Related Publications

Use this *Cisco SCMS SM DHCP Lease Query LEG Reference Guide* in conjunction with the following Cisco documentation:

- *Cisco SCMS Subscriber Manager User Guide*

## Conventions

This document uses the following conventions:

Convention	Description
<b>boldface font</b>	Commands and keywords are in <b>boldface</b> .
<i>italic font</i>	Arguments for which you supply values are in <i>italics</i> .

Convention	Description
[ ]	Elements in square brackets are optional.
{x   y   z}	Alternative keywords are grouped in braces and separated by vertical bars.
[x   y   z]	Optional alternative keywords are grouped in brackets and separated by vertical bars.
string	A nonquoted set of characters. Do not use quotation marks around the string, or the string will include the quotation marks.
<code>screen font</code>	Terminal sessions and information that the system displays are in <code>screen font</code> .
<b>boldface screen font</b>	Information you must enter is in <b>boldface screen font</b> .
<i>italic screen font</i>	Arguments for which you supply values are in <i>italic screen font</i> .
<>	Nonprinting characters, such as passwords, are in angle brackets.
[ ]	Default responses to system prompts are in square brackets.
!, #	An exclamation point (!) or a pound sign (#) at the beginning of a line of code indicates a comment line.

**Note**

Means *reader take note*. Notes contain helpful suggestions or references to materials not covered in this manual.

Means *reader be careful*. In this situation, you might do something that could result in equipment damage or loss of data.

Means *reader be warned*. In this situation, you might do something that could result in bodily injury.

## Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, submitting a service request, and gathering additional information, see the monthly *What's New in Cisco Product Documentation*, which also lists all new and revised Cisco technical documentation, at:

<http://www.cisco.com/en/US/docs/general/whatsnew/whatsnew.html>

Subscribe to the *What's New in Cisco Product Documentation* as a Really Simple Syndication (RSS) feed and set content to be delivered directly to your desktop using a reader application. The RSS feeds are a free service and Cisco currently supports RSS Version 2.0.





# CHAPTER 1

## About the DHCP Lease Query LEG

---

This module describes the Subscriber Manager DHCP Lease Query LEG software module and the terms and concepts relevant to the DHCP Lease Query LEG.

- [Information About the DHCP Lease Query LEG, page 1-1](#)
- [Information About DHCP Lease Query LEG Functionality, page 1-4](#)

## Information About the DHCP Lease Query LEG


The SCMS SM DHCP Lease Query LEG is a software module that handles pull-requests from the different SCE platforms in the network. The LEG queries the DHCP server using a DHCP Lease-Query transaction. The DHCP Lease Query LEG can be run on the SM server or on the SCE device. If you use an SM, the LEG must be used on the SM, not on the SCE.

- [DHCP Lease Query LEG Operation, page 1-1](#)
- [Terms and Concepts, page 1-3](#)

## DHCP Lease Query LEG Operation

[Figure 1-1](#) represents the operation of the DHCP Lease Query LEG:


**Figure 1-1 DHCP Lease Query LEG Operation - SM Installation**



The subscriber's traffic (1) triggers a pull-request from the SCE (2). The SM receives the request for processing. If the SM does not find a subscriber with a matching IP address in the subscriber database, it passes the pull-request to the DHCP Lease Query LEG (3). The LEG queries the DHCP server. If the server finds a match for the IP address in its database, the server replies with the subscriber information (4). The LEG performs a login operation (5). This operation updates the subscriber database based on the received information and logs the subscriber into the SCE (6), which triggered the pull-request.

If desired, install the DHCP Lease Query LEG directly on the SCE device to integrate the SCE with DHCP servers without the use of an SM server. [Figure 1-2](#) represents the operation of the LEG when installed on the SCE device:

**Figure 1-2 DHCP Lease Query LEG Operation - SCE Installation**



The subscriber's traffic (1) triggers a pull-request from the SCE (2). The Lease Query LEG receives the request and queries the DHCP server. If the server finds a match for the IP address in its database, the server replies with the subscriber information (3). Based on the received information, the LEG responds to the SCE with a pull-response, which includes the subscriber ID and the IP address lease-time returned from the DHCP server (4).

**Note**

An Internet Engineering Task Force (IETF) standard defines the DHCP Lease-Query transaction. The LEG supports the RFC 4388 standard. For more information, see the IETF website.

## Terms and Concepts

The following terms and concepts are necessary to understand the DHCP Lease Query LEG and SM configuration and operation. Additional information can be found in the *Cisco SCMS Subscriber Manager User Guide*.

- [LEG \(Login Event Generator\), page 1-3](#)
- [Cable/Satellite Modem, page 1-3](#)
- [CPE \(Customer Premise Equipment\), page 1-3](#)
- [DHCP Lease Query Transaction, page 1-3](#)
- [Subscriber Mappings, page 1-4](#)
- [Pull-request, page 1-4](#)
- [Subscriber Domain, page 1-4](#)
- [Subscriber Package, page 1-4](#)

### LEG (Login Event Generator)

A software component that performs subscriber login and logout operations on the SM/SCE. The LEG handles dynamic subscriber integration.

### Cable/Satellite Modem

A data modem that provides Internet access over cable and satellite networks. The modem usually corresponds to a single subscriber of the Internet Service Provider (ISP).

### CPE (Customer Premise Equipment)

Any equipment that an end-user can connect to the network through a modem. The end-user usually owns multiple CPE devices that are used to connect to the Internet through a single modem.

### DHCP Lease Query Transaction

The DHCP Lease Query transaction is a DHCP transaction with special message types that enable, among other things, clients to query DHCP servers regarding the owner and the lease-expiration-time of an IP address.

An IETF standard defines the DHCP Lease-Query transaction. For more information, see the IETF website.

## Subscriber Mappings

The SCE platform requires mappings between the network IDs (IP addresses) of the flows it encounters and the subscriber IDs. The SM database contains the network IDs that map to the subscriber IDs. The SCE network-ID-to-subscriber mappings are constantly updated from the SM database.

The main function of the DHCP Lease Query LEG is to provide the SM/SCE with network-ID-to-subscriber mappings in real time.

## Pull-request

A message sent from an SCE device to the SM or the LEG when it identifies the use of a new subscriber IP address in the network. The SM uses the IP address provided in this message to query the database to retrieve the subscriber data of the subscriber associated with this address and to send its data to the SCE.

## Subscriber Domain

The SM provides the option of partitioning SCE platforms and subscribers into subscriber domains. A subscriber domain is a group of SCE platforms that share a group of subscribers. Subscriber domains can be configured using the SM configuration file and can be viewed using the SM Command-Line Utility (CLU).

For additional information about domains and domain aliases, see the “Configuration File Options” chapter of the *Cisco SCMS Subscriber Manager User Guide*.

## Subscriber Package

A subscriber policy package usually defines the policy enforced by Cisco SCMS solutions on each subscriber. The DHCP Lease Query LEG can handle the package ID in any of the following ways:

- Set the package ID according to configurable options of the DHCP initial login or lease extension transactions
- Set the package ID using a constant default value
- Leave the package ID unset

For additional information, see [Configuring Policy Association](#), and the *Cisco Service Control Application for Broadband (SCA BB) User Guide*.

# Information About DHCP Lease Query LEG Functionality

- [DHCP Lease Query LEG Process](#), page 1-5
- [DHCP Lease Query Transaction](#), page 1-5
- [Installation and Usage](#), page 1-5
- [Package Contents](#), page 1-6

## DHCP Lease Query LEG Process

The LEG processes DHCP Lease-Query transactions to the DHCP server using the IP address indicated in the pull-request from the SCE. The DHCP server replies whether there is an active lease (DHCPLEASEACTIVE message) for this IP address and provides information about the subscriber associated with this IP address according to a list of options requested by the LEG. By default, the LEG requests the lease time and the modem MAC and adds package association related options if needed.

The DHCP Lease Query LEG supports up to two redundant DHCP servers. The LEG identifies a server failure by counting the consecutive requests that time out. After a configurable threshold of timed-out requests, the LEG starts to send the requests to the recently activated server, which was previously in standby. The LEG does not return to the failed server until the activated server fails.

When installing the LEG on the SM server, it runs with the privileges assigned to the user **pcube** on this machine. On UNIX platforms, because only the super-user (root) can open ports under 1024, the LEG cannot open the DHCP ports. To solve this problem, a simple application is supplied with the LEG, which forwards the DHCP packets between the LEG and the DHCP servers. This application is the DHCP Forwarder, which is described in the [DHCP Forwarder Application](#) module.

When installing the LEG on the SCE device, there is no need to use the DHCP Forwarder application.

## DHCP Lease Query Transaction

The DHCP Lease Query transaction is a DHCP transaction where the client (LEG) sends a DHCPLEASEQUERY message to the server, indicating the information it wants to query. The LEG only queries the IP address. The server can reply with several types of messages; for example a DHCPLEASEACTIVE message means that an active lease was found and the request information is supplied, or a DHCPLEASEUNASSIGNED message means this IP is currently not assigned to any subscriber.

The following is a detailed description of the attributes extracted from the *DHCP Lease Query transaction*:

- **Subscriber ID**—By default, the subscriber ID is the modem MAC address, which you extract from option 82 (Remote ID sub-option of the DHCP Relay Agent Information Option). Therefore, the DHCP server must support and store option 82 for each Customer Premise Equipment (CPE). This default can be overwritten by configuration. Furthermore, the LEG can assign the IP address as a fallback if the option does not exist in the server's response. This fallback is disabled by default.
- **Lease time**—The assigned IP is added to the SM or SCE database with a lease time taken from option 51. Note that if option 51 does not appear in the DHCPLEASEACTIVE reply, an infinite lease time is assigned for this IP address.
- **Package**—Configurable options in the DHCP message determine how to assign the package information. The LEG includes a component that converts the package information data from the DHCP packet to a subscriber package ID. If the packet does not contain package information, it is possible to log in the subscriber with a default package, or log in the subscriber with no package information at all. The package options are assumed to be encoded as strings.

After extracting the preceding information, the LEG logs the subscriber into the SM/SCE.

## Installation and Usage

The DHCP Lease Query LEG is an external component (PQI file) that can be installed on the SM or SCE device.

For information about installing and using the DHCP Lease Query LEG on the SM, see [Subscriber Manager Integration](#) and [Subscriber Manager Integration - Configuration](#). For information about installing and using the DHCP Lease Query LEG on the SCE, see [SCE Integration](#) and [SCE Integration - Configuration](#).

## Package Contents

The DHCP Lease Query LEG distribution is part of the SM LEG distribution. The DHCP Forwarder application distribution and installation script are also part of the SM LEG distribution.

The DHCP Lease Query LEG uses the DHCP Forwarder application on UNIX machines. For more information, see [DHCP Forwarder Application, page A-1](#).

The LEG installation package includes a set of configuration files and command-line utilities for the LEG.

The SCMS SM LEG distribution file contains the DHCP Lease Query LEG distribution, which is located in the Lease\_Query\_LEG directory. Cisco supplies a DHCP Lease Query LEG distribution package. [Table 1-1](#) describes the package contents:

**Table 1-1 File Layout of the DHCP Lease Query LEG Distribution Package**

Root	Folder (under root)	File name	Notes
<i>pkg-ext-dir</i>			
		Install	LEG installation procedure description
		install-forwarder.sh	DHCP Forwarder installation script
		linux-def.sh	Linux-specific definitions
		solaris-def.sh	Solaris-specific definitions
		dhcp_forwarder.tar.gz	DHCP Forwarder distribution
		sm-common.sh	General utility script
	sce		
		dhcp_pkg.cfg	Default configuration file for package association
		leaseq.pqi	DHCP Lease Query LEG distribution
	sm		
		leaseq.pqi	DHCP Lease Query LEG distribution



**Note**

The directory to which the distribution is extracted is referred to as *pkg-ext-dir*.



## CHAPTER 2

# Subscriber Manager Integration

---

This module describes the procedures for installing, uninstalling, and upgrading the DHCP Lease Query LEG on the SM.



### Note

---

This module is relevant if you are using the Subscriber Manager server on your network. You should install the DHCP Lease Query LEG on the SM server and not on the SCE device.

---

## How to Install, Uninstall, and Upgrade the DHCP Lease Query LEG

- [Installing the DHCP Lease Query LEG on the SM, page 2-1](#)
- [Uninstalling the DHCP Lease Query LEG from the SM Server, page 2-2](#)
- [Upgrading the DHCP Lease Query LEG, page 2-2](#)

### Installing the DHCP Lease Query LEG on the SM

---

**Step 1** Install the DHCP Forwarder application

The DHCP Forwarder application bridges between the LEG and the DHCP server. See [Installing the DHCP Forwarder, page A-1](#).

**Step 2** Install the PQI file of the DHCP Lease Query LEG

- a. Run the **p3inst** command-line utility (CLU) from the SM CLU directory **~pcube/sm/server/bin**

Example:

```
>p3inst --install -f leaseq.pqi
```



### Note

---

After the installation of the PQI file, the SM restarts itself automatically.

---

**Step 3** Edit the DHCP Lease Query LEG configuration files

The DHCP Lease Query LEG includes two configuration files under **~pcube/sm/server/root/config** :

- **leaseq.cfg**—Configures general attributes of the LEG

- **dhcp\_pkg.cfg**—Configures rules for policy assignment

It is recommended to edit the files according to the configuration required at first use.

- Step 4** Edit the SM configuration file **p3sm.cfg** and set the subscriber introduction mode to be pull mode

Example:

```
[SM General]
# The following parameter defines whether the SM introduces
# the subscribers to
# the SCEs immediately after the subscriber's
# login operation (push-mode) or when the SE requests
# subscriber information specifically (pull-mode).
# Optional values: [pull, push]. Default: push.
introduction_mode=pull
```

- Step 5** Load the configuration files to the SM using the **p3sm** CLU

This command-line utility loads the new configuration to the SM and activates it.

Example:

```
>p3sm --load-config
```

- Step 6** Add a resource to the Veritas Cluster Server

This can be done only on SM Cluster setups. To add a resource, see [Adding a DHCP Forwarder Resource, page A-2](#).

## Uninstalling the DHCP Lease Query LEG from the SM Server

- Step 1** Run the **p3inst** command-line utility from the SM CLU directory **~pcube/sm/server/bin**

Example:

```
>p3inst --uninstall -f leaseq.pqi
```



### Note

After the uninstall process, the SM restarts itself automatically.

- Step 2** Uninstall the DHCP Forwarder Veritas Cluster Agent.

This can be done only on SM Cluster setups. See [Removing a DHCP Forwarder Resource, page A-4](#).

- Step 3** Uninstall the DHCP Forwarder application. See [Uninstalling the DHCP Forwarder, page A-2](#).

## Upgrading the DHCP Lease Query LEG

The DHCP Lease Query LEG must be upgraded as part of the SM upgrade process, because previous versions of the DHCP Lease Query LEG are incompatible with the SM 3.x version. The upgrade for the DHCP Lease Query LEG should be performed together with the upgrade process of the SM.

- Step 1** Backup the configuration files of the DHCP Lease Query LEG.



The original configuration files are deleted by the uninstall process in the next step.

**Step 2** Uninstall the DHCP Lease Query LEG by running the **p3inst** CLU

Example:

```
>p3inst --uninstall -f lease-query-pqi
```



---

**Note** After the uninstall process, the SM restarts automatically.

---

**Step 3** Perform an upgrade of the SM

The SM upgrade procedure is described in the *Cisco SCMS Subscriber Manager User Guide*.

**Step 4** Install the new version of the DHCP Lease Query LEG by running the **p3inst** CLU

Example:

```
>p3inst --install -f lease-query-pqi
```

**Step 5** Restore the configuration files of the DHCP Lease Query LEG

**Step 6** Load the new configuration of the SM by running the **p3sm** CLU

Example:

```
>p3sm --load-config
```

---





## CHAPTER 3

# Subscriber Manager Integration - Configuration

---

This module describes how to configure the DHCP Lease Query LEG on the SM and how to use the CLU.



### Note

This module is relevant if you are using the Subscriber Manager server on your network. You should install the DHCP Lease Query LEG on the SM server and not on the SCE device.

---

## Information About Configuring the DHCP Lease Query LEG

The DHCP Lease Query LEG on the SM is configured using two configuration files: **leaseq.cfg** (general configuration) and **dhcp\_pkg.cfg** (dynamic package association), which reside in the **~pcube/sm/server/root/config** directory.

The configuration files consist of sections headed by a bracketed section title; for example, **[DHCP-Lease-Query-LEG]**. Each section consists of several parameters having the format **parameter=value**. The number sign (“#”) at the beginning of a line signifies that it is a remark.

- [Configuring the DHCP Lease Query LEG, page 3-1](#)
- [Configuring Policy Association, page 3-4](#)
- [Information About the DHCP Lease Query LEG CLU, page 3-7](#)

## Configuring the DHCP Lease Query LEG

The following is a description of the configuration variables of **leaseq.cfg**.

The **[DHCP-Lease-Query-LEG]** section contains the following parameters:

- **start**  
Defines whether the SM runs the DHCP Lease Query LEG at startup.  
Possible values for this parameter are **yes** and **no**. The default value is **no**.  
To run the LEG, this parameter must be set to **yes**.
- **max\_concurrent\_sessions**  
Defines the number of concurrent sessions the LEG should support. This parameter limits the resources used by this module.  
Possible values for this parameter are integers. The default value is 256.

- **dhcp\_servers**  
Defines to which DHCP servers the LEG can send requests.  
You must enter the IP addresses or hostnames of the DHCP servers separated by commas.
- **server\_port**  
Defines the UDP port to which the DHCP servers listen and the Lease Query messages are sent. It is recommended to use 9067 when working with the DHCP Forwarder. The default value is 9067.
- **listening\_port**  
Defines the UDP port to which the LEG listens and the Lease Query replies are sent. It is recommended to use 9068 when working with the DHCP Forwarder. The default value is 9068.
- **client\_port**  
Defines the UDP port that the LEG uses when sending Lease Query messages to the DHCP servers. It is recommended to use 8068 when working with the DHCP Forwarder. The default value is 8068.
- **client\_ip\_address**  
Defines the source IP address of the lease-query packets sent to the DHCP servers. The giaddr field of the DHCP packet also uses this IP address. This parameter is useful for machines with multiple network interfaces.  
The default value is the loopback IP address of the machine.
- **support\_auto\_logout**  
Defines whether the LEG should query the DHCP servers whenever the auto-logout mechanism identifies an expired lease.  
Possible values for this parameter are **true** and **false**. The default value is **false**.
- **use\_forwarder**  
Defines whether the LEG utilizes the DHCP Forwarder application on the local machine.  
Possible values for this parameter are **true** and **false**. The default value is **true**.
- **fail\_over\_criteria**  
Defines the number of consecutive request failures (timeouts) that triggers a fail-over. Since the queries are not answered when the server fails, these queries will time out. The consecutive timed-out queries are counted and when they reach this threshold, the second server is set as the active server. The default value is 3.

**Note**


---

The **session\_timeout** parameter affects how long it will take to detect a failed server. Only when the configured amount of queries fail will the fail-over process be triggered.

---

- **log\_timed\_out\_queries**  
Controls log messages regarding timed-out queries.  
Possible values for this parameter are **true** or **false**. The default value is **true**.
- **log\_failed\_queries**  
Controls log messages regarding queries that are not sent.  
Possible values for this parameter are **true** or **false**. The default value is **true**.
- **log\_all\_queries**  
Controls log messages regarding each query sent and any reply received.

Possible values for this parameter are **true** or **false**. The default value is **false**.

Use this parameter only for troubleshooting.

- log\_login\_failures

Controls log messages regarding replies that did not result in the login of a subscriber to the SM.

Possible values for this parameter are **true** or **false**. The default value is **true**.

The [**Subscriber ID**] section defines the functionality of how the LEG handles the subscriber ID. The subscriber ID can be taken from a DHCP option, with the ability to fallback to using the allocated IP address as the subscriber ID. This section contains the following parameters:

- dhcp\_option

Defines which DHCP option to use as the subscriber ID. The format of this parameter is the option number itself; or for DHCP options that have sub-options, the format is the DHCP option and sub-option type, separated by a colon. For example: 43:123 or 61. The default value is 82:2 (Relay-Agent-Information using the Remote-ID information).

- dhcp\_option\_type

Defines the format type of the DHCP option defined by the **dhcp\_option** parameter.

Optional values are **binary**, indicating a binary string converted to an ASCII hexadecimal string; or **string**, indicating an ASCII string. The default value is **binary**.

- default\_id

Defines whether in cases where the dhcp\_option is not found in the DHCP packet, the LEG should fall back to a different way of defining the subscriber ID. The supported fallbacks are:

- ip—Use the allocated IP address to create a subscriber ID in the format of: IP\_aaa.bbb.ccc.ddd
- Not setting this parameter—No fallback. No login will be performed.

- By default, this parameter is not set.

The [**DHCP-Lease-Query-Ids**] section contains the message type numbers of the different Lease Query transaction message types. This is necessary, because the DHCP Lease Query definition is an IETF draft. This section contains the following parameters:

- lease\_query

Defines the DHCPLEASEQUERY message type value. The default value is 13.

- lease\_active

Defines the DHCPLEASEACTIVE message type value. The default value is 16.

The following is a sample configuration file:

```
[DHCP-Lease-Query-LEG]
start=yes
dhcp_servers = 198.1.2.3, 198.5.6.7
fail_over_criteria=10
session_timeout=10
log_timed_out_queries=true
log_failed_queries=true
log_all_queries=true
log_login_failures=true
[Subscriber ID]
dhcp_option=44
dhcp_option_type=binary
[DHCP-Lease-Query-Ids]
lease_query=13
lease_active=16
```

## Configuring Policy Association



### Note

The configuration described in this section is optional.

The subscriber policy configuration in the DHCP Lease Query LEG can be handled in one of the following ways:

- Dynamic assignment of policy information using information extracted from the DHCP packet. See [Dynamic Assignment of Policy Information, page 3-4](#).
- Static assignment of a constant package ID for all subscribers who log on via the DHCP Lease Query LEG. See [Static Assignment of Policy Information, page 3-7](#).

### Dynamic Assignment of Policy Information

Dynamic assignment of policy information is supported when policy information is submitted in the DHCP packets. The LEG concatenates the desired options and creates a *policy-name*. It is possible to map, using the configuration, between the *policy-names* and the application policy parameters such as package IDs and Virtual-links. The DHCP Lease Query LEG can support multiple policies.

To extract the policy information data from the DHCP packet, use the **dhcp\_pkg.cfg** configuration file to define the option types that contain the policy information and define the conversion map of the *policy-names* to the package IDs (or any other policy) of the Service Control Application for Broadband (SCA BB).

The LEG is able to add additional data to the login operation based on the LEG configuration. This data is added as a key-value pair. Other modules in the login chain can use this data, such as the SOAP LEG (see the *Cisco SCMS SM SOAP LEG Reference Guide*). This data can be created by concatenating the data of several DHCP options and can be given a user-defined label.

The **[DHCP.Policy.XXX]** sections contain the following parameters:

- **options\_order\_for\_policy\_name**  
Defines the DHCP options that contain the policy association information and defines the order of concatenation of the data. The DHCP header field called giaddr (Relay-Agent IP) is also supported; it requires the use of the type integer in the **option\_type** parameter.  
This parameter has no default value.  
The format is: **option[:subtype],option[:subtype],giaddr**
- **options\_type**  
Defines the format type of the DHCP options and fields defined by the **options\_order\_for\_policy\_name** parameter.  
Possible values for this parameter are **binary** (a binary string that is converted to an ASCII hexadecimal string), **string** (an ASCII string), or **integer** (a 4-byte integer converted to an IP address string in dotted notation). Order the list in the same way as **options\_order\_for\_policy\_name**.  
This parameter has no default value.
- **name\_seperator\_value**

Defines the separator character to use between two options when concatenating them to each other to create the policy name. Any character is accepted. The default value is '\_'.

- `use_default`

Determines whether to use a default policy when no policy information can be extracted from the DHCP data, such as the configurable options are missing or no options were configured.

Possible values for this parameter are **true** or **false**. The default value is **false**.

- `default_policy`

Defines the default policy ID to use if no policy information is extracted from the DHCP data. This parameter is relevant only if the **use\_default** parameter is set to **true**.

Possible values for this parameter are any integer number. This parameter has no default value.

- `allow_login_with_no_policy`

Defines whether to perform a login without policy information when no policy information can be extracted from the DHCP data and the **use\_default** parameter is set to **false**.

This parameter is relevant only if the **use\_default** parameter is set to **false**.

Possible values for this parameter are **true** or **false**. The default value is **true**.

- `policy_property_name`

Defines the name of the application property that contains the policy information. This parameter has no default value.



**Note**

The **policy\_property\_name** parameter is case sensitive and must be written exactly as defined by the SCA BB Console. For example, **packageId**, **monitor**, **upVlinkId**, or **downVlinkId**.

- `log_all`

Defines whether to write detailed user-log messages for all policy association events.

Possible values for this parameter are **true** or **false**. The default value is **false**.

- `log_default_assignment`

Defines whether to write a user-log message for every assignment of the default value (as defined by the **default\_policy** parameter).

Possible values for this parameter are **true** or **false**. The default value is **false**.

- `mapping_table.<policy_name>`

Multiple entries containing the information to convert from the policy information as it appears in the DHCP packet to the policy property value to be used by the SCA BB application.

These entries do not have default values.



**Note**

The `policy_name` is case sensitive and must be written exactly as it exists in the DHCP packets.

The **[Additional Data]** section of the configuration file contains the following parameters:

- `label_options`

Defines which DHCP option to extract to add to the login operation.

Possible values are the option number or, in the case of DHCP options with sub-options, the option and sub-option separated by a colon. For example, 43:123 or 61.

There is no default value for this parameter.

- `label_keys`

Defines the keys that should mark the DHCP options defined by the `label_options` parameter.

There is no default value for this parameter.

- `label_options_type`

Defines the format type of the DHCP option defined by the `label_options` parameter.

Possible values for this parameter are **binary** (a binary string that is converted to an ASCII hexadecimal string) or **string** (an ASCII string).

The default value is **binary**.

## Dynamic Assignment of Policy Information Example

Suppose that the policy information appears inside option 43 (Vendor Specific Option) of the DHCP packet and that both subtypes, 102 and 101, are in use. Configure the `options_order_for_policy_name` parameter as follows:

```
options_order_for_policy_name=43:102,43:101
```

Suppose that option 43 with subtype 102 contains the type of package (gold, silver, or bronze), and that option 43 with subtype 101 contains domain information (the package type has a different meaning in different domains). If the separator value is configured to the default value, configure the `mapping_table` entries as follows:

```
mapping_table.gold_domain1=11
mapping_table.gold_domain2=12
mapping_table.silver_domain1=13
mapping_table.silver_domain2=14
```

This configuration means that if the DHCP packet contains the value 'gold' inside option 43 with subtype 102, and the value 'domain1' inside option 43 with subtype 101, the package ID that will be associated to the subscriber in the SM will have the value 11.

The following configuration describes how to add the data of the Relay-Agent Circuit-Id option as additional data to the login operation:

```
[Additional Data]
label_options=82:1
label_keys=PORT_ID
label_option_type=string
```

The following is an example of the entire configuration file:

```
[DHCP.Policy.Package]
options_order_for_policy_name=43:102,43:101
name_separator_value=_
use_default=true
default_policy=1
policy_property_name=packageId
allow_login_with_no_policy=false
log_all=false
log_default_assignment=false
mapping_table.gold_domain1=11
mapping_table.gold_domain2=12
mapping_table.silver_domain1=13
mapping_table.silver_domain2=14
[Additional Data]
```



```
label_options=82:1
label_keys=PORT_ID
label_option_type=string
```

## Static Assignment of Policy Information

If the installation does not require dynamic assignment of package information, the configuration file **dhcp\_pkg.cfg** should define the default package ID and default Virtual-Link to be assigned to all the subscribers, as shown in the following example:

```
[DHCP.Policy.Package]
policy_property_name=packageId
allow_login_with_no_policy=false
use_default=true
default_policy=1
[DHCP.Policy.VirtualLinkDownstream]
policy_property_name=downVlinkId
allow_login_with_no_policy=false
use_default=true
default_policy=0
[DHCP.Policy.VirtualLinkUpstream]
policy_property_name=upVlinkId
allow_login_with_no_policy=false
use_default=true
default_policy=0
```

All other configuration parameters should not be set.

## Information About the DHCP Lease Query LEG CLU

The `p3leasequery` utility displays the DHCP Lease Query LEG configuration, status, and statistics. The command format is **p3leasequery <operation>**.

Table 3-1 lists the `p3leasequery` operations.

**Table 3-1** *p3leasequery Operations*

Operation	Description
<code>--show</code>	Displays all of DHCP Lease Query LEG configurations and status
<code>--show-statistics</code>	Displays counters of DHCP messages handled and number of logon operations performed
<code>--show-version</code>	Displays the version number of the DHCP Lease Query LEG
<code>--help</code>	Displays a list of available operations and arguments with a short explanation of their meanings

- [Viewing the DHCP Lease Query LEG Status, page 3-8](#)
- [Viewing the DHCP Lease Query LEG Statistics, page 3-8](#)
- [Viewing the DHCP Lease Query LEG Version, page 3-8](#)

## Viewing the DHCP Lease Query LEGStatus

The following is an example using the **p3leasequery** command-line utility with the **show** operation:

```
>p3leasequery --show
DHCP Lease-Query LEG:
=====
Active:      true
DHCP Servers:
Active:    10.1.2.3
Standby:  N/A
Session timeout: 20
Fail over criteria: 3
Subscriber ID:
Option:    82:2
Format:   binary
Fallback: none
Command terminated successfully
>
```

## Viewing the DHCP Lease Query LEG Statistics

The following is an example of the **p3leasequery** command-line utility using the **show-statistics** operation:

```
>p3leasequery --show-statistics
DHCP Lease-Query LEG Statistics:
=====
Lease-Queries Sent:           16
Lease-Queries Replied:       16
Active Lease Replies:         16
Non-Active Lease Replies:     0
Total timed-out sessions:     0
Consecutive timed-out sessions: 0
Number of fail-overs          0
Invalid Replies:              0
Sessions in process:          0
Max-Concurrent sessions:     3
Command terminated successfully
>
```

## Viewing the DHCP Lease Query LEG Version

The following is an example of the **p3leasequery** command-line utility using the **show-version** operation:

```
>p3leasequery --show-version
DHCP LEASE QUERY LEG 3.1.0 Build 176
>
```



# CHAPTER 4

## SCE Integration

---



### Note

This section is relevant if you intend to install the DHCP Lease Query LEG directly on the SCE device in an SM-less installation.

---

This module describes the procedures for installing, uninstalling, and upgrading the DHCP Lease Query LEG on the SCE.

The SM-less integration supports a cascade SCE installation.

## How to Install, Uninstall, and Upgrade the DHCP Lease Query LEG

- [Installing the DHCP Lease Query LEG on the SCE, page 4-1](#)
- [Uninstalling the DHCP Lease Query LEG from the SCE Device, page 4-2](#)
- [Upgrading the DHCP Lease Query LEG, page 4-2](#)

## Installing the DHCP Lease Query LEG on the SCE

---

**Step 1** Install the PQI file of the DHCP Lease Query LEG.

Run the following CLI on the SCE device:

```
SCE2000#>configure
SCE2000 (config)#>interface LineCard 0
SCE2000 (config if)#>pqi install file LEG-PQI
```



### Note

After the installation of the PQI file, the management agent restarts itself automatically. Please wait until the management agent is up before proceeding with configuring the LEG.

---

**Step 2** Configure the LEG using the SCE CLI.

Before you start using the LEG, you must configure the DHCP servers and start the LEG operation. See the [Configuration CLI](#) for more details.

---

## Uninstalling the DHCP Lease Query LEG from the SCE Device

**Step 1** Uninstall the DHCP Lease Query LEG using the CLI on the SCE device.

Run the following CLI on the SCE device.

```
SCE2000#>configure
SCE2000(config)#>interface LineCard 0
SCE2000(config if)#>pqi uninstall file LEG-PQI
```



**Note** After the uninstallation of the PQI file, the management agent restarts itself automatically. Please wait until the management agent is up before using the SCE device.

## Upgrading the DHCP Lease Query LEG

The DHCP Lease Query LEG must be upgraded as part of the SCE upgrade process, because previous versions of the DHCP Lease Query LEG are incompatible with the SM 3.x version. The upgrade for the DHCP Lease Query LEG should be performed together with the upgrade process of the SCE.

**Step 1** Backup the configuration files of the DHCP Lease Query LEG.

The original configuration files are deleted by the uninstall process in the next step.

The files to backup are **leaseq.cfg** and **dhcp\_pkg.cfg**, which both reside in the **~pcube/sm/server/root/config** directory.

**Step 2** Uninstall the DHCP Lease Query LEG.

Run the following CLI on the SCE device.

```
SCE2000#>configure
SCE2000(config)#>interface LineCard 0
SCE2000(config if)#>pqi uninstall file LEG-PQI
```



**Note** After the uninstallation of the PQI file, the management agent restarts itself automatically. Please wait until the management agent is up before using the SCE device.

**Step 3** Perform an upgrade of the SCE.

The SCE upgrade procedure is described in the *Cisco SCE Software Configuration Guide*.

**Step 4** Install the new version of the DHCP Lease Query LEG.

Run the following CLI on the SCE device.

```
SCE2000#>configure
SCE2000(config)#>interface LineCard 0
SCE2000(config if)#>pqi install file LEG-PQI
```



**Note** After the installation of the PQI file, the management agent restarts itself automatically. Please wait until the management agent is up before proceeding with configuring the LEG.

**Step 5** Configure the LEG using the SCE CLI.

---





## CHAPTER 5

# SCE Integration - Configuration

---

This module describes how to configure the DHCP Lease Query LEG on the SCE and the CLI.

- [Configuring the DHCP Lease Query LEG on the SCE, page 5-1](#)
- [Information About the DHCP Lease Query LEG CLI, page 5-1](#)

## Configuring the DHCP Lease Query LEG on the SCE

The DHCP Lease Query LEG on the SCE is configured using the CLI.

## Information About the DHCP Lease Query LEG CLI

- [Configuration CLI, page 5-1](#)
- [Show CLI, page 5-2](#)

## Configuration CLI

Use the Command-Line Interface (CLI) to configure the general LEG settings of the DHCP Lease Query LEG.

To enable the LEG:

```
SCE(config)# subscriber LEG dhcp-lease-query
```

To disable the LEG:

```
SCE(config)# no subscriber LEG dhcp-lease-query
```

To set the IP addresses of the DHCP servers (one or two addresses):

```
SCE(config)# subscriber LEG dhcp-lease-query servers STRING STRING
```

To reset the DHCP servers:

```
SCE(config)# no subscriber LEG dhcp-lease-query servers
```

To set the **session\_timeout** configuration variable (see also [Information About Configuring the DHCP Lease Query LEG, page 3-1](#)):

```
SCE(config)# subscriber LEG dhcp-lease-query session-timeout DECIMAL
```

To set the `session_timeout` variable to the default value:

```
SCE(config)# default subscriber LEG dhcp-lease-query session_timeout
```

The failover criteria configuration variable defines the number of consecutive request failures (timeouts) that triggers a fail-over. Because the queries are not answered when the server fails, these queries time out. The consecutive timed-out queries are counted and when they reach this threshold, the second server is set as the active server. The default value is 3.

To set the `fail_over_criteria`:

```
SCE(config)# subscriber LEG dhcp-lease-query failover-criteria DECIMAL
```

To set the `fail_over_criteria` variable to the default value:

```
SCE(config)# default subscriber LEG dhcp-lease-query failover-criteria
```

The format of the subscriber ID can be set to binary or string. Setting the subscriber ID to binary indicates a binary string converted to an ASCII hexadecimal string. Setting it to string indicates an ASCII string. Use the `ip-fallback` parameter to set the IP to be the subscriber ID if the DHCP option is not found in the packet.

To set the subscriber ID option:

```
SCE(config)# subscriber LEG dhcp-lease-query sub-id-option STRING binary|string
[ip-fallback]
```

For example:

- `subscriber LEG dhcp-lease-query sub-id-option 82:2 binary`  
This example uses DHCP option 82:2 for the subscriber ID, and its type is binary. No fallback is performed if the option is not found.
- `subscriber LEG dhcp-lease-query sub-id-option 43:1 string ip-fallback`  
This example uses DHCP option 32:1 for the subscriber ID, and its type is string. The IP is used as the subscriber ID if the DHCP option is not found.

To set the subscriber ID option to the default value:

```
SCE(config)# default subscriber LEG dhcp-lease-query sub-id-option
```

For policy association, the LEG uses exactly the same file described in the [Configuring Policy Association](#) section. Set and load the configuration file with the following CLI (you must specify the full path and the file name):

```
SCE(config)# subscriber LEG dhcp-lease-query package-association-file STRING
```

The default package association configuration does not assign package information. To set the configuration back to the default configuration file:

```
SCE(config)# default subscriber LEG dhcp-lease-query package-association-file
```

To set all parameters of the DHCP lease query LEG to the default settings, use the following CLI:

```
SCE(config)# default subscriber LEG dhcp-lease-query
```

## Show CLI

To view the general configuration of the LEG, enter the following command:

```
SCE# show subscriber LEG dhcp-lease-query
```



To view the statistics counters of the LEG:

```
SCE# show subscriber LEG dhcp-lease-query counters
```

To reset the statistics counters of the LEG:

```
SCE# clear subscriber LEG dhcp-lease-query counters
```





# APPENDIX **A**

## DHCP Forwarder Application

---

This module describes how to install the DHCP forwarder application as well as adding and removing resources.



### Note

---

This module is only relevant when the DHCP Lease Query LEG is installed on the SM server.

---

The DHCP Forwarder application acts as a bridge between the DHCP Lease Query LEG and the DHCP servers. The LEG sends a request to the DHCP Forwarder, which then forwards the request to the appropriate DHCP server. The DHCP Forwarder passes the replies from the DHCP servers to the LEG. The LEG signals the forwarder which server should receive each request. Therefore, no special configuration is needed for this application.

Because only root privileged applications can open ports under 1024 (DHCP uses ports 67 and 68), the DHCP Forwarder runs with root privileges.

- [Installing the DHCP Forwarder, page A-1](#)
- [Uninstalling the DHCP Forwarder, page A-2](#)
- [DHCP Forwarder VCS Agent, page A-2](#)

## Installing the DHCP Forwarder

---

**Step 1** Run the DHCP Forwarder installation script from the Lease\_Query\_LEG directory of the SM DIST root directory.

You must run the DHCP Forwarder installation script as **root**.

```
#!/install-forwarder.sh
```

The installation script extracts the DHCP Forwarder distribution to the *sm-inst-dir* \sm\server\addons\dhcp-forwarder directory (*sm-inst-dir* refers to the SM installation directory). The script adds the initialization scripts to their location according to the machine's OS.

**Step 2** Run the DHCP Forwarder application.

The DHCP Forwarder application can be run using one of the following methods:

- Restart the machine. The initialization script will start the application automatically.
- Run the following command as **root**:

```
#!/etc/init.d/p3dhcpforwarder start
```

**Note**

It is not possible to run the script if the `/etc/motd` file exists. The file should be moved *or* removed prior to running the `install-forwarder.sh` script.

## Uninstalling the DHCP Forwarder

**Step 1** Stop the DHCP Forwarder application.

Run the following command as **root** to stop the application.

```
#/etc/init.d/p3dhcpforwarder stop
```

**Step 2** Remove the DHCP Forwarder application startup and shutdown scripts.

Run the following command as **root** to remove the startup and shutdown scripts.

- For Solaris:

```
# rm /etc/rc*.d/[SK]*p3dhcpforwarder
# rm /etc/init.d/p3dhcpforwarder
```

- For Red Hat:

```
# rm /etc/rc.d/rc*.d/[SK]*p3dhcpforwarder
# rm /etc/rc.d/init.d/p3dhcpforwarder
```

**Step 3** Remove the DHCP Forwarder application directory.

Run the following command to remove the application.

```
# rm -r ~pcube/sm/server/addons/dhcp-forwarder
```

## DHCP Forwarder VCS Agent

To verify that the DHCP Forwarder process is active at all times, a Veritas Cluster Server (VCS) Agent of type *OnOnlyProcess* is added as a resource.

- [Adding a DHCP Forwarder Resource, page A-2](#)
- [Removing a DHCP Forwarder Resource, page A-4](#)

## Adding a DHCP Forwarder Resource

**Step 1** Import the OnOnlyProcess agent's type from the `/opt/VRTSvcs/bin/OnOnlyProcess/OnOnlyProcess.cf` file.

**Step 2** Add an OnOnlyProcess resource called *DHCP\_Forwarder* to the service group.

**Step 3** Note the path and arguments of the DHCP Forwarder.

Run the following command via a Telnet session on each of the servers:

```
>ps -ea -o pid,s,args
```

Look for the line containing the text "DHCP\_FORWARDER". This line contains the path and arguments of the DHCP Forwarder to be used in the next step.

**Step 4** Define the **OnlineCmd**, **PathName**, and **Arguments** parameters.

Define the parameters as follows:

- **OnlineCmd**—Type the DHCP Forwarder start command:  


```
/etc/init.d/p3dhcpforwarder start
```
- **PathName**—Type the DHCP Forwarder process path (from the previous step). For example:  

```
/opt/pcube/j2re1.4.2_05/bin/java
```
- **Arguments**—Type the DHCP Forwarder process arguments (from the previous step). For example:  

```
DAPP=DHCP_FORWARDER -jar /opt/pcube/sm/server.
```

For further information about the parameters, see [Figure A-1](#).

**Figure A-1** Adding a DHCP Forwarder Resource



**Note**

The arguments line might seem shorter than the actual full argument list. This is perfectly acceptable.

## Removing a DHCP Forwarder Resource

- Step 1** Right-click on the DHCP Forwarder Resource icon and choose **Delete** from the drop-down menu as shown in [Figure A-2](#).

**Figure A-2** Removing a DHCP Forwarder Resource

