



stcli security Commands

- [stcli security Commands, on page 1](#)
- [stcli security encryption Commands, on page 1](#)
- [stcli security password Command, on page 4](#)
- [stcli security ssh Command, on page 4](#)
- [stcli security whitelist Commands, on page 4](#)

stcli security Commands

Security related operations.

stcli security [-h] {password | whitelist | ssh | encryption}

Syntax Description	Option	Required or Optional	Description
	password	One of set required.	Commands supported in the Storage security password manipulation namespace.
	ssh	One of set required.	Commands supported in the Storage security ssh namespace.
	whitelist	One of set required.	Commands supported in the Storage security ip whitelist namespace.
	encryption	One of set required.	Commands supported in the Storage security encryption namespace.

Command Default None. One option from the set is required.

Usage Guidelines Accompany the `stcli security` command with one of the positional arguments enclosed in `{ }` or optional arguments enclosed in `[]`.

stcli security encryption Commands

Encryption management operations.

stcli security encryption [-h] {ucsm-ro-user}

Syntax Description	Option	Required or Optional	Description
	ucsm-ro-user	Required.	Commands supported in the security encryption UCSM RO user namespace.
Command Default	None.		
Usage Guidelines	Accompany the <code>stcli security encryption</code> command with one of the positional arguments enclosed in <code>{ }</code> or optionally, the arguments enclosed in <code>[]</code> .		

stcli security encryption ucsm-ro-user Commands

Encryption UCSM read only (RO) user operations.

stcli security encryption ucsm-ro-user [-h] {show | create | delete}

Syntax Description	Option	Required or Optional	Description
	create	Required one of set.	Create UCSM RO user.
	delete	Required one of set.	Delete UCSM RO user.
	show	Required one of set.	Show UCSM RO user credentials.
Command Default	None.		
Usage Guidelines	Accompany the <code>stcli security encryption ucsm-ro-user</code> command with one of the positional arguments enclosed in <code>{ }</code> or optionally, the arguments enclosed in <code>[]</code> .		

stcli security encryption ucsm-ro-user create Command

Encryption UCSM read only (RO) user create operations.



Important Please enter password when prompted.

stcli security encryption ucsm-ro-user create [-h] --hostname HOSTNAME [--username USERNAME]

Syntax Description	Option	Required or Optional	Description
	--hostname HOSTNAME	Required.	UCSM host name.

Option	Required or Optional	Description
--username USERNAME	Optional.	UCSM user name.
		Note The UCSM user used to create the RO user should be the local UCSM user, and not an LDAP or AD user.
		Enter UCSM admin level password when prompted.

Command Default Username default is `admin`.

Usage Guidelines Accompany the `stcli security encryption ucsd-ro-user create` command with the required arguments with leading two dashes (--), and optionally, the arguments enclosed in [].

stcli security encryption ucsd-ro-user delete Command

Encryption UCSM read only (RO) user delete operations.



Important Please enter password when prompted.

stcli security encryption ucsd-ro-user delete [-h] --hostname HOSTNAME [--username USERNAME]

Syntax Description	Option	Required or Optional	Description
	--hostname HOSTNAME	Required.	UCSM host name.
	--username USERNAME	Optional.	UCSM user name. Must be UCSM admin level user. Enter UCSM admin level password when prompted.

Command Default Username default is `admin`.

Usage Guidelines Accompany the `stcli security encryption ucsd-ro-user delete` command with the required arguments with leading two dashes (--), and optionally, the arguments enclosed in [].

stcli security encryption ucsd-ro-user show Command

Encryption UCSM read only (RO) show users.

stcli security encryption ucsd-ro-user show [-h]

Command Default None.

Usage Guidelines Accompany the `stcli security encryption ucsd-ro-user show` command optionally, the arguments enclosed in [].

stcli security password Command

SSH key management operations. Sets user password for all the controller VMs in the storage cluster.



Important Enter password when prompted

stcli security password set [-h] [--user USER]

Syntax Description	Option	Required or Optional	Description
	set	Required.	Sets user password for all the controller VMs in the storage cluster.
	--user USER	Optional.	User must be either admin or root. User root is assumed if not specified.

Command Default Default controller VM username, `root` and password, `Cisco123`.

Usage Guidelines Accompany the `stcli security password set` command with one of the optional arguments enclosed in [].

stcli security ssh Command

SSH key management operations. Resyncs SSH keys in storage cluster.

stcli security ssh [-h] resync

Syntax Description	Option	Required or Optional	Description
	resync	Required.	Resyncs SSH keys in storage cluster.

Command Default None.

Usage Guidelines Run the `stcli security ssh` command with the `resync` positional argument, or include the optional arguments enclosed in [].

stcli security whitelist Commands

IP tables white-listing operations.

stcli security whitelist [-h] [list | add | remove | clear]

Syntax Description	Option	Required or Optional	Description
	add	One of set required.	Adds IP addresses to IP table white-list.
	clear	One of set required.	Clears IP addresses from IP table white-list.
	list	One of set required.	List IP table white-listed entries.
	remove	One of set required.	Removes IP addresses from IP table white-list.

Command Default None. One option from the set is required.

Usage Guidelines Accompany the `stcli security whitelist` command with one of the positional arguments enclosed in `{ }` or optional arguments enclosed in `[]`.

stcli security whitelist add Command

Adds IP addresses to the IP table white list.

`stcli security whitelist add [-h] --ips IP [IP . . .]`

Syntax Description	Option	Required or Optional	Description
	--ips IP [IP . . .]	Required.	The IP addresses to add to white list.

Command Default None. IP addresses required.

Usage Guidelines Accompany the `stcli security whitelist add` command with the IPs of the servers to add.

```
# stcli security whitelist add --ips 10.1.2.3 10.3.4.5
```

stcli security whitelist clear Command

Deletes the entire list of IP addresses in the IP table white list.

`stcli security whitelist clear [-h]`

Command Default None.

Usage Guidelines Run the `stcli security whitelist clear` command to delete IP addresses from the white list.

stcli security whitelist list Command

Displays the list of white list entries in the IP table.

`stcli security whitelist list [-h]`

Command Default None.

Usage Guidelines Accompany the `stcli security whitelist list` command, or include optional arguments enclosed in [].

```
# stcli security whitelist list
10.1.1.2
10.1.2.3
```

stcli security whitelist remove Command

Deletes the specified IP addresses from the IP table white list.

stcli security whitelist remove [-h] --ips IP [IP ...]

Syntax Description	Option	Required or Optional	Description
	<code>--ips IP [IP ...]</code>	Required.	IP addresses to remove from white list.

Command Default None.

Usage Guidelines Accompany the `stcli security whitelist remove` command with the IP addresses to remove from the white list.

```
# stcli security whitelist remove --ips 10.1.2.3
```