

# Standalone MAB Support

Standalone MAC Authentication Bypass (MAB) is an authentication method that grants network access to specific MAC addresses regardless of 802.1X capability or credentials. As a result, devices such as cash registers, fax machines, and printers can be readily authenticated, and network features that are based on authorization policies can be made available.

Before standalone MAB support was available, MAB could be configured only as a failover method for 802.1x authentication. Standalone MAB is independent of 802.1x authentication.

- Finding Feature Information, page 1
- Information About Configuring Standalone MAB, page 1
- How to Configure Standalone MAB Support, page 2
- Configuration Examples for Standalone MAB Support, page 4
- Additional References, page 4
- Feature Information for Standalone MAB Support, page 5

## **Finding Feature Information**

Your software release may not support all the features documented in this module. For the latest caveats and feature information, see Bug Search Tool and the release notes for your platform and software release. To find information about the features documented in this module, and to see a list of the releases in which each feature is supported, see the feature information table at the end of this module.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to <a href="https://www.cisco.com/go/cfn">www.cisco.com/go/cfn</a>. An account on Cisco.com is not required.

## Information About Configuring Standalone MAB

### **Standalone MAB**

MAC Authentication Bypass (MAB) uses the MAC address of the connecting device to grant or deny network access. To support MAB, the RADIUS authentication server maintains a database of MAC addresses for

devices that require access to the network. MAB generates a RADIUS request with a MAC address in the Calling-Station-Id (attribute 31) and with a Service-Type (attribute 6) 10. After a successful authentication, the Auth Manager enables various authorization features specified by the authorization policy, such as ACL assignment and VLAN assignment.

# **How to Configure Standalone MAB Support**

### **Enabling Standalone MAB**

Ports enabled with the Standalone MAB feature can use the MAC address of connecting devices to grant or deny network access. Perform the steps described in this section to enable standalone MAB on individual ports.

### **Before You Begin**

Before you can configure standalone MAB, the device must be connected to a Cisco Secure ACS server and RADIUS authentication, authorization, and accounting (AAA) must be configured.



Note

Standalone MAB can be configured on devices with switched ports only; it cannot be configured on devices with routed ports.



Note

If you are unsure whether MAB or MAB Extensible Authentication Protocol (EAP) is enabled or disabled on the switched port, use the **default mab** or **default mab** eap commands in interface configuration mode to configure MAB or MAB EAP.

#### **SUMMARY STEPS**

- 1. enable
- 2. configure terminal
- 3. interface type slot / port
- 4. switchport
- 5. switchport mode access
- 6. authentication port-control auto
- 7. mab
- 8. end

#### **DETAILED STEPS**

	Command or Action	Purpose
Step 1	enable	Enables privileged EXEC mode.

	Command or Action	Purpose
		Enter your password if prompted.
	Example:	
	Device> enable	
Step 2	configure terminal	Enters global configuration mode.
	Example:	
	Device# configure terminal	
Step 3	interface type slot   port	Enters interface configuration mode.
	Example:	
	Device(config) # interface FastEthernet2/1	
Step 4	switchport	Places interface in Layer 2 switched mode.
	Example:	
	Switch(config-if)# switchport	
Step 5	switchport mode access	Sets the interface type a as nontrunking, nontagged single VLAN Layer 2 interface.
	Example:	
	Device(config-if)# switchport mode access	
Step 6	authentication port-control auto	Configures the authorization state of the port.
	Example:	
	Device(config-if)# authentication port-control auto	
Step 7	mab	Enables MAB.
	Example:	
	Device(config-if) # mab	
Step 8	end	Exits interface configuration mode and returns to privileged EXEC mode.
	Example:	
	Device(config-if) # end	

### **Troubleshooting Tips**

The following commands can help troubleshoot standalone MAB:

- · debug authentication
- · debug mab all
- · show authentication registrations
- · show authentication sessions
- · show mab

# **Configuration Examples for Standalone MAB Support**

### **Example: Standalone MAB Configuration**

The following example shows how to configure standalone MAB on a port. In this example, the client is reauthenticated every 1200 seconds and the connection is dropped after 600 seconds of inactivity.

```
Device> enable
Device# configure terminal
Device(config)# interface GigabitEthernet2/1
Device(config-if)# switchport
Device(config-if)# switchport mode access
Device(config-if)# switchport access vlan 2
Device(config-if)# authentication port-control auto
Device(config-if)# mab
Device(config-if)# authentication violation shutdown
Device(config-if)# authentication timer restart 30
Device(config-if)# authentication periodic
Device(config-if)# authentication timer reauthenticate 1200
Device(config-if)# authentication timer inactivity 600
```

## **Additional References**

### **Related Documents**

Related Topic	Document Title	
Cisco IOS commands	Cisco IOS Master Command List, All Releases	
Authentication commands	Cisco IOS Security Command Reference	
IEEE 802.1x—Flexible Authentication	Securing User Services Configuration Library	

#### **MIBs**

MIB	MIBs Link
CISCO-AUTH-FRAMEWORK-MIB     CISCO-MAC-AUTH-BYPASS-MIB	To locate and download MIBs for selected platforms, Cisco IOS software releases, and feature sets, use Cisco MIB Locator found at the following URL:
• CISCO-PAE-MIB	http://www.cisco.com/go/mibs
• IEEE8021-PAE-MIB	

### **RFCs**

RFC	Title
RFC 3580	IEEE 802.1x Remote Authentication Dial In User Service (RADIUS)

#### **Technical Assistance**

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	http://www.cisco.com/cisco/web/support/index.html

# **Feature Information for Standalone MAB Support**

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to <a href="https://www.cisco.com/go/cfn">www.cisco.com/go/cfn</a>. An account on Cisco.com is not required.

Table 1: Feature Information for Standalone MAB Support

Feature Name	Releases	Feature Information
Standalone MAB Support	12.2(33)SXI 15.2(2)T	This feature grants network access to devices based on MAC address regardless of 802.1x capability or credentials.
		The following commands were introduced or modified: authentication periodic, authentication port-control, authentication timer inactivity, authentication timer reauthenticate, authentication timer restart, authentication violation, debug authentication, mab, show authentication interface, show authentication registrations, show authentication sessions, and show mab.