



# CHAPTER 4


## Auth Service Configuration Commands

This chapter describes the command line interface (CLI) commands that you can use to configure various settings for the auth service running on the Cisco Broadband Access Center (Cisco BAC) Device Provisioning Engine (DPE).

This is the global syntax of the commands that you can use to configure various settings for the auth service running on the DPE. Using these commands, you can:

- Enable the auth service
- Set the host address for the service
- Set the port number for the service
- Configure the service to use HTTP over SSL/TLS.

Command Usage	Syntax Description	Examples
<b>service auth <i>num</i> enable {true   false}</b>		
Enables or disables the auth service running on the DPE.	<p><i>num</i>—Identifies the auth service, which is always 1.</p> <p>By default, the auth service is enabled.</p> <ul style="list-style-type: none"> <li>• <b>true</b>—Enables the auth service.</li> <li>• <b>false</b>—Disables the auth service.</li> </ul>	<pre>dpe# service auth 1 enabled true % OK (Requires DPE restart "# dpe reload")</pre>
<b>service auth <i>num</i> address <i>address</i></b>		
Sets the host address for the auth service running on the DPE.	<p><i>num</i>—Identifies the auth service, which is always 1.</p> <p><i>address</i>—Identifies the host address for the auth service running on the DPE.</p> <p>By default, the host address for the auth service running on the DPE is 127.0.0.1.</p>	<pre>dpe# service auth 1 host address 127.0.0.1 % OK (Requires DPE restart "# dpe reload")</pre>

Command Usage	Syntax Description	Examples
<p><b>service auth <i>num</i> port <i>port</i></b></p> <p>Identifies the port on which the auth service communicates with the Cisco Access Registrar Extension Points. By specifying a different port number, this command enables the DPE to prevent potential sharing violations among ports used by other applications.</p>	<ul style="list-style-type: none"> <li><i>num</i> - Identifies the auth service, which is always 1.</li> <li><i>port</i> - Identifies the port number that is to be used by the service.</li> </ul> <p>By default, the auth service is configured to listen on Port 7551.</p>	<pre>dpe# service auth 1 port 7551 % OK (Requires DPE restart "# dpe reload")</pre>
<p><b>service auth <i>num</i> ssl enabled {true   false}</b></p> <p>Enables or disables the use of HTTP over SSL/TLS for the auth service on the DPE.</p> <p> <b>Note</b> The auth service will fail to start up if you do not configure the keystore file and the keystore passwords before restarting the DPE. For information on how to configure a keystore file and keystore passwords, see the <a href="#">Cisco Broadband Access Center Administrator's Guide, Release 3.6</a>.</p>	<ul style="list-style-type: none"> <li><i>num</i> - Identifies the auth service, which is always 1.</li> <li><b>true</b> - Enables SSL/TLS transport.</li> <li><b>false</b> - Disables SSL/TLS transport. This is the default configuration for auth service.</li> </ul>	<pre>dpe# service auth 1 ssl enabled true % OK (Requires DPE restart "# dpe reload")</pre>