



Cisco Virtualized Infrastructure Manager Administrator Guide, Release 2.4.9

First Published: 2019-01-09

Last Modified: 2019-11-14

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: [www.cisco.com go trademarks](http://www.cisco.com/go/trademarks). Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2019 Cisco Systems, Inc. All rights reserved.



CONTENTS

CHAPTER 1

Managing Cisco NFVI 1

Managing Cisco NFVI Pods	2
General Guidelines for Pod Management	2
Identifying the Install Directory	4
Managing Hosts in Cisco VIM or NFVI Pods	5
Recovering Cisco NFVI Pods	9
Managing Nova Compute Scheduler Filters and User Data	11
Monitoring Cisco NFVI Health with CloudPulse	12
Assessing Cisco NFVI Status with Cloud-Sanity	15
Service Catalog URL	18
Get Token from Keystone	18
Get Service Catalog URL for Cloudpulse	19
Cloudpulse APIs	19
List of Cloudpulse Tests	19
Get detailed result of 1 test	20
Get List of Tests Available	21
Schedule a manual cloudpulse test:	21
Remove the results of a test	22
Checking Network Connections	22
Enabling NFVBench Post Deployment	23
NFVBench Usage	27
NFVBench Command-Line Options and Status	28
Using NFVBench Configuration File	28
Control Plane Verification	28
Fixed Rate Run Test	29
Packet Sizes	29

NDR and PDR Test	29
Multi-chain Test	29
Multi-Flow Test	29
Encapsulation	30
External Chain Test	31
NFVBench Results	32
Examples of NFVIBench Result Execution	32
Cisco VIM CLI	37
NFVBench REST Interface	37
Enabling or Disabling Autobackup of Management Node	37
Forwarding ELK logs to External Syslog Server	38
Adding and Reconfiguring VIM Administrators	39
Adding Read-Only OpenStack Role	40
Reconfiguration of Proxy Post Install	41
Reconfiguring Sever KVM Console Password Post Install	42
Enabling Head-End Replication Option	42
Enabling Layer BGP Adjacency Between Controllers and Peering Route Reflector	43
Enabling Custom Policy for VNF Manager Post Install	44
Migrate SRIOV from 2-X520 to 2-XL710 in a VIC/NIC POD	45
Augmenting Cisco VIM M4 VIC/(10/40G) NIC pods with M5-based 40G VIC/NIC Computes	46
Updating Containers in a Running Cisco VIM Cloud	47
Updating Cisco VIM Software Using USB	48
Updating Cisco VIM Software Using Network Installation	50
Upgrading Containers in a Running Cisco VIM Cloud	51
Prerequisites and Assumptions for VIM Update	53
Upgrading VIM Software Using a USB	54
Upgrading Cisco VIM Software Using Network Installation	56
Common Tasks Post Cisco VIM Update	56
Migrating Server Configuration from Bonding to Teaming on Post-Upgrade	58
Supporting RMA of ToRs with Auto-ToR Configuration	59
VM Resizing	59
Nova Migrate	60
Live Migrate	60
Power Management Of Computes (for C-Series)	61

Power On Compute Nodes	62
Managing Reboot of Cisco VIM Nodes	62
Cisco VIM Client Reboot and Remove Compute Using Force Option	63
Managing Reboot Status of Cisco VIM Nodes	64
Cisco UCS Firmware Upgrade	65
Limitations During Cisco IMC Upgrade	66
Tools Usage	66

CHAPTER 2**Cisco VIM REST API 69**

Overview to Cisco VIM REST API	69
Cisco VIM REST API Resources	71

CHAPTER 3**Monitoring Cisco NFVI Performance 107**

Logging and Monitoring in Cisco NFVI	107
Displaying Cisco VIM Log Files Using the CLI	109
Logging Into the Kibana Dashboard	112
Rotation of the Cisco VIM Logs	122
Snapshot Manager Tool for Elasticsearch	122
Remote NFS Backup for Elasticsearch Snapshots	124
Network Performance Test with NFVBench	124

CHAPTER 4**Managing Cisco NFVI Security 125**

Verifying Management Node Network Permissions	125
Verifying Management Node File Permissions	126
Viewing Administrator Access Attempts	126
Verifying SELinux	127
Validating Port Listening Services	127
Validating Non-Root Users for OpenStack Services	128
Verifying Password Strength	128
Reconfiguring Passwords and OpenStack Configurations	129
Enabling CVIMMON Post Pod Installation	133
Enabling NFVIMON Post Pod Install	133
Reconfiguring CIMC Password on an Existing Install	135
Increasing Provider and Tenant VLAN Ranges	136

Fernet Key Operations	137
Managing Certificates	138
Reconfiguring TLS Certificates	138
Enabling Keystone v3 on an Existing Install	139
LDAP/AD support with Keystone v3	140
Moving Netapp transport from http to https	141
Replacing ACI Controller in Cisco VIM	141
Hardening Cisco VIM Deployment	142
Cisco VIM Monitor Alerting Rules Customization	145
Alert Manager and Receiver Customization	148

CHAPTER 5**Managing Cisco NFVI Storage 153**

Cisco NFVI Storage Architecture	153
Verifying and Displaying Ceph Storage Pools	154
Checking the Storage Cluster Health	155
Checking Glance Connectivity	156
Verifying Glance and Ceph Monitor Keyrings	157
Verifying Glance Image ID on Ceph	158
Checking Cinder Connectivity	158
Verifying Cinder and Ceph Monitor Keyrings	159
Verifying the Cinder Volume ID on Ceph	160
Checking Nova Connectivity	161
Verifying Nova and Ceph Monitor Keyrings	161
Verifying Nova Instance ID	162
Displaying Docker Disk Space Usage	163
Reconfiguring SwiftStack Integration	164
Integrating SwiftStack over TLS	164
Cinder Volume Backup on SwiftStack	165
Reconfiguring Administrator Source Networks	165
Password Reset for Cisco VIM Management Node	166

CHAPTER 6**Overview to Cisco VIM Unified Management 169**

Cisco VIM Unified Management Overview	169
Cisco VIM Unified Management Admin UI Overview	171

Cisco VIM Unified Management Pod UI Overview 171

CHAPTER 7

Managing Cisco VIM through Unified Management 173

UI Administrators Privileges and Responsibilities 173

Pod UI Privileges and Responsibilities 174

Adding Cisco VIM Pod 174

Deleting Pod from Cisco VIM Unified Management 175

Context Switching Within Unified Management 176

Dashboard 176

Blueprint Name 177

Deployed Cloud Status 177

Deployed Blueprint Details 177

Pod Operation Details 178

CHAPTER 8

Managing Blueprints 179

Blueprints 179

Blueprint Activation 179

Viewing Blueprint Details 180

Creating a Blueprint Using Upload Functionality 180

Activating a Blueprint in an Existing Pod with OpenStack Installed 181

Blueprint Management 181

Creating a Blueprint for B-Series Server Platform 185

Creating a Blueprint for C-Series Server Platform 233

Redeploy Multiple Install Stages during Cisco VIM Installation using Unified Management 276

Downloading Blueprint 278

Validating Blueprint 278

Managing Post Install Features 279

Monitoring the Pod 279

Cross Launching Horizon 279

NFVI Monitoring 280

Run VMTP 280

Run CloudPulse 281

Run Cloud Sanity Test 282

Run NFV Bench 283

Reconfiguring CIMC Password Through Unified Management 284

CHAPTER 9**Managing Pod Through Cisco VIM Unified Management 285**

Monitoring Pod Status 285

Managing Hardware 286

Searching Compute and Storage Nodes 286

POD Management 287

Managing Storage Nodes 288

Adding Storage Node 289

Deleting Storage Node 290

Managing Compute Nodes 290

Adding Compute Node 290

Deleting Compute Node 292

Managing Control Nodes 293

Replacing Control Node 293

Power Management 294

Power On a Compute Node 294

Powering Off Compute Node 295

Rebooting Compute Node 297

Searching Compute and Storage Nodes 298

Managing Software 298

Reconfigure Openstack Passwords 300

Reconfigure OpenStack Services, TLS Certificates, and ELK Configurations 300

Reconfiguring CIMC Password through Unified Management 301

Reconfigure Optional Services 301

Reconfiguring Optional Features Through Unified Management 303

View Topology 315

Pod User Administration 315

Managing Roles 315

Managing Users 316

Revoke Users 317

Edit Users 318

Managing Root CA Certificate 318

CHAPTER 10	Day 2 Operations of Cisco VIM Unified Management	321
	Shutting Down Cisco VIM Unified Management	321
	Restarting Cisco VIM Unified Management	322
	Restoring VIM Unified Management	322
	Reconfiguring VIM Unified Management	324
	Reconfiguring Unified Management TLS Certificate	324
	Reconfiguring Third-party TLS Certificate	325
	Reconfiguring Self Signed TLS Certificate	326
	Switch from Self Signed TLS Certificate to Third-party TLS Certificate	328
	Reconfiguring Unified Management MySQL Database Password	330
	System-generated Unified Management DB Password	330
	User-supplied Unified Management DB Password	331
	Reconfiguring Unified Management SMTP Server	332
	Reconfiguring Unified Management LDAP Server	334
	Update VIM Unified Management	336
	Updating VIM UM from 2.4.4/2.4.6 to 2.4.10 or later	336
	Updating UM from 2.4.10 to later versions	338
	Update Scenarios	339
	Update VIM Unified Management with Internet Access	339
	VIM Unified Management without Internet Access	340
	Rollback VIM Unified Management	341
	Commit VIM Unified Management	343

CHAPTER 11	Overview to the Cisco Virtual Topology System	345
	Understanding Cisco VTS	345
	Cisco VTS Architecture Overview	346
	Virtual Topology Forwarder	347
	Overview to Cisco VTF and VPP	347
	VPP + VHOSTUSER	348
	Virtual Topology System High Availability	349

CHAPTER 12	Managing Backup and Restore Operations	351
	Managing Backup and Restore Operations	351

Backing Up the Management Node	351
Backup with Forwarding ELK Logs to External Syslog Server	353
Backing Up VIM UM	353
Autobackup Unified Management	353
Back Up Unified Management at Default Back Up Location	355
Backup Unified Management at user defined backup location	356
Restoring the Management Node	357
Management Node Autobackup	359
Managing Cisco VIM Software Hub	360
Updating Cisco VIM Software Hub TLS Certificate and Registry Credentials	361
Cisco VIM Software Hub Server Backup and Restore	361
Checking Integrity of Autobackup Files	361
Restoring Cisco VIM Software Hub from Backup	362
Resolving Low Disk Space	363
Manually Updating Packages	364

CHAPTER 13
Troubleshooting 365

Displaying Cisco NFVI Node Names and IP Addresses	365
Verifying Cisco NFVI Node Interface Configurations	366
Displaying Cisco NFVI Node Network Configuration Files	367
Viewing Cisco NFVI Node Interface Bond Configuration Files	368
Viewing Cisco NFVI Node Route Information	368
Viewing Linux Network Namespace Route Information	369
Prior to Remove Storage Operation	369
Troubleshooting Cisco NFVI	371
Managing CIMC and ISO Installation	371
Management Node Installation Fails	371
Configuring Boot Order	372
PXE Failure Issue During Baremetal Step	372
Connecting to Docker Container	375
Management Node Recovery Scenarios	376
Recovering Compute Node Scenario	385
Running the Cisco VIM Technical Support Tool	387
Tech-Support Configuration File	388

Tech-Support When Servers Are Offline	391
Disk-Maintenance Tool to Manage Physical Drives	391
OSD-Maintenance Tool	394
Utility to Resolve Cisco VIM Hardware Validation Failures	397
Command Usage	397
Examples of Command Usage	398
Cisco VIM Client Debug Option	399



CHAPTER 1

Managing Cisco NFVI

The following topics provide general management procedures that you can perform if your implementation is Cisco VIM by itself or if it is Cisco VIM and Cisco VIM Unified Management.

- [Managing Cisco NFVI Pods, on page 2](#)
- [Managing Nova Compute Scheduler Filters and User Data, on page 11](#)
- [Monitoring Cisco NFVI Health with CloudPulse, on page 12](#)
- [Assessing Cisco NFVI Status with Cloud-Sanity, on page 15](#)
- [Service Catalog URL, on page 18](#)
- [Checking Network Connections, on page 22](#)
- [Enabling NFVBench Post Deployment, on page 23](#)
- [NFVBench Usage, on page 27](#)
- [Enabling or Disabling Autobackup of Management Node, on page 37](#)
- [Forwarding ELK logs to External Syslog Server, on page 38](#)
- [Adding and Reconfiguring VIM Administrators, on page 39](#)
- [Adding Read-Only OpenStack Role, on page 40](#)
- [Reconfiguration of Proxy Post Install, on page 41](#)
- [Reconfiguring Sever KVM Console Password Post Install, on page 42](#)
- [Enabling Head-End Replication Option, on page 42](#)
- [Enabling Layer BGP Adjacency Between Controllers and Peering Route Reflector, on page 43](#)
- [Enabling Custom Policy for VNF Manager Post Install, on page 44](#)
- [Migrate SRIOV from 2-X520 to 2-XL710 in a VIC/NIC POD, on page 45](#)
- [Augmenting Cisco VIM M4 VIC/\(10/40G\) NIC pods with M5-based 40G VIC/NIC Computes, on page 46](#)
- [Updating Containers in a Running Cisco VIM Cloud, on page 47](#)
- [Updating Cisco VIM Software Using USB, on page 48](#)
- [Updating Cisco VIM Software Using Network Installation, on page 50](#)
- [Upgrading Containers in a Running Cisco VIM Cloud, on page 51](#)
- [Prerequisites and Assumptions for VIM Update, on page 53](#)
- [Upgrading VIM Software Using a USB, on page 54](#)
- [Upgrading Cisco VIM Software Using Network Installation, on page 56](#)
- [Common Tasks Post Cisco VIM Update, on page 56](#)
- [Migrating Server Configuration from Bonding to Teaming on Post-Upgrade , on page 58](#)
- [Supporting RMA of ToRs with Auto-ToR Configuration, on page 59](#)
- [VM Resizing, on page 59](#)

- [Nova Migrate](#), on page 60
- [Live Migrate](#), on page 60
- [Power Management Of Computes \(for C-Series\)](#), on page 61
- [Power On Compute Nodes](#), on page 62
- [Managing Reboot of Cisco VIM Nodes](#), on page 62
- [Cisco VIM Client Reboot and Remove Compute Using Force Option](#), on page 63
- [Managing Reboot Status of Cisco VIM Nodes](#), on page 64
- [Cisco UCS Firmware Upgrade](#), on page 65

Managing Cisco NFVI Pods

You can perform OpenStack management operations on Cisco NFVI pods including addition and removal of Cisco NFVI compute and Ceph nodes, and replacement of controller nodes. Each action is mutually exclusive. You can perform only one pod management action at a time. Before you perform a pod action, ensure that the following requirements are met:

- The node is part of an existing pod.
- The node information exists in the `setup_data.yaml` file, if the pod management task is removal or replacement of a node.
- The node information does not exist in the `setup_data.yaml` file, if the pod management task is to add a node.

For more information on operations that can be performed on pods, see the [Managing Hosts in Cisco VIM or NFVI Pods](#), on page 5 section.

General Guidelines for Pod Management

The `setup_data.yaml` file is the only user-generated configuration file that is used to install and manage the cloud. While many instances of pod management indicate that the `setup_data.yaml` file is modified, the administrator does not update the system generated `setup_data.yaml` file directly.



Note To avoid translation errors, we recommend that you avoid copying and pasting commands from the documents to the Linux CLI.

Follow these steps to update the `setup_data.yaml` file:

1. Copy the setup data into a local directory:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
```

2. Update the setup data manually:

```
[root@mgmt1 ~]# vi my_setup_data.yaml (update the targeted fields for the setup_data)
```

3. Run the reconfiguration command:

```
[root@mgmt1 ~]# ciscovim --setupfile ~/MyDir/<my_setup_data.yaml>
<pod_management_action>
```

In Cisco VIM, you can edit and enable a selected set of options in the `setup_data.yaml` file using the `reconfigure` option. After installation, you can change the values of the feature parameters. Unless specified, Cisco VIM does not allow you to undo the feature configuration.

The following table provides the list of features that you can reconfigure after installing a pod.

Features Enabled after post-pod deployment	Comment
Optional OpenStack Services	<ul style="list-style-type: none"> • Heat: OpenStack Orchestration Program • Keystone v3: Pod running Keystone v2 can be migrated to Keystone v3 • LDAP: Works only with Keystone v3. Full or partial reconfiguration can be done. Except for domain, all attributes are reconfigurable.
Pod Monitoring	<ul style="list-style-type: none"> • NFVIMON: Third-party monitoring from host to service level; needs involvement and planning with Cisco Advance Services. • CVIMMON: monitoring host and service level.
Export of EFK logs to External Syslog Server	Reduces single point of failure on management node and provides data aggregation.
NFS for Elasticsearch Snapshot	NFS mount point for Elastic-search snapshot is used so that the disk on management node does not get full.
Admin Source Networks	White list filter for accessing management node admin service.
NFVBench	Tool to help measure cloud performance. Management node needs a dedicated 10G/40G Intel NIC (4x10G 710, or 2x40G XL710 Intel NIC).
EFK settings	Enables you to set EFK rotation frequency and size.
OpenStack service password	Implemented for security reasons, so that OpenStack passwords can be reset on-demand.
CIMC Password Reconfigure Post Install	Implemented for security reasons, so that CIMC passwords for C-series pod, can be reset on-demand.
SwiftStack Post Install	Integration with third-party Object-Store. The SwiftStack Post Install feature works only with Keystone v2.
TENANT_VLAN_RANGES and PROVIDER_VLAN_RANGES	Ability to increase the tenant and provider VLAN ranges on a pod that is up and running. It gives customers flexibility in network planning.

Features Enabled after post-pod deployment	Comment
Support of Multiple External Syslog Servers	Ability to offload the OpenStack logs to an external Syslog server post-install.
Replace of Failed APIC Hosts and add more leaf nodes	Ability to replace Failed APIC Hosts, and add more leaf nodes to increase the fabric influence.
Make Netapp block storage end point secure	Ability to move the Netapp block storage endpoint from Clear to TLS post-deployment
Auto-backup of Management Node	Ability to enable/disable auto-backup of Management Node. It is possible to unconfigure the Management Node.
VIM Admins	Ability to configure non-root VIM Administrators.
EXTERNAL_LB_VIP_FQDN	Ability to enable TLS on external_vip through FQDN.
EXTERNAL_LB_VIP_TLS	Ability to enable TLS on external_vip through an IP address.
http_proxy and/or https_proxy	Ability to reconfigure http and/or https proxy servers.
Admin Privileges for VNF Manager (ESC) from a tenant domain	Ability to enable admin privileges for VNF Manager (ESC) from a tenant domain.
SRIOV_CARD_TYPE	Mechanism to switch between 2-X520 and 2-XL710 as an SRIOV option in Cisco VIC NIC settings at a global and per compute level through reconfiguration. In the absence of per compute and global level, X520 card type is set by default.
NETAPP	Migrate NETAPP transport protocol from http to https.
Reset of KVM console passwords for servers	Aids to recover the KVM console passwords for servers.
Ability to add Layer 3 BGP session.	Ability to switch BGP sessions from Layer 2 to Layer 3 with VXLAN configuration.
Add or remove head-end-replication option	Enables to add or remove head-end-replication option, in the presence of VXLAN configuration.

Identifying the Install Directory

If you are an administrator and want to use CLI to manage the pods, you must know the location of the installer directory. To identify the installer directory of a pod, execute the following commands:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# ls -lrt | grep openstack-configs
lrwxrwxrwx. 1 root root      38 Mar 12 21:33 openstack-configs ->
/root/installer-<tagid>/openstack-configs
```

From the output, you can understand that the OpenStack-configs is a symbolic link to the installer directory.

Verify that the REST API server is running from the same installer directory location, by executing the following commands:

```
# cd installer-<tagid>/tools
# ./restapi.py -a status
Status of the REST API Server:  active (running) since Thu 2016-08-18 09:15:39 UTC; 9h ago
REST API launch directory: /root/installer-<tagid>/
```

Managing Hosts in Cisco VIM or NFVI Pods

In Cisco VIM, a node can participate in multiple roles based on the pod type. The following rules apply for hardware management of a node:

1. If a node is a Micropod node that acts as controller, compute, and Ceph, the node can only go through the action of replace controller for its swap. You can perform this action on one node at a time.
2. If a node is a hyper-converged node (that is, acting as both compute and Ceph), the node is treated as a ceph node from hardware management point of view and the node can only go through the action of add or remove of Ceph. This action can be done only on one node at a time.
3. If a node is a standalone compute node, the node can only go through the action of add or remove of compute. You can add or remove multiple nodes at a time, but you cannot operate the pod with zero compute at any given time.
4. If a node is a dedicated controller node, the node can only go through the action of replace controller for its swap. This action can be done only on one node at a time.
5. If a node is a dedicated Ceph node, the node can only go through the action of add or remove of Ceph. This action can be done only on one node at a time and you cannot have a pod with less than two node Ceph at a time.

Based on the preceding rules, to perform hardware management actions on the pod, run the commands specified in the following table. If you log in as root, manually change the directory to /root/installer-xxx to get to the correct working directory for these Cisco NFVI pod commands.

Table 1: Cisco NFVI Pod Management

Action	Steps	Restrictions
Remove block_storage or compute node	<ol style="list-style-type: none"> Remove the node information from the ROLES and SERVERS section of the setup_data.yaml file for the specific node. Enter one of the following commands. For compute nodes: <pre>ciscovim remove-computes --setupfile ~/MyDir/my_setup_data.yaml <"compute-1,compute-2"> [--force]</pre> For storage nodes: <pre>ciscovim remove-storage --setupfile ~/MyDir/my_setup_data.yaml <"storage-1"> [--force]</pre> 	<p>You can remove multiple compute nodes and only one storage at a time;</p> <p>The pod must have a minimum of one compute and two storage nodes after the removal action.</p> <p>In Cisco VIM the number of ceph OSD nodes can vary from 3 to 20. You can remove one OSD node at a time as part of the pod management.</p> <p>Note On a Micropod expanded with standalone computes, only the standalone compute nodes can be removed. Pod management operation for storage node is not supported for Micropod. In hyper-converged mode, compute management operations are not supported for hyper-converged nodes. In UMHC pod, if a VM is running on the storage node, remove-storage operation fails in pre-validation and gives a warning to the user about running VM's. Use force option to forcefully remove the storage node.</p>

Action	Steps	Restrictions
<p>Add block_storage or compute node</p>	<ol style="list-style-type: none"> 1. Add the node information from the ROLES and SERVERS section of the setup_data.yaml file for the specific node. 2. Enter one of the following commands. For compute nodes: <pre>ciscovim add-computes --setupfile ~/MyDir/my_setup_data.yaml <"compute-1,compute-2"></pre> For storage nodes: <pre>ciscovim add-storage --setupfile ~/MyDir/my_setup_data.yaml <"storage-1"></pre> 	<p>You can add multiple compute nodes and only one storage node at a time.</p> <p>The pod must have a minimum of one compute, and two storage nodes before the addition action.</p> <p>In Cisco VIM the number of ceph OSD nodes can vary from 3 to 20. You can add one OSD node at a time as part of the pod management.</p> <p>Note On a micro-pod expanded with standalone computes, only the standalone compute nodes can be added. Pod management operation for storage node is not supported for micro-pod. In hyper-converged mode, compute management operations are not supported for hyper-converged nodes.</p>
<p>Replace controller node</p>	<ol style="list-style-type: none"> 1. If the controller node is in a UCS C-Series pod, update the CIMC info node in the SERVERS section of the setup_data.yaml file for the specific node 2. For B-series only update the blade and chassis info 3. Enter the following command: <pre>ciscovim replace-controller --setupfile ~/MyDir/my_setup_data.yaml <"control-1"> [--force]</pre> 	<p>You can replace only one controller node at a time. The pod can have a maximum of three controller nodes.</p> <p>In Cisco VIM the replace controller node operation is supported in micro-pod.</p> <p>Note While replacing the controller node, the IP address and hostname are reused. So, do not update any other controller information other than CIMC access for C-series, and blade and chassis information for B-series. For Micropod, this operation is supported on the AIO (all in one) nodes. In Micropod, if a VM is running on the controller node, the replace controller operation fails during pre-validation and gives a warning to the user about running VM's. Use force option to forcefully replace the controller.</p>

When you add a compute or storage node to a UCS C-Series pod, you can increase the management/provision address pool. Similarly, for a UCS B-Series pod, you can increase the Cisco IMC pool to provide routing

space flexibility for pod networking. Along with server information, these are the only items you can change in the `setup_data.yaml` file after the pod is deployed. To make changes to the management or provisioning sections and/or CIMC (for UCS B-Series pods) network section, you must not change the existing address block as defined on day 0. You can add only to the existing information by adding new address pool block(s) of address pool as shown in the following example:

```
NETWORKING:
:
:

networks:
-
  vlan_id: 99
  subnet: 172.31.231.0/25
  gateway: 172.31.231.1
  ## 'pool' can be defined with single ip or a range of ip
  pool:
    - 172.31.231.2, 172.31.231.5 -> IP address pool on Day-0
    - 172.31.231.7 to 172.31.231.12 -> IP address pool ext. on Day-n
    - 172.31.231.20
  segments:
    ## CIMC IP allocation. Needs to be an external routable network
    - cimc
-
  vlan_id: 2001
  subnet: 192.168.11.0/25
  gateway: 192.168.11.1
  rt_prefix: < Local to POD > #optional, only for segment management/provision, storage,
  tenant and ToR-type NCS-5500
  rt_suffix: < Region>:< pod_region_number > #optional, only for segment
  management/provision, storage, tenant and ToR-type NCS-5500

  ## 'pool' can be defined with single ip or a range of ip
  pool:
    - 192.168.11.2 to 192.168.11.5 -> IP address pool on Day-0
    - 192.168.11.7 to 192.168.11.12 -> IP address pool on day-n
    - 192.168.11.20 -> IP address pool on day-n
  segments:
    ## management and provision goes together
    - management
- provision
:
:
```

The IP address pool is the only change allowed in the networking space of the specified networks management/provision and/or CIMC (for B-series). The overall network must have enough address space to accommodate for future enhancement on day-0. After making the changes to servers, roles, and the corresponding address pool, you can execute the add compute/storage CLI shown above to add new nodes to the pod.

For C-series M5 pods, with Cisco NCS 5500 as ToR with splitter cable connection onto the server, along with the server (`cimc_ip`), and connection (`tor_info`, `dp_tor_info`, `srivov_tor_info`) details, you have to adjust the entry for the `splitter_opt_4_10` in respective SWITCHDETAILS for the Cisco NCS 5500 ToR pairs.

For example, to add compute or storage with Cisco NCS 5500 as ToR with splitter cable, add the following entry to the respective Cisco NCS 5500:

```
TORSWITCHINFO:
CONFIGURE_TORS: true # Mandatory
TOR_TYPE: NCS-5500 # Mandatory
```

```

ESI_PREFIX:91.<Pod_number>.<podregion_number>.00.00.00.00 #optional - only for NCS-5500
SWITCHDETAILS: -
hostname: <NCS-5500-1> # hostname of NCS-5500-1
username: admin
password: <ssh_password of NCS-5500-1>
...
splitter_opt_4_10: 'FortyGigE<C/D/X/Y>,HundredGigE<E/F/A/B>, ...' # Optional for NCS-5500,
only when
    splitter is needed on per switch basis (i.e. the peer switch may or may not have the
entry)

ESI_PREFIX:91.<Pod_number>.<podregion_number>.00.00.00.00 #optional for NCS-5500 only

```

To remove a compute or a storage, delete the respective information. To replace the controller, swap the relevant port information from which the splitter cables originate.



Note For replace controller, you can change only a subset of the server information. For C-series, you can change the server information such as CIMC IP, CIMC Username, CIMC password, rack_id, and tor_info. For B-series, you can change the rack_id, chassis_id, and blade_id, but not the server hostname and management IP during the operation of replace controller.

Recovering Cisco NFVI Pods

This section describes the recovery processes for Cisco NFVI control node and the pod that is installed through Cisco VIM. For recovery to succeed, a full Cisco VIM installation must have occurred in the past, and recovery is caused by a failure of one or more of the controller services such as Rabbit MQ, MariaDB, and other services. The management node must be up and running and all the nodes must be accessible through SSH without passwords from the management node. You can also use this procedure to recover from a planned shutdown or accidental power outage.

Cisco VIM supports the following control node recovery command:

```
# ciscovim cluster-recovery
```

The control node recovers after the network partition is resolved.



Note It may be possible that database sync between controller nodes takes time, which can result in cluster-recovery failure. In that case, wait for some time for the database sync to complete and then re-run cluster-recovery.

To make sure Nova services are good across compute nodes, execute the following command:

```
# source /root/openstack-configs/openrc
# nova service-list
```

To check for the overall cloud status, execute the following:

```
# cd installer-<tagid>/tools
# ./cloud_sanity.py -c all
```

In case of a complete pod outage, you must follow a sequence of steps to bring the pod back. The first step is to bring up the management node, and check that the management node containers are up and running using the docker ps -a command. After you bring up the management node, bring up all the other pod nodes. Make

sure every node is reachable through password-less SSH from the management node. Verify that no network IP changes have occurred. You can get the node SSH IP access information from `/root/openstack-config/mercury_servers_info`.

Execute the following command sequence:

- Check the `setup_data.yaml` file and runtime consistency on the management node:

```
# cd /root/installer-<tagid>/tools
# ciscovim run --perform 1,3 -y
```

- Execute the cloud sanity command:

```
# cd/root/installer-<tagid>/tools
# ./cloud_sanity.py -c all
```

- Check the status of the REST API server and the corresponding directory where it is running:

```
# cd/root/installer-<tagid>/tools
# ./restapi.py -a status
Status of the REST API Server: active (running) since Thu 2016-08-18 09:15:39 UTC; 9h ago
REST API launch directory: /root/installer-<tagid>/
```

- If the REST API server is not running from the right installer directory, execute the following to get it running from the correct directory:

```
# cd/root/installer-<tagid>/tools
# ./restapi.py -a setup
```

```
Check if the REST API server is running from the correct target directory
# ./restapi.py -a status
Status of the REST API Server: active (running) since Thu 2016-08-18 09:15:39 UTC; 9h ago
REST API launch directory: /root/new-installer-<tagid>/
```

- Verify Nova services are good across the compute nodes by executing the following command:

```
# source /root/openstack-configs/openrc
# nova service-list
```

If cloud-sanity fails, execute `cluster-recovery` (`ciscovim cluster-recovery`), then re-execute the `cloud-sanity` and `nova service-list` steps as listed above.

Recovery of compute and OSD nodes requires network connectivity and reboot so that they can be accessed using SSH without password from the management node.

To shut down, bring the pod down in the following sequence:

1. Shut down all VMs, then all the compute nodes. It should be noted that graceful shut down of VMs is important. Check the VM status from the output of `"openstack server list --all-projects"`, which must show that all VMs are in SHUTOFF State before you proceed.
2. Shut down all compute node (s).
3. Shut down all storage nodes serially. Before proceeding to next step, ensure that you wait until the storage node shutdown is completed.
4. Shut down all controllers, but one at a time. Before proceeding to next step, wait for the controller node shutdown to complete.

5. Shut down the management node.
6. Shut down the networking gears.



Note To shut down a node, SSH to the node or connect to CIMC KVM console and issue the shutdown command

```
# shutdown -h now
```

Bring the nodes up in reverse order, that is:

1. Bring up the networking gears.
2. Bring up the management node.
3. Bring up the control nodes.
4. Bring up the storage nodes.
5. Wait until the Ceph health reports are fine and then proceed to next step.
6. Bring up the compute nodes.

In each step, ensure that each node type is completely booted up before you move on to the next node type.

Run the cluster recovery command to bring up the pod post power-outage

```
# ciscovim cluster-recovery
```

Run the cloud sanity using the command # ciscovim cloud-sanity

Execute docker cloudpulse check to ensure that all containers are up:

```
cloudpulse run --name docker_check
```

Validate the Cisco API server by running the following command:

```
# ciscovim run --perform 1,3 -y
```

Bring up all the VMs and validate if they are up (not in shutdown state). If any of the VMs are in down state, bring them up using the Horizon dashboard.

Managing Nova Compute Scheduler Filters and User Data

OpenStack Nova is an OpenStack component that provides on-demand access to compute resources by provisioning large networks of virtual machines (VMs). In addition to the standard Nova filters, Cisco VIM supports the following additional scheduler filters:

- **ServerGroupAffinityFilter**—Ensures that an instance is scheduled onto a host from a set of group hosts. To use this filter, you must create a server group with an affinity policy and pass a scheduler hint using `group` as the key and the server group UUID as the value. Use the **nova** command-line tool and the **--hint** flag. For example:

```
$ nova server-group-create --policy affinity group-1
$ nova boot --image IMAGE_ID --flavor 1 --hint group=SERVER_GROUP_UUID server-1
```

- **ServerGroupAntiAffinityFilter**—Ensures that each group instance is on a different host. To use this filter, you must create a server group with an anti-affinity policy and pass a scheduler hint, using `group` as the

key and the server group UUID as the value. Use the **nova** command-line tool and the **--hint** flag. For example:

```
$ nova server-group-create --policy anti-affinity group-1
$ nova boot --image IMAGE_ID --flavor 1 --hint group=SERVER_GROUP_UUID server-1
```

- **SameHostFilter**—Within an instance set, schedules one instance on the same host as another instance. To use this filter, pass a scheduler hint using **same_host** as the key and a list of instance UUIDs as the value. Use the **nova** command-line tool and the **--hint** flag. For example:

```
$ nova boot --image IMAGE_ID --flavor 1 --hint same_host=INSTANCE_ID server-1
```

- **DifferentHostFilter**—Within an instance set, schedules one instance on a different host than another instance. To use this filter, pass a scheduler hint using **different_host** as the key and a list of instance UUIDs as the value. The filter is the opposite of **SameHostFilter**. Use the **nova** command-line tool and the **--hint** flag. For example:

```
$ nova boot --image IMAGE_ID --flavor 1 --hint different_host=INSTANCE_ID server-1
```

In addition to scheduler filters, you can set up user data files for cloud application initializations. A user data file is a special key in the metadata service that holds a file that cloud-aware applications in the guest instance can access. For example, one application that uses user data is the cloud-init system, an open-source package that is available on various Linux distributions. The cloud-init system handles early cloud instance initializations. The typical use case is to pass a shell script or a configuration file as user data during the Nova boot, for example:

```
$ nova boot --image IMAGE_ID --flavor 1 --hint user-data FILE_LOC server-1
```

Monitoring Cisco NFVI Health with CloudPulse

You can query the state of various Cisco NFVI OpenStack endpoints using CloudPulse, an OpenStack health-checking tool. By default, the tool automatically polls OpenStack Cinder, Glance, Nova, Neutron, Keystone, Rabbit, Mariadb, and Ceph every four minutes. However, you can use a CLI REST API call from the management node to get the status of these services in real time. You can integrate the CloudPulse API into your applications and get the health of the OpenStack services on demand. You can find additional information about using CloudPulse in the following OpenStack sites:

- <https://wiki.openstack.org/wiki/Cloudpulse>
- <https://wiki.openstack.org/wiki/Cloudpulseclient>
- <https://wiki.openstack.org/wiki/Cloudpulse/DeveloperNotes>
- <https://wiki.openstack.org/wiki/Cloudpulse/OperatorTests>
- <https://wiki.openstack.org/wiki/Cloudpulse/APIDocs>

CloudPulse has two set of tests: `endpoint_scenario` (runs as a cron or manually) and `operator test` (run manually). The supported Cloudpulse tests groups include:

- `nova_endpoint`
- `neutron_endpoint`
- `keystone_endpoint`
- `glance_endpoint`

- `cinder_endpoint`

Operator tests include:

- `ceph_check`—Executes the command, "ceph -f json status" on the Ceph-mon nodes and parses the output. If the result of the output is not "HEALTH_OK" `ceph_check` the reports for an error.
- `docker_check`—Finds out if all the Docker containers are in the running state in all the nodes. It the report for an error if any containers are in the Exited state. It runs the command "docker ps -aq --filter 'status=exited'".
- `galera_check`—Executes the command, "mysql 'SHOW STATUS;'" on the controller nodes and displays the status.
- `node_check`—Checks if all the nodes in the system are up and online. It also compares the result of "nova hypervisor list" and finds out if all the computes are available.
- `rabbitmq_check`—Runs the command, "rabbitmqctl cluster_status" on the controller nodes and finds out if the rabbitmq cluster is in quorum. If nodes are offline in the cluster `rabbitmq_check` the report is considered as failed.

CloudPulse servers are installed in containers on all control nodes. The CloudPulse client is installed on the management node by the Cisco VIM installer. To execute CloudPulse, source the `openrc` file in the `openstack-configs` directory and execute the following:

```
[root@MercRegTB1 openstack-configs]# cloudpulse --help
usage: cloudpulse [--version] [--debug] [--os-cache]
                [--os-region-name <region-name>]
                [--os-tenant-id <auth-tenant-id>]
                [--service-type <service-type>]
                [--endpoint-type <endpoint-type>]
                [--cloudpulse-api-version <cloudpulse-api-ver>]
                [--os-cacert <ca-certificate>] [--insecure]
                [--bypass-url <bypass-url>] [--os-auth-system <auth-system>]
                [--os-username <username>] [--os-password <password>]
                [--os-tenant-name <tenant-name>] [--os-token <token>]
                [--os-auth-url <auth-url>]
                <subcommand> ...
```

To check the results of periodic CloudPulse, enter the following command:

```
[root@MercRegTB1 openstack-configs]# cloudpulse result
+-----+-----+-----+-----+-----+
| uuid                                     | id  | name                | testtype | state |
+-----+-----+-----+-----+-----+
| 4f4c619a-1ba1-44a7-b6f8-3a06b5903260 | 7394 | ceph_check          | periodic | success |
| 68b984fa-2edb-4d66-9d9b-7c1b77d2322e | 7397 | keystone_endpoint  | periodic | success |
| c53d5f0f-a710-4612-866d-caa896e2d135 | 7400 | docker_check       | periodic | success |
| 988d387c-1160-4601-b2ff-9dbb98a3cd08 | 7403 | cinder_endpoint    | periodic | success |
| 5d702219-eacc-47b7-ae35-582bb8e9b970 | 7406 | glance_endpoint    | periodic | success |
| 033ca2fc-41c9-40d6-b007-16e06dda812c | 7409 | rabbitmq_check     | periodic | success |
| 8476b21e-7111-4b1a-8343-afd634010b07 | 7412 | galera_check       | periodic | success |
| a06f8d6e-7b68-4e14-9b03-bc4408b55b48 | 7415 | neutron_endpoint   | periodic | success |
| ef56b26e-234d-4c33-aeel-ffc99de079a8 | 7418 | nova_endpoint      | periodic | success |
| f60021c7-f70a-44fb-b6bd-03804e5b7bf3 | 7421 | node_check         | periodic | success |
+-----+-----+-----+-----+-----+
```

To view all CloudPulse tests:

```
# cd /root/openstack-configs
# source openrc
# cloudpulse test-list
```

To run a CloudPulse test on demand:

```
# cd /root/openstack-configs
# source openrc
# cloudpulse run --name <test_name>
# cloudpulse run --all-tests
# cloudpulse run --all-endpoint-tests
# cloudpulse run --all-operator-tests
```

To run a specific CloudPulse test on demand:

```
# cloudpulse run --name neutron_endpoint
+-----+
| Property | Value |
+-----+
| name      | neutron_endpoint |
| created_at | 2016-03-29T02:20:16.840581+00:00 |
| updated_at | None |
| state     | scheduled |
| result    | NotYetRun |
| testtype  | manual |
| id        | 3827 |
| uuid      | 5cc39fa8-826c-4a91-9514-6c6de050e503 |
+-----+
```

To show detailed results of a specific CloudPulse run:

```
#cloudpulse show 5cc39fa8-826c-4a91-9514-6c6de050e503
+-----+
| Property | Value |
+-----+
| name      | neutron_endpoint |
| created_at | 2016-03-29T02:20:16+00:00 |
| updated_at | 2016-03-29T02:20:41+00:00 |
| state     | success |
| result    | success |
| testtype  | manual |
| id        | 3827 |
| uuid      | 5cc39fa8-826c-4a91-9514-6c6de050e503 |
+-----+
```

To see the CloudPulse options, source the openrc file in openstack-configs dir and execute:

```
#cloudpulse --help
```

The CloudPulse project has a RESTful Http service called the Openstack Health API. Through this API cloudpulse allows the user to list the cloudpulse tests, create new cloudpulse tests and see the results of the cloudpulse results.

The API calls described in this documentation require keystone authentication. We can use the keystone v2 or v3 version for the authentication. The corresponding configuration must be configured properly in the cloudpulse config in order that the cloudpulse can reach the v2 or the v3 keystone API.

The Identity service generates authentication tokens that permit access to the Cloudpulse REST APIs. Clients obtain this token and the URL endpoints for other service APIs by supplying their valid credentials to the

authentication service. Each time you make a REST API request to Cloudpulse, you need to supply your authentication token in the X-Auth-Token request header.

Assessing Cisco NFVI Status with Cloud-Sanity

The cloud-sanity tool is designed to give you a quick overall status of the pods health checks. Cloud-sanity can run tests on all node types in the Pod: management, control, compute and ceph storage.

The following are test areas supported in cloud-sanity:

1. RAID Disk health checks.
2. Basic network connectivity between the management node and all other nodes in the Pod.
3. Mariadb cluster size.
4. RabbitMQ operation and status.
5. Nova service and hypervisor list.
6. CEPHMon operation and status.
7. CEPHOSD operation and status.

To run the cloud-sanity tool, login to the management node and run the ciscovim command with the cloud-sanity option

Cloud-Sanity user workflow:

1. Use “ciscovim cloud-sanity create ...” command to initiate a test.
2. Use “ciscovim cloud-sanity list ...” command to view summary/status of current test jobs.
3. Use “ciscovim cloud-sanity show ... --id <ID>” command to view detail test results.
4. Use “ciscovim cloud-sanity delete ... --id <ID>” to delete test results no longer needed.

The results are maintained so that you can view them any time.



Note Delete the results which are no longer needed.

Step 1 To run the cloud sanity complete the following steps:

```
# ciscovim help cloud-sanity
usage: ciscovim cloud-sanity [--id <id>] [--skip-disk-checks] [-y]
      create|delete|list|show test|result
      all|control|compute|cephmon|cephosd|management
```

Run cloud-sanity test suite

```
Positional arguments:
  create|delete|list|show      The control command to perform
  test|result                  The identity of the task/action
  all|control|compute|cephmon|cephosd|management
                              The sanity check
```

```
Optional arguments:
  --id <id>                ID used to identify specific item to
                           show/delete.
  --skip-disk-checks       Flag to skip running disk-checks during
                           cloud-sanity test
  -y, --yes                Yes option to perform the action
```

Step 2 To run the cloud sanity test, you need to create a test job. Once the test job is created, the system displays a message with the time and the ID when the test job was created.

Run the following command to create a test job:

```
# ciscovim cloud-sanity create test all
+-----+-----+
| Field      | Value                               |
+-----+-----+
| command    | create                              |
| created_at | 2018-03-07T15:37:41.727739         |
| id         | c000ca20-34f0-4579-a997-975535d51dda |
| result     |                                       |
| status     | not_run                             |
| test_name  | all                                  |
| updated_at | None                                 |
+-----+-----+
```

The user can create different test suites based on target roles. All, management, control, compute, cephmon and cephosd. Only one test will be run at any time.

Example test create commands:

- `ciscovim cloud-sanity create test control`
- Runs control node tests only
- `ciscovim cloud-sanity create test compute`
- Runs compute nodes tests only
- `ciscovim cloud-sanity create test management`
- Runs management node tests only
- `ciscovim cloud-sanity create test cephmon`
- Runs cephmon tests only
- `ciscovim cloud-sanity create test cephosd`
- Runs cephosd tests only

The cloud-sanity tests use the disk-maintenance and osd-maintenance tools to assess overall health and status of the RAID disks and OSD status.

Note Failures detected in RAID disk health and CEPHOSD operational status can be future evaluated with the disk-maintenance and osd-maintenance tools. See the sections on those tools for information on their use.

Step 3 The `ciscovim cloud-sanity list ...` command is used to monitor a currently running test or just view all the tests that have been run/completed in the past.

```
# ciscovim cloud-sanity list test all
+-----+-----+-----+-----+
| ID                                     | Sanity Check | Status  | Created          |
+-----+-----+-----+-----+
| c000ca20-34f0-4579-a997-975535d51dda | all          | Complete | 2018-03-07 15:37:41 |
| 83405cf0-e75a-4ce2-a438-0790cf0a196a | cephmon     | Complete | 2018-03-07 15:52:27 |
| 6beceb00-4029-423b-87d6-5aaf0ce087ff | cephmon     | Complete | 2018-03-07 15:55:01 |
| 2707a2e1-d1b5-4176-8715-8664a86bbf7d | cephosd    | Complete | 2018-03-07 16:11:07 |
| b30e1f49-a9aa-4f90-978a-88ba1f0b5629 | control     | Complete | 2018-03-07 16:14:29 |
| f024ff94-ac3e-4745-ba57-626b58ca766b | compute     | Running  | 2018-03-07 16:16:44 |
+-----+-----+-----+-----+
```

We can filter on cephmon if needed

```
# ciscovim cloud-sanity list test cephmon
```

```

+-----+-----+-----+-----+
| ID                | Sanity Check | Status  | Created          |
+-----+-----+-----+-----+
| 83405cf0-e75a-4ce2-a438-0790cf0a196a | cephmon      | Complete | 2018-03-07 15:52:27 |
| 6beceb00-4029-423b-87d6-5aaf0ce087ff | cephmon      | Complete | 2018-03-07 15:55:01 |
+-----+-----+-----+-----+
    
```

Example cloud-sanity list commands:

- ciscovim cloud-sanity list control
- ciscovim cloud-sanity list compute
- ciscovim cloud-sanity list management
- ciscovim cloud-sanity list cephmon
- ciscovim cloud-sanity list cephosd

Step 4

This functionality allows you to view the details results of the test-sanity. Cloud-sanity test results can be passed, failed, or skipped. A skipped test is one that is not supported on this particular POD (ex. RAID test is only support with Hardware RAID.) A skipped test does not count to the overall pass/fail status.

```

# ciscovim cloud-sanity show test all --id c000ca20-34f0-4579-a997-975535d51dda
Cloud sanity Results
+-----+-----+-----+-----+
| Role      | Task                                                                 | Result |
+-----+-----+-----+-----+
| Management | Management - Disk Maintenance RAID Health ***** | PASSED |
| Management | Management - Container Version Check ***** | PASSED |
| Management | Management - Disk Maintenance VD Health ***** | PASSED |
| Control    | Control - Check RabbitMQ is Running ***** | PASSED |
| Control    | Control - Check RabbitMQ Cluster Status ***** | PASSED |
| Control    | Control - Container Version Check ***** | PASSED |
| Control    | Control - Check MariaDB Cluster Size ***** | PASSED |
| Control    | Control - Ping All Controller Nodes ***** | PASSED |
| Control    | Control - Check Nova Service List ***** | PASSED |
| Control    | Control - Ping Internal VIP ***** | PASSED |
| Control    | Control - Disk Maintenance RAID Health ***** | PASSED |
| Control    | Control - Disk Maintenance VD Health ***** | PASSED |
| Compute    | Compute - Check Nova Hypervisor List ***** | PASSED |
| Compute    | Compute - Disk Maintenance RAID Health ***** | PASSED |
| Compute    | Compute - Ping All Compute Nodes ***** | PASSED |
| Compute    | Compute - Container Version Check ***** | PASSED |
| Compute    | Compute - Disk Maintenance VD Health ***** | PASSED |
| CephOSD    | CephOSD - Ping All Storage Nodes ***** | PASSED |
| CephOSD    | CephOSD - Check OSD Result Without OSDInfo ***** | PASSED |
| CephOSD    | CephOSD - OSD Overall Status ***** | PASSED |
| CephOSD    | CephOSD - Check OSD Result With OSDInfo ***** | PASSED |
    
```

```

| CephMon | CephMon - Check Cephmon Status ***** | PASSED |
| CephMon | CephMon - Ceph Cluster Check ***** | PASSED |
| CephMon | CephMon - Check Cephmon Results ***** | PASSED |
| CephMon | CephMon - Check Cephmon is Running ***** | PASSED |
+-----+-----+-----+
[PASSED] Cloud Sanity All Checks Passed

```

Step 5 To delete the cloud sanity test results run the following command:

```
# ciscovim cloud-sanity delete test all --id c000ca20-34f0-4579-a997-975535d51dda
```

```
Perform the action. Continue (Y/N)Y
```

```
Delete of UUID c000ca20-34f0-4579-a997-975535d51dda Successful
```

```
# ciscovim cloud-sanity list test all
```

```

+-----+-----+-----+-----+
| ID | Sanity Check | Status | Created |
+-----+-----+-----+-----+
| 83405cf0-e75a-4ce2-a438-0790cf0a196a | cephmon | Complete | 2018-03-07 15:52:27 |
| 6beceb00-4029-423b-87d6-5aaf0ce087ff | cephmon | Complete | 2018-03-07 15:55:01 |
| 2707a2e1-d1b5-4176-8715-8664a86bbf7d | cephosd | Complete | 2018-03-07 16:11:07 |
| b30e1f49-a9aa-4f90-978a-88ba1f0b5629 | control | Complete | 2018-03-07 16:14:29 |
| f024ff94-ac3e-4745-ba57-626b58ca766b | compute | Complete | 2018-03-07 16:16:44 |
+-----+-----+-----+-----+

```

The cloud-sanity tests use the disk-maintenance and osd-maintenance tools to assess overall health and status of RAID disks and OSD status.

Note Failures detected in RAID disk health and CEPHOSD operational status can be future evaluated with the disk-maintenance and osd-maintenance tools. See the sections on those tools for information on their use.

Service Catalog URL

The OpenStack Keystone service catalog allows API clients to dynamically discover and navigate to cloud services. Cloudpulse has its own service URL which is added to the Keystone service catalog. You need to send a token request to Keystone to find the service URL of cloudpulse. The token request lists all the catalog of services available.

Get Token from Keystone

To get the token from keystone run the following commands:

Resource URI

Verb	URI
POST	http://<controller_lb_ip>:5000/v2.0/tokens

Example

```

JSON Request
POST / v2.0/tokens
Accept: application/json
{
  "auth": {
    "passwordCredentials":{
      "username": "admin",
      "password": "iVF1YciVKoMGId1O"
    }
  }
}

JSON Response
200 OK
Content-Type: application/json
{
  "access": {
    "token": {
      "issued_at": "2017-03-29T09:54:01.000000Z",
      "expires": "2017-03-29T10:54:01Z",
      "id":
      "gAAAAABY24Q5TDIqizuGmhOXakV2rIzSvSPQpMAmC7SA2UzUXZQXSH-ME98d3Fp4Fsj16G561a420B4BK0fylcykL22Ec09",
      .....
      .....
    }
  }
}

```

Get Service Catalog URL for Cloudpulse

Resource URI

Verb	URI
GET	http://<controller_ip>:35357/v2.0/endpoints

Example

```

JSON Request
GET /v2.0/endpoints
Accept: application/json

JSON Response
200 OK
Content-Type: application/json
{"endpoints": [
  {"internalurl": "http://<controller>:9999",
   "adminurl": "http://<controller>:9999",
   "publicurl": "http://<controller>:9999"
  }]
}

```

Cloudpulse APIs

The following are a list of APIs and the corresponding functions that the API performs. The cloudpulse APIs is accessed with the X-Auth-Token which contains the token which is received from the Keystone token generation API mentioned in the preceding panel.

List of Cloudpulse Tests

To get the list of cloudpulse tests:

Resource URI

Verb	URI
GET	http://<controller_ip>:9999/cpulse

Example

```
JSON Request
GET /cpulse
Accept: application/json
```

```
JSON Response
200 OK
Content-Type: application/json
{
  "cpulses": [
    {
      "name": "galera_check",
      "state": "success",
      "result": "ActiveNodes:16.0.0.37,16.0.0.17,16.0.0.27",
      "testtype": "periodic",
      "id": 4122,
      "uuid": "a1b52d0a-ca72-448a-8cc0-5bf210438d89"
    }
  ]
}
```

Get detailed result of 1 test

To get detailed result of the test.

Resource URI

Verb	URI
GET	http://<controller_ip>:9999/cpulse/<uuid>

Uuid : uuid of the test

Example

```
JSON Request
GET /cpulse/e6d4de91-8311-4343-973b-c507d8806e94
Accept: application/json
```

```
JSON Response
200 OK
Content-Type: application/json
{
  "name": "galera_check",
  "state": "success",
  "result": "ActiveNodes:16.0.0.37,16.0.0.17,16.0.0.27",
  "testtype": "periodic",
  "id": 4122,
  "uuid": " e6d4de91-8311-4343-973b-c507d8806e94"
}
```

Get List of Tests Available

To get a list of available cloudpulse tests:

Resource URI

Verb	URI
GET	http://<controller_ip>:9999/cpulse/list_tests

Example

```
JSON Request
GET /cpulse/list_tests
Accept: application/json
```

```
JSON Response
200 OK
Content-Type: application/json
{
  "endpoint_scenario":
  "all_endpoint_tests\ncinder_endpoint\n glance_endpoint\nkeystone_endpoint\nneutron_endpoint\nnova_endpoint",

  "operator_scenario":
  "all_operator_tests\nceph_check\ndocker_check\n galera_check\nnode_check\nrabbitmq_check"
}
```

Schedule a manual cloudpulse test:

To schedule a manual test of cloudpulse run the following commands:

Resource URI

Verb	URI
POST	http://<controller_ip>:9999/cpulse

Example

```
JSON Request
POST /cpulse
Accept: application/json
{
  "name": "galera_check"
}
```

```
JSON Response
200 OK
Content-Type: application/json
{
  "name": "galera_check",
  "state": "scheduled",
  "result": "NotYetRun",
  "testtype": "manual",
  "id": 4122,
  "uuid": " e6d4de91-8311-4343-973b-c507d8806e94"
}
```

Remove the results of a test

To remove the results of a test.

Resource URI

Verb	URI
DELETE	http://<controller_ip>:9999/cpulse/<uuid>

Uuid : uuid of the test

Example

```
JSON Request
DELETE /cpulse/68ffaae3-9274-46fd-b52f-ba2d039c8654
Accept: application/json
```

```
JSON Response
204 No Content
```

Checking Network Connections


You can use Virtual Machine Through Put (VMTP) to check Layer 2 and Layer 3 data plane traffic between Cisco NFVI compute nodes. VMTP performs ping connectivity, round trip time measurement (latency), and TCP/UDP throughput measurement for the following Cisco NFVI east to west VM-to-VM flows:

- Same network (private fixed IP, flow number 1).
- Different network using fixed IP (same as intra-tenant L3 fixed IP, flow number 2).
- Different network using floating IP and NAT (same as floating IP inter-tenant L3, flow number 3.)
- When an external Linux host is available for testing north to south flows, external host to VM download and upload throughput and latency (L3/floating IP, flow numbers 4 and 5).

The following figure shows the traffic flows VMTP measures. Cloud traffic flows are checked during Cisco VIM installation and can be checked at any later time by entering the following command:

```
$ ciscovim run --perform 8 -y
```

Figure 1: VMTP Cloud Traffic Monitoring



413788

Enabling NFVBench Post Deployment

NFVBench is a data plane performance benchmark tool for NFVI that can be optionally installed after the pod deployment.

NFVBench is used to:

- Verify that the data plane is working properly and efficiently when using well defined packet paths that are typical of NFV service chains.
- Measure the actual performance of your data plane so that you can estimate what VNFs can expect from the infrastructure when it comes to receiving and sending packets.

While VMTP only measures VM to VM traffic, NFVBench measures traffic flowing from an integrated software traffic generator (TRex) running on the management node to the ToR switches to test VMs running in compute nodes.


In Cisco VIM, the NFVBench (performance benchmark) is an optional tool. You can deploy NFVBench after the installation of the pod.

Before you begin

- An extra 10 GE (Intel X710 NIC) or 40GE (Intel XL710 NIC) must be installed on the management node.

- A TRex traffic generator which uses the DPDK interface to interact with Intel NIC and makes use of hardware, instead of software to generate packets. This approach is more scalable and enables NFVBench to perform tests without software limitations.
- Wire two physical interfaces of the Intel NIC to the TOR switches (as shown in the following figure).

Figure 2: NFVBench topology setup



Procedure

	Command or Action	Purpose
<p>Step 1</p>	<p>Enable the NFVBench configuration in the setup_data.yaml file.</p>	<p>Sample configuration files for OVS/VLAN or VPP mechanism driver:</p> <pre> NFVBENCH: enabled: True # True or False tor_info: {TORa: eth1/42, TORb: eth1/42} # mandatory # tor_info: {TOR: 'eth1/42,eth1/43'} # use if there is only one TOR switch # nic_ports: 3,4 # Optional input, indicates which 2 of the 4 available ports # of 10G Intel NIC on the management node is NFVbench tool using # to send and receive traffic. # Defaults to the first 2 ports of NIC (ports 1 and 2) if not specified. # Port number must be between 1 and 4, one port cannot be used twice. # nic_slot: <int> # Optional, defaults to 1st set of unbonded pair of NIC ports in an Intel 710 or 520 card the code finds; Via this option, one can choose to run NFVbench via XL710, 520 or X710 card # Example: # nic_ports: 1,4 # the first and the last port of Intel NIC are used # nic_slot: 2 # # Optional, defaults to 1st set of unbonded pair of </pre>

	Command or Action	Purpose
		<pre> NIC ports in an Intel 710 or 520 card the code finds; Via this option, one can choose to run NFVbench via XL710, 520 or X710 card # nic_slot: Management node slot on which the NFVbench NIC card is anchored off # For VTS/VXLAN # vteps: "vtep_ip1,vtep_ip2" # Mandatory and needed only for VTS/VXLAN. Specify separated IP pairs in tenant network and not in the tenant pool, reconfigurable # # For VXLAN over vxlan-tenant network # vteps: "vtep_ip1,vtep_ip2" # Mandatory, specify separated IP pairs in vxlan-tenant network and not in the vxlan-tenant pool, reconfigurable # vnis: "vni_id1, vni_id2" # Mandatory, specify the VNI range to be used for all vxlan networks created by NFVbench for benchmarking Sample configuration for VTS mechanism driver: NFVBENCH: enabled: True # True or False tor_info: {TORa: eth1/42, TORb: eth1/42} # mandatory vtep: "ip1, ip2" # Mandatory and needed only for VTS/VXLAN. # Specify any pair of unused VLAN ids to be used # for VLAN to VxLAN encapsulation in TOR switch. # tor_info: {TOR: 'eth1/42,eth1/43'} # Use if there is only one TOR switch. # nic_ports: 3,4 # Optional input, indicates which 2 of the 4 available ports # of 10G Intel NIC on the management node is NFVbench tool using # to send and receive traffic. # Defaults to the first 2 ports of NIC (ports 1 and 2) if not specified. # Port number must be between 1 and 4, one port cannot be used twice. # Example: # nic_ports: 1,4 # the first and the last port of Intel NIC are used # nic_slot: 2 # # Optional, defaults to 1st set of unbonded pair of NIC ports in an Intel 710 or 520 card the code finds; Via this option, one can choose to run NFVbench via XL710 or X710 card # Note: if nic_ports are defined, then nic_slot has to be defined and vice-versa VTS_PARAMETERS: ... VTS_DAY0: '<True False>' # Required parameter when VTS enabled VTS_USERNAME: '<vts_username>' # Required parameter when VTS enabled VTS_PASSWORD: '<vts_password>' # Required parameter </pre>

	Command or Action	Purpose
		<pre>when VTS enabled VTS_NCS_IP: '11.11.11.111'# '<vts_ncs_ip>', mandatory when VTS enabled VTC_SSH_USERNAME: 'admin'# '<vtc_ssh_username>', mandatory for NFVBench VTC_SSH_PASSWORD: 'my_password'# '<vtc_ssh_password>', mandatory for NFVBench</pre>
Step 2	Configuring minimal settings of NFVBench:	<pre># Minimal settings required for NFVBench TORSWITCHINFO: CONFIGURE_TORS: <True or False> # True if switches should be configured to support NFVBench ... SWITCHDETAILS: - hostname: 'TORa' # Hostname matching 'tor_info' switch name. username: 'admin' # Login username for switch user. password: 'my_password' # Login password for switch user. ssh_ip: '172.31.230.123' # SSH IP for switch. - hostname: 'TORb' username: 'admin' password: 'my_password' ssh_ip: '172.31.230.124'</pre> <p>TOR switches will be configured based on information provided in tor_info. Two ports specified by interfaces are configured in trunk mode. It is not required to set 'CONFIGURE_TORS' to 'True', but then manual configuration is necessary.</p> <p>With VTS as mechanism driver additional settings are needed. NFVBench needs access to VTS NCS to perform cleanup after it detaches the traffic generator port from VTS. Also a pair of VTEP VLANs is required for VLAN to VxLAN mapping. Value can be any pair of unused VLAN ID.</p>
Step 3	Reconfigure Cisco VIM to start or restart the NFVBench container. To reconfigure add necessary configuration to the setup_data.yaml file, run the reconfigure command as follows.	<pre>[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir [root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/ [root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# # update the setup_data to include NFVBENCH section [root@mgmt1 ~]# cd /root/MyDir/ [root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx [root@mgmt1 ~]# ciscovim --setupfile /root/MyDir/setup_data.yaml reconfigure</pre> <p>After the reconfiguration, you can see that the NFVBench container is up and ready for use.</p>


NFVBench Usage

Built-in packet paths

NFVBench can setup and stage three different packet paths.

The default packet path is called **PVP** (Physical - VM - Physical) and represents a typical service chain made of 1 VNF/VM:

Figure 3: Single VNF chain (PVP)



The traffic generator runs inside the NFVBench container on the management node. DC-SW represents the top of rack switch(es). The VNF is a test VM that contains a fast L3 router based on FD.io VPP. This VNF image can also be configured to run an L2 forwarder based on DPDK testpmd (both options generally yield roughly similar throughput results).


Traffic is made of UDP packets generated on the 2 physical interfaces (making it a bi-directional traffic). Packets are forwarded by the switch to the appropriate compute node before arriving to the virtual switch, then to the VNF before looping back to the traffic generator on the other interface. Proper stitching of the traffic on the switch is performed by NFVBench by using the appropriate mechanism (VLAN tagging for VLAN based deployments, VxLAN VTEP in the case of VTS deployments).

The performance of the PVP packet path provides a very good indication of the capabilities and efficiency of the NFVi data plane in the case of a single service chain made of 1 VNF/VM.

NFVBench also supports more complex service chains made of 2 VM in sequence and called PVVP (Physical-VM-VM-Physical).

In a PVVP packet path, the 2 VMs reside on the same compute node (PVVP intra node).

Figure 4: 2-VNF chain (PVVP)



NFVBench Command-Line Options and Status

You can execute most of the benchmark variants using CLI options from the shell prompt on the management node. The common NFVBench command-line options are displayed using the `--help` option:

```
[root@mgmt1 ~]# nfvbench --help
```

Use the `--status` option to check the NFVBench version and see if benchmark is running:

```
[root@mgmt1 ~]# nfvbench --status
2018-12-19 20:29:49,656 INFO Version: 3.X.X
2018-12-19 20:29:49,656 INFO Status: idle
2018-12-19 20:29:49,704 INFO Discovering instances nfvbench-loop-vm...
2018-12-19 20:29:50,645 INFO Discovering flavor nfvbench.medium...
2018-12-19 20:29:50,686 INFO Discovering networks...
2018-12-19 20:29:50,828 INFO No matching NFVBench resources found
```

Using NFVBench Configuration File

More advanced use-cases require passing a yaml NFVBench configuration file. You can get the default NFVBench configuration file by using the `-show-default-config` option.

Navigate to the host folder mapped to a container (`/root/nfvbench`) and copy the default NFVBench configuration by using the following command:

```
[root@mgmt1 ~]# cd /root/nfvbench
[root@mgmt1 ~]# nfvbench --show-default-config > nfvbench.cfg
```

Edit the configuration file to remove all the properties that are not changed and retain the properties that are required. You can then pass the edited file to NFVBench using the `-c` option.

Ensure that you use a container visible pathname as this file is read from the container. The `/root/nfvbench` folder on the host is mapped to the `/tmp/nfvbench` folder in the container, so that the configuration file stored under `/root/nfvbench` can be referenced as `/tmp/nfvbench/<file>` in the CLI option.

For example:

```
[root@mgmt1 ~]# nfvbench -c /tmp/nfvbench/nfvbench.cfg
```

Control Plane Verification

If you are trying NFVBench for the first time, verify that the tool can stage the default packet path properly without sending any traffic.

The `--no-traffic` option exercises the control plane by creating a single test service chain with one VM, but does not send any traffic.

The following command stages only the default PVP packet path (but does not generate any traffic):

```
[root@mgmt1 ~]# nfvbench --no-traffic
```

Fixed Rate Run Test

The data plane traffic test is done to generate traffic at a fixed rate for a fixed duration. For example, you can generate a total of 10000 packets per second (which is 5000 packets per second per direction) for the default duration (60 seconds), with the default frame size of 64 bytes using the following configuration:

```
[root@mgmt1 ~]# nfvbench
```

Packet Sizes

You can specify any list of frame sizes using the `-frame-size` option (pass as many as desired), including IMIX. Following is an example, to run a fixed rate with IMIX and 1518 byte frames:

```
[root@mgmt1 ~]# nfvbench --rate 10kpps --frame-size IMIX --frame-size 1518
```

NDR and PDR Test

NDR and PDR test is used to determine the performance of the data plane in terms of throughput at a given drop rate.

- No Drop Rate(NDR) is the highest throughput achieved while allowing zero packet drop (allows a very low drop rate usually lesser than 0.001%).
- Partial Drop Rate (PDR) is the highest throughput achieved while allowing most at a given drop rate (typically less than 0.1%).

NDR is always less or equal to PDR.

To calculate the NDR and PDR for your pod, run the following command:

```
[root@mgmt1 ~]# nfvbench --rate ndr_pdr
```

Multi-chain Test

In multi-chain test, each chain represents an independent packet path symbolizing real VNF chain. You can run multiple concurrent chains and better simulate network conditions in real production environment. Results with single chain versus with multiple chains usually vary because of services competing for resources (RAM, CPU, and network).

To stage and measure multiple service chains at the same time, use `--service-chain-count` flag or shorter `-scc` version.

The following example shows how to run the fixed rate run test with ten PVP chains:

```
[root@mgmt1 ~]# nfvbench -scc 10 --rate 100kpps
```

The following example shows how to run the NDR/PDR test with ten PVP chains:

```
[root@mgmt1 ~]# nfvbench -scc 10 --rate ndr_pdr
```

Multi-Flow Test


In Multi-flow test, one flow is defined by a source and destination MAC/IP/port tuple in the generated packets. It is possible to have many flows per chain. The maximum number of flows that are supported is in the order of 1 million flows per direction.

The following command runs three chains with a total of 100K flows per direction (for all chains):

```
[root@mgmt1 ~]# nfvbench -scc 3 -fc 100k
```

Encapsulation


By default, Nfvbench uses vlan tagging for the generated traffic and directs the traffic to the vswitch in the target compute node (OVS or VPP). The following diagram illustrates an example of NfvBench execution with two chains using VLAN and when VPP is vswitch.



If VxLAN is enabled, it is possible to force the use of VxLAN using the `-vxlan` CLI option.

The provision of custom configuration allows you to specify more VxLAN options such as specific VNIs to use. For more details, check the default configuration file.

The following diagram illustrates an example of NfvBench execution with two chains using VxLAN and when VPP is vswitch.



SR-IOV

If SR-IOV is deployed, NFVbench can support to send the traffic to the test VMs that use SR-IOV instead of vswitch.

To test SR-IOV, you must have compute nodes configured to support one or more SR-IOV interfaces (also known as PF or physical function) and OpenStack to support SR-IOV.

You need to know:

- The name of the physical networks associated with the SR-IOV interfaces (this is a configuration in Nova compute).
- The VLAN range that can be used on the switch ports that are wired to the SR-IOV ports. Such switch ports are normally configured in trunk mode with a range of VLAN ids enabled on that port.

For example, if two SR-IOV ports exist per compute node, two physical networks are generally configured in OpenStack with a distinct name.

The VLAN range to use is also allocated and reserved by the network administrator and in coordination with the corresponding top of rack switch port configuration.

To enable SR-IOV test, you must provide the following configuration options to NFVbench in the configuration file.

This example instructs NFVbench to create the left and right networks of a PVP packet flow to run on two SRIOV ports named "phys_sriov0" and "phys_sriov1" using resp. segmentation_id 2000 and 2001:

```
sriov: true
internal_networks:
  left:
    segmentation_id: 2000
    physical_network: phys_sriov0
  right:
    segmentation_id: 2001
    physical_network: phys_sriov1
```

The segmentation ID fields must be different.

In case of PVVP, the middle network must be provisioned properly. The same physical network can also be shared by the virtual networks, but with different segmentation IDs.

External Chain Test

NFVBench measures the performance of chains that are pre-staged (using any means external to NFVBench). These chains can be real VNFs with L3 routing capabilities or L2 forwarding chains.

The external chain test is used when you want to use NFVBench only for traffic generation. In this case, NFVBench sends traffic from traffic generator and reports results without performing any staging or configuration.

Ensure that the setup is staged externally prior to running NFVbench by creating networks and VMs with a configuration that allows generated traffic to pass. You need to provide the name of the two edge neutron networks to which the traffic generators are to be attached, during configuration so that NFVbench can discover the associated segmentation ID (VLAN or VNI).

If the external chains support only L2 forwarding, the NFVBench configuration must specify the destination MAC to use in each direction for each chain

If the external chains support IPv4 routing, the NFVBench configuration must specify the public IP addresses of the service chain end points (gateway IP) that are used to discover destination MAC using ARP.

To measure performance for external chains, use the `--service-chain EXT` (or `-sc EXT`) option:

```
[root@mgmt1 ~]# nfvbench -sc EXT
```

NFVBench Results

You can store the NFVBench detailed results in JSON format using the below command, if you pass the `--json` option with a destination file name or the `--std-json` option with a destination folder pathname to use the standard file name generated by NFVBench.

```
[root@mgmt1 ~]# nfvbench -scc 3 -fc 10 -fs 64 --json /tmp/nfvbench/my.json
```

The above command stores the results in JSON file in `/tmp/nfvbench` container directory, which is mapped to the host `~/nfvbench` directory. The first file is named as `my.json`.

Examples of NFVBench Result Execution

VLAN Fixed Rate

The following example shows the generation of the default frame size (64B) over 100Kpps for the default duration (60s) with the default chain type (PVP), default chain count (1) and default flow count (10k):

```
# nfvbench -rate 100kpps -fs IMIX
```

The summary of NFVBench result is shown below:

```
Date: 2018-12-19 21:26:26
NFVBench version 3.0.4.dev2
Openstack Neutron:
  vSwitch: VPP
  Encapsulation: VLAN
Benchmarks:
> Networks:
  > Components:
    > Traffic Generator:
      Profile: trex-local
      Tool: TRex
    > Versions:
      > Traffic_Generator:
        build_date: Nov 13 2017
        version: v2.32
        built_by: hhaim
        mode: STL
        build_time: 10:58:17
      > VPP: 18.07
      > CiscoVIM: 2.4.3-15536
> Service chain:
  > PVP:
    > Traffic:
      Profile: custom_traffic_profile
      Bidirectional: True
      Flow count: 10000
      Service chains count: 1
      Compute nodes: [u'nova:c45-compute-2']
```

The following NFVBench Result Execution Summary table provides the drop rate measured (in this example no drops) and latency measurements in micro-seconds (time for a packet to be sent on one port and receive back on the other port)

Table 2: NFVBench Result Execution Summary

L2 Frame Size	Drop Rate	Avg Latency (usec)	Min Latency (usec)	Max Latency (usec)
IMIX	0.0000%	28	20	330

The following NFVBench Result Configuration table provides the mode details for both forward and reverse directions, where:

- Requested TX Rate is the rate that is requested in bps and pps.
- Actual TX Rate is the actual rate achieved by the traffic generator. It can be lower than the requested rate if there is not enough CPU.
- RX Rate is the rate of packets received.

Table 3: NFVBench Result Configuration

Direction	Requested TX Rate (bps)	Actual TX Rate (bps)	RX Rate (bps)	Requested TX Rate (pps)	Actual TX Rate (pps)	RX Rate (pps)
Forward	152.7333 Mbps	152.7334 Mbps	152.7344 Mbps	50,000 pps	50,000 pps	50,000 pps
Reverse	152.7333 Mbps	152.7334 Mbps	152.7344 Mbps	50,000 pps	50,000 pps	50,000 pps
Total	305.4667 Mbps	305.4668 Mbps	305.4688 Mbps	100,000 pps	100,000 pps	100,000 pps

The Forward and Reverse Chain Packet Counters and Latency table shows the number of packets sent or received at different hops in the packet path, where:

- TRex.TX.p0 or p1 shows the number of packets sent from each port by the traffic generator.
- Vpp.RX.vlan.<id> shows the number of packets received on the VLAN subinterface with VLAN id <id> in the VPP vswitch.
- Vpp.TX.veth/<id> shows the number of packets sent to the VM.
- Vpp.RX.veth/<id> shows the number of packets received from the VM.

Table 4: Forward Chain Packet Counters and Latency

Chain	TRex.TX.p0	vppRXlan1/0	vppTXveth2	vppRXveth1	vppTXlan1/1	TRex.RX.p1	Avg Lat.	Min lat.	Max lat
0	3,000,001	=>	=>	=>	=>	3,000,001	28 usec	20 usec	320 usec

Table 5: Reverse Chain Packet Counters and Latency

Chain	TrexTXp1	vppRXlan0	vppTXveth1	vppRXveth2	vppTXlan0	TrexRXp0	Avg Lat.	Min lat.	Max lat
0	3,000,001	=>	=>	=>	=>	3,000,001	28 usec	20 usec	330 usec



Note ‘=>’ indicates that no packets are dropped. Otherwise the value will indicate the number of packets dropped.

VLAN NDR/PDR

Use the following command to measure NDR and PDR for IMIX, with the default chain type (PVP), default chain count (1) and default flow count (10k):

```
# nfvbench -fs IMIX
```

The summary of the NFVBench result execution is shown below:

```
Date: 2018-12-20 23:11:01
NFVBench version 3.0.5.dev2
Openstack Neutron:
  vSwitch: VPP
  Encapsulation: VLAN
Benchmarks:
> Networks:
  > Components:
    > Traffic Generator:
      Profile: trex-local
      Tool: TRex
    > Versions:
      > Traffic_Generator:
        build_date: Nov 13 2017
        version: v2.32
        built_by: hhaim
        mode: STL
        build_time: 10:58:17
      > VPP: 18.07
      > CiscoVIM: 2.3.46-17358
  > Measurement Parameters:
    NDR: 0.001
    PDR: 0.1
  > Service chain:
    > PVP:
      > Traffic:
        Profile: custom_traffic_profile
        Bidirectional: True
        Flow count: 10000
        Service chains count: 1
        Compute nodes: [u'nova:a22-mchester-micro-3']
```

The NFVBench Result Execution Summary table shows the following:

- L2 frame size
- Highest throughput achieved in bps and pps below the drop rate thresholds being the sum of TX for both ports.

- Drop rate measured
- Latency measured (average, min, max)

Table 6: NFVIBench Result Execution Summary

	L2 Frame Size	Rate (fwd+rev) in Gbps	Rate (fwd+rev) in pps	Avg Drop Rate	Avg Latency (usec)	Min Latency (usec)	Max Latency (usec)
NDR	IMIX	8.5352	2,794,136	0.0000%	124	10	245
PDR	IMIX	9.5703	3,133,012	0.0680%	167	10	259

VXLAN Fixed Rate

It is applicable for platforms that support VxLAN only

Example 1:

In this example, default frame size of 64B is sent over 1Mpps on two chains using VxLAN with flow count of 10k:

```
# nfvbench --duration 10 -scc 2 --rate 1Mpps --vxlan
```

The summary of the NFVIBench Result is shown below:

```
2018-12-20 23:28:24,715 INFO --duration 10 -scc 2 --rate 1Mpps --vxlan
2018-12-20 23:28:24,716 INFO VxLAN: vlan_tagging forced to False (inner VLAN tagging must
be disabled)
2018-12-20 23:28:24,716 INFO Using default VxLAN segmentation_id 5034 for middle internal
network
2018-12-20 23:28:24,716 INFO Using default VxLAN segmentation_id 5017 for right internal
network
2018-12-20 23:28:24,716 INFO Using default VxLAN segmentation_id 5000 for left internal
network
```

Example 2:

In this example, VxLAN benchmark is ran and 64B frames are sent over 100kpps for the default duration.

```
# nfvbench -rate 100kpps --vxlan
```

```
2018-12-18 19:25:31,056 INFO VxLAN: vlan_tagging forced to False (inner VLAN tagging must
be disabled)
2018-12-18 19:25:31,056 INFO Using default VxLAN segmentation_id 5034 for middle internal
network
2018-12-18 19:25:31,056 INFO Using default VxLAN segmentation_id 5017 for right internal
network
2018-12-18 19:25:31,056 INFO Using default VxLAN segmentation_id 5000 for left internal
network
```

The NFVIBench result summary is as follows:

```
Date: 2018-12-18 19:26:40
NFVIBench version 3.0.5.dev2
Openstack Neutron:
  vSwitch: VPP
  Encapsulation: VxLAN
```

```

Benchmarks:
> Networks:
  > Components:
    > Traffic Generator:
      Profile: trex-local
      Tool: TRex
    > Versions:
      > Traffic_Generator:
        build_date: Nov 13 2017
        version: v2.32
        built_by: hhaim
        mode: STL
        build_time: 10:58:17
      > VPP: 18.07
      > CiscoVIM: 2.3.46-17358
  > Service chain:
    > PVP:
      > Traffic:
        Profile: traffic_profile_64B
        Bidirectional: True
        Flow count: 10000
        Service chains count: 1
        Compute nodes: ['nova:a22-mchester-micro-1']

```

Table 7: NFVIBench Result Summary

L2 Frame Size	Drop Rate	Avg Latency (usec)	Min Latency (usec)	Max Latency (usec)
64	0.0000%	0	nan	0

Table 8: NFVIBench Result Configuration

Direction	Requested TX Rate (bps)	Actual TX Rate (bps)	RX Rate (bps)	Requested TX Rate (pps)	Actual TX Rate (pps)	RX Rate (pps)
Forward	33.6000 Mbps	33.6000 Mbps	33.6000 Mbps	50,000 pps	50,000 pps	50,000 pps
Reverse	33.6000 Mbps	33.6000 Mbps	33.6000 Mbps	50,000 pps	50,000 pps	50,000 pps
Total	67.2000 Mbps	67.2000 Mbps	67.2000 Mbps	100,000 pps	100,000 pps	100,000 pps

Table 9: Forward Chain Packet Counters and Latency

Chain	TRex.TX.p0	vpp.RX.veth/0	vpp.TX.veth/0	vpp.RX.veth/1	vpp.TX.veth/1	TRex.RX.p1
0	50,000	=>	=>	=>	=>	50,000

Table 10: Reverse Chain Packet Counters and Latency

Chain	TRex.TX.p1	vpp.RX.veth/1	vpp.TX.veth/1	vpp.RX.veth/0	vpp.TX.veth/0	TRex.RX.p0
0	50,000	=>	=>	=>	=>	50,000

Cisco VIM CLI

An alternate way to NFVBench CLI is to use `ciscovimclient`. `ciscovimclient` is meant to provide an interface that is more consistent with the CiscoVIM CLI and can run remotely while the NFVBench CLI is executed on the management node.

Pass JSON configuration matching structure of the NFVBench config file to start a test:

```
[root@mgmt1 ~]# ciscovim nfvbench --config '{"rate": "10kpps"}'
+-----+
| Name          | Value          |
+-----+
| status        | not_run        |
| nfvbench_request | {"rate": "5kpps"} |
| uuid          | 0f131259-d20f-420f-840d-363bdcc26eb9 |
| created_at    | 2017-06-26T18:15:24.228637 |
+-----+
```

Run the following command with the returned UUID to poll status:

```
[root@mgmt1 ~]# ciscovim nfvbench --stat 0f131259-d20f-420f-840d-363bdcc26eb9
+-----+
| Name          | Value          |
+-----+
| status        | nfvbench_running |
| nfvbench_request | {"rate": "5kpps"} |
| uuid          | 0f131259-d20f-420f-840d-363bdcc26eb9 |
| created_at    | 2017-06-26T18:15:24.228637 |
| updated_at    | 2017-06-26T18:15:32.385080 |
+-----+

+-----+
| Name          | Value          |
+-----+
| status        | nfvbench_completed |
| nfvbench_request | {"rate": "5kpps"} |
| uuid          | 0f131259-d20f-420f-840d-363bdcc26eb9 |
| created_at    | 2017-06-26T18:15:24.228637 |
| updated_at    | 2017-06-26T18:18:32.045616 |
+-----+
```

When the test is done, retrieve results in a JSON format:

```
[root@mgmt1 ~]# ciscovim nfvbench --json 0f131259-d20f-420f-840d-363bdcc26eb9
{"status": "PROCESSED", "message": {"date": "2017-06-26 11:15:37", ...}}
```

NFVBench REST Interface

When enabled, the NFVBench container can also take benchmark request from a local REST interface. Access is only local to the management node in the current Cisco VIM version (that is the REST client must run on the management node).

Details on the REST interface calls can be found in Chapter 2, Cisco VIM REST API Resources.

Enabling or Disabling Autobackup of Management Node

Cisco VIM supports the backup and recovery of the management node. By default, the feature is enabled. Auto snapshot of the management node happens during pod management operation. You can disable the auto backup of the management node.

To enable or disable the management node, update the `setup_data.yaml` file as follows:

```
# AutoBackup Configuration
# Default is True
#autobackup: <True or False>
```

Take a backup of `setupdata` file and update it manually with the configuration details by running the following command:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/
[root@mgmt1 ~]# # update the setup_data to change autobackup
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Forwarding ELK logs to External Syslog Server

Cisco VIM supports backup and recovery of the management node. To keep the process predictable and to avoid loss of logs, the software supports the capability of forwarding the ELK logs to multiple external syslog servers (Minimum 1 and Maximum 3). The capability is introduced to enable this feature after the pod is up and running, with Cisco VIM, through the reconfigure option.

The Syslog Export reconfigure option supports the following options:

- Enable forwarding of ELK logs to External Syslog Server on a pod that is already up and running.
- Reconfigure existing External Syslog Setting to point to a different syslog cluster.

The following section needs to be configured in the `setup_data.yaml` file.

```
#####
## SYSLOG EXPORT SETTINGS
#####
SYSLOG_EXPORT_SETTINGS:
-
  remote_host: <Syslog_ipv4_or_v6_addr> # requiredIP address of the remote syslog
  server protocol : udp # defaults to udp
  facility : <string> # required; possible values local[0-7]or user
  severity : <string; suggested value: debug>
  port : <int>; # defaults, port number to 514
  clients : 'ELK' # defaults and restricted to ELK;

remote_host: <Syslog_ipv4_or_v6_addr> #
  required
  protocol : udp # defaults to udp
  facility : <string> # required; possible values local[0-7]or user
  severity : <string; suggested value: debug>
  port : <int>; # defaults, port number to 514
  clients : 'ELK' # defaults and restricted to ELK;
```

Take a backup of the `setupdata` file and update the file manually with the configuration listed in the preceding section. Then run the reconfiguration command as follows:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
```

```
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/
[root@mgmt1 ~]# # update the setup_data to include Syslog Export info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

With this configuration, you should now be able to use export ELK logs to an external syslog server. On the remote host, verify if the logs are forwarded from the management node.

Adding and Reconfiguring VIM Administrators

Cisco VIM supports management of the VIM Administrators. VIM administrator has the permission to log in to the management node through SSH or the console using the configured password. By configuring to one VIM admin account, administrators do not have to share credentials. Administrators have individual accountability.

To enable one or more VIM administrators, perform the following steps:

Step 1 Take a backup of the setupdata file and update the file manually with the configurations listed as,

```
vim_admins:
- vim_admin_username: <username>
  vim_admin_password_hash: <sha512-password-hash>
- vim_admin_username: <username>
  vim_admin_password_hash: <sha512-password-hash>
- vim_admin_username: <username>
  vim_admin_password_hash: <sha512-password-hash>
```

The value of password hash must be in the standard sha512 format. # To generate the hash admin_password_hash should be the output from on the management node
python -c "import crypt; print crypt.crypt('<plaintext password>')"

Step 2 Run the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to include vim_admin info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Note Cisco VIM administrators can manage their own passwords using the Linux passwd command. You can add or remove Cisco VIM administrator through the reconfigure option, while the passwords for their existing accounts remain unchanged.

Adding Read-Only OpenStack Role

By default, Cisco VIM's deployment of OpenStack supports two roles: admin and user. The admin can view and change all OpenStack resources including system and project resources. The user can view and change only the project resources.

Cisco VIM, optionally provides OpenStack user role, which is the read-only administrator or **readonly**. The read-only user can view project resources, but cannot make any changes.

To enable read-only OpenStack role and create read-only OpenStack administrator, perform the following steps

Step 1 Take a backup of the setupdata file and update the file manually with the configuration given below:

```
ENABLE_READONLY_ROLE: True
```

Step 2 Enable the OpenStack user role, by executing the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to include vim_admin info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

When the feature is enabled, an OpenStack administrator can create new user accounts that will have the special privileges of a Read-Only user.

Step 3 From the management node, load the OpenStack authentication variables:

```
[root@management-server-cisco ~]# source ~/openstack-configs/openrc
```

Step 4 Create a new user account with a strong password.

```
[root@management-server-cisco images]# openstack user create --password-prompt reader
User Password:
Repeat User Password:
+-----+-----+
| Field  | Value |
+-----+-----+
| email  | None  |
| enabled| True  |
| id     | e2f484de1e7d4faa9c9de2446ba8c3de |
| name   | reader|
| username| reader|
+-----+-----+
```

Step 5 Assign the project and role to that user account:

```
[root@management-server-cisco images]# openstack role add --project admin --user reader
readonly
+-----+-----+
```

Field	Value
domain_id	None
id	ed2fb5b2c88e4241918573624090174b
name	readonly

Alternatively, the OpenStack admin logged into the Horizon dashboard can perform the above steps. The actions corresponding to the CLI commands can be done on the Identity/Users panel in the dashboard.

The OpenStack read-only user can:

- Access the project and identity dashboards, but not the admin dashboard.
- View all the project resources, but cannot make any changes to them.

Note If the `ENABLE_READONLY_ROLE` is `False` (the default value), the `readonly` role will have no special permissions or restrictions. It has create, update, and delete permissions to project resources, similar to that of the project member. You need to assign users to the role of `readonly`, when `ENABLE_READONLY_ROLE` is set to `True`.

Reconfiguration of Proxy Post Install

During post-install you can update the http/https proxy server information that is listed in `NETWORKING` section of the `setup_data.yaml`.

To update the proxy in the post-VIM install follow these steps:

Step 1 Take a backup of the `setupdata` file and update the file manually with the configuration listed below:

```
http_proxy_server: <a.b.c.d:port> # optional, needed if install is through internet, and the pod is
  behind a proxy
and/or
https_proxy_server: <a.b.c.d:port> # optional, needed if install is through internet, and the pod is
  behind a proxy
```

Step 2 Run the following command to reconfigure:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to update the proxy info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Reconfiguring Sever KVM Console Password Post Install

You need the reconfigure option to reset the KVM console password for the servers, if the administrator forgets the KVM console password post cloud installation. The risk of forgetting the password leads to the failure of SSH connectivity to the server and the option of debugging through KVM console.

During post-install, you can update the `admin_password_hash` information that is listed in COBBLER section of the `setup_data.yaml`.

To update the password post-install, follow the below steps:

Step 1 Take a backup of the `setupdata` file and update the file manually with the configuration listed below:

```
COBBLER:
  admin_password_hash: <$6...> # <Please generate the admin pwd hash via the command below; verify
  the output starts with $6>
  # execute the following on the management node to get the admin_password_hash
  # python -c 'import crypt; print crypt.crypt("<plaintext_strong_password>")'
```

Step 2 Run the following reconfiguration command:

```
[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to update the proxy info [root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Enabling Head-End Replication Option

For the releases Cisco VIM 2.4.9 and later, the multi-VXLAN EVPN based design optionally supports the static implementation of VXLAN technology using head-end replication (HER). HER helps leverage the VXLAN technology, regardless of the hardware or software limitation of the VXLAN feature set at the remote end of the VTEP tunnel.

With the static information defined in the `HERsetup_data`, VPP performs the head-end replication to all defined remote VTEPs and the Layer-2 Forwarding Information Base (L2FIB) MAC-IP table is populated based on flood and learn. When EVPN coexists with HER, Cisco VIM considers them as two different sets of BGP speakers each giving the information which ends up in the same etcd FIB table.

In Cisco VIM, the EVPN acts as the primary mechanism and HER as the fallback methodology. You can add or remove HER to or from an existing EVPN pod through Cisco VIM reconfigure option.

Following are the assumptions for the HER feature:

- VNIs can be allowed in the range of 1 to 65535.
- VNIs can be repeated across two or more remote POD VTEPs for HA.

- VNIs cannot be repeated for the same remote POD VTEP.
- Within the same network segment, no remote POD VTEPs IP address can be repeated.

Step 1 Ensure that multi-VXLAN feature exists in day-0 configuration of the setup_data. Add a new section called head-end-replication under the NETWORK_OPTIONS -> vxlan -> vxlan-ecn and vxlan-tenant sections.

```
NETWORK_OPTIONS:
  vxlan:
  vxlan-tenant:
  head_end_replication: # Optional and reconfigurable
    - vtep_ips: vni_id1:vni_id2, vni_id3, ... (upto as many remote POD vteps as required)

  vxlan-ecn:
  head_end_replication: # Optional and reconfigurable
    - vtep_ips: vni_id1:vni_id2, vni_id3, ... (upto as many remote POD vteps as required)
```

Update all compute nodes with vtep_ip information under the SERVERS section:

```
SERVERS:
```

```
  Compute1:
```

```
  ...
```

For head-end-replication option, define vtep_ips on all servers that act as control and compute nodes

```
# vtep_ips: {vxlan-tenant: <ip address>, vxlan-ecn: <ip address>} # These IPs must belong to the
  associated IP pool of vxlan-tenant and vxlan-ecn networks, and must match the existing
  assigned vtep_ip for EVPN as they are brought in as part of reconfiguration.
```

Step 2 To determine the respective vtep_ip on a per segment and server basis, run the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

[root@mgmt1 ~]# cd /root/installer-<x.y.z>/tools
[root@mgmt1 ~]# ./vtep_ip_server_mapping.py
# Update the setup_data to include the HER section and vtep_ip corresponding to the network segment
  for the respective servers

[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Enabling Layer BGP Adjacency Between Controllers and Peering Route Reflector

From release Cisco VIM 2.4.9 onwards, the Layer 2 or Layer 3 BGP adjacency with the peering route-reflector is supported.



Note For releases prior to Cisco VIM 2.4.9, only Layer 2 BGP adjacency is supported.

Following are the assumptions made to move a pod from a Layer 2 BGP adjacency to that of Layer 3:

- The controllers with the `bgp_speaker_addresses` peer with the route-reflector over Layer 3.
- This option is only available when vxlan is enabled as `NETWORK_OPTIONS`.
- Every vxlan segment (`vxlan-ec2` and `vxlan-tenant`) will have its own IPs.
- IPs are picked up from management subnet, but they do not belong in the management pool.
- Switching from Layer 2 to Layer 3 peering is only supported, but not vice-versa.
- Once enabled, the only way to change the `bgm_mgmt_address` is through a replace controller.

Step 1 Update all controller nodes with `bgp_mgmt_address` where the IPs reside in the management subnet, but not in the management IP pool.

- Note**
- VXLAN feature must exist in day-0 configuration of the `setup_data`.
 - One unique IP must be available per VXLAN segment.

```
SERVERS:
  Controll1:
  ...
# bgp_mgmt_address: {vxlan-tenant: <ip address>, vxlan-ec2: <ip address>} # These IPs must belong to
the
management segment, but not in the management IP pool.
```

Step 2 Run the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to include HER section and vtep_ips info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Enabling Custom Policy for VNF Manager Post Install

During the post-installation of a cloud, Cisco VIM helps to enable a VNF Manager (such as ESC) to operate and manage tenant VMs in the OpenStack cloud, with additional privileged features.

Following are the steps to enable the custom policy for VNF Manager:

Step 1 Take a backup of the setupdata file and update the file manually with the configurations listed as,

```
ENABLE_ESC_PROV: True
```

Step 2 Run the following commands to reconfigure:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/

# update the setup_data to update the proxy info
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Migrate SRIOV from 2-X520 to 2-XL710 in a VIC/NIC POD

To use this feature, ensure that both the card types are available on the SRIOV compute nodes of the pod and with one of the card type participating in SRIOV as part of installation, and then execute the following steps:

Before you begin

In Cisco VIM, you can redeploy the SRIOV ports between 2-X520 and 2-XL710, in a Cisco VIM pod where the control and data plane are running OFF Cisco VIC. This is driven through an optional parameter SRIOV_CARD_TYPE listed in the setup_data.yaml.

It is assumed that all computes participating in SRIOV has two sets of card types. Reconfiguration fails if the card type with a total of 4 ports is not available. Cisco recommends you to have two of each of the card type inserted on a per-compute basis, so that the correct network ports from the target network cards are picked by the orchestrator. However, if the SRIOV_CARD_TYPE is present during the fresh install or during add compute, the SRIOV_CARD_TYPE parameter is given preference for the target/configured card type.

You can define the SRIOV_CARD_TYPE at a per-compute level, to override the global definition. This option allows some computes to run with XL-710, while others to run with X-520 for SRIOV ports. It should be noted that computes without SRIOV can co-exist in this pod.

Step 1 Take a backup of the setupdata file and update the file manually with the configuration listed below:

```
SRIOV_CARD_TYPE: <X520 or XL710>
and/or update the hardware_info at a per compute level (see example below)
compute-xx:
  hardware_info: {SRIOV_CARD_TYPE: <XL710 or X520>}
```

Step 2 Run the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/
# update the setup_data to include the target SRIOV card type
```

```
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml
```

Augmenting Cisco VIM M4 VIC/(10/40G) NIC pods with M5-based 40G VIC/NIC Computes

From release Cisco VIM 2.4.9 onwards, the augmentation of an existing M4 VIC/NIC based pod (some computes have X520, while others have XL710 for SRIOV), with the M5-based VIC/NIC (40G) computes is supported. To use this augmentation feature, you must define the SRIOV_CARD_TYPE at a per compute level (default is X520).

You can add M5-based 40G VIC/NIC computes into the pod in the following scenarios:

Use Case 1: If you run a pod with M4-based computes having only X520 cards, execute the reconfiguration operation and define the SRIOV_CARD_TYPE as XL710 under the hardware_info section of the target compute, to add the compute of M5 with 40G Cisco VIC and two XL710 cards,.

Use Case 2: If you run the pod with M4-based VIC/NIC computes having XL710 cards, execute the add compute operation and define the SRIOV_CARD_TYPE as XL710 for the target compute, to add M5-based compute nodes with XL710 cards.



Note The following steps 1 through 3 are not applicable for Use Case 2, and you can directly add/remove compute when required.

Before you begin

Identify if the pod has M4 computes running with two XL710 or not, that is, whether the pod is running with **Use Case 1** or **Use Case 2**.

Step 1 If the pod is running with **Use Case 1**, execute the following command:

```
# ciscovim reconfigure
```

Step 2 Take a backup of the setupdata file and update the file manually with the configuration listed below:

```
Update the hardware_info at a per compute level (see example below)
compute-xx:
hardware_info: {SRIOV_CARD_TYPE: <XL710 or X520>}
```

Step 3 Run the following reconfiguration commands:

```
[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/ # update the setup_data to
include the target SRIOV card type [root@mgmt1 ~]# cd /root/MyDir/
```

```
[root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim --setupfile /root/MyDir/setup_data.yaml add-computes <m5compute1, ...>
```

Updating Containers in a Running Cisco VIM Cloud

Cisco VIM allows you to update all OpenStack and infrastructure services such as RabbitMQ, MariaDB, HAProxy, and management node containers such as Cobbler, ELK, VMTP and repo containers with almost no impact to the Cisco NFVI implementation. Updates allows you to integrate Cisco VIM patch releases without redeploying the Cisco NFVI stack from the beginning. Updates have minimal service impact because they run serially component by component one node at a time. If an error occurs during an update, auto-rollback is triggered to return the cloud to its pre-update state. After an update you can check for any functional impacts on the cloud. If everything is fine you can commit the update, which deletes the old containers and old images from the nodes. Should you see any functional cloud impact you can perform a manual rollback to start the old containers again.

Before you begin a container update, keep the following in mind:

- Updates are not supported for registry-related containers and `authorized_keys`.
- You cannot roll back the repo containers on the management node to an older version after they are updated because rollbacks will delete node packages and might cause the cloud to destabilize.
- To prevent double-faults, a cloud sanity check is performed before the update is started. A cloud sanity check is performed as the last step of the update.

The following table provides an overview to the methods to start the OpenStack update using Cisco VIM. The Internet options refer to management node connectivity to the Internet. If your management server lacks Internet access, you must have a staging server with Internet access to download the Cisco VIM installation artifacts to a USB drive. Ensure that you select one method and stay with it for the full pod lifecycle.

Table 11: OpenStack Update Options

	Without Cisco VIM Unified Management	With Cisco VIM Unified Management
Without Internet	<ul style="list-style-type: none"> • Prepare the USB on a staging server • Plug the USB into the management node. • Follow the update steps in the update without Internet procedure. 	<ul style="list-style-type: none"> • Prepare the USB on a staging server • Plug the USB into the management node. • Follow the update steps in the update without Internet procedure.
With Internet	<ul style="list-style-type: none"> • Download the .tgz file from the registry. • Follow the update steps in the update with Internet procedure. 	<ul style="list-style-type: none"> • Download the .tgz file from the registry. • Follow the update steps in the update with Internet procedure.

Updating Cisco VIM Software Using USB

The following procedure describes you how to load the Cisco VIM installation files onto a Cisco NFVI management node that does not have Internet access. Installation files include: buildnode-K9.iso, mercury-installer.tar.gz, nova-libvirt.tar, registry-2.3.1.tar.gz, and respective checksums.

Before you begin

This procedure requires a CentOS 7 staging server (VM, laptop, or UCS server) with a 64 GB USB 2.0 stick. You can save the VIM installation files on a USB stick and then use the USB stick to load the installation files onto the management node. The installation files are around 24 GB in size, downloading them to the USB stick might take several hours, depending on the speed of your Internet connection, so plan accordingly. Before you begin, disable the CentOS sleep mode.

Step 1 On the staging server, use yum to install the following packages:

- PyYAML (yum install PyYAML)
- python-requests (yum install python-requests)

Step 2 Connect to the Cisco VIM software download site using a web browser and login credentials provided by your account representative and download the **getartifacts.py** script from the external registry.

```
# download the new getartifacts.py file (see example below)
curl -o getartifacts.py -u '<username>:<password>'
https://cvim-registry.com/mercury-releases/cvim24-rhel7-osp10/releases/<2.4.0>/getartifacts.py

curl -o getartifacts.py-checksum.txt -u '<username>:<password>'
https://cvim-registry.com/mercury-releases/cvim24-rhel7-osp10/releases/<2.4.0>/getartifacts.py-checksum.txt

# calculate the checksum and verify that with one in getartifacts.py-checksum.txt
sha512sum getartifacts.py

# Change the permission of getartificats.py
chmod +x getartifacts.py
```

Step 3 Run the **getartifacts.py** script. The script formats the USB 2.0 stick and downloads the installation artifacts. Provide the registry username and password, the tag ID, and the USB partition on the staging server. For example:

Run the getartifacts.py script. The script formats the USB 2.0 stick and downloads the installation artifacts. You will need to provide the registry username and password, the tag ID, and the USB partition on the staging server. For example: To identify the USB drive, execute the lsblk command before and after inserting the USB stick. (The command displays a list of available block devices.) The output delta will help find the USB drive location. Provide the entire drive path in the `-d` option, instead of any partition.

```
sudo ./ getartifacts.py -t <tag_id> -u <username> -p <password> -d </dev/sdc>
```

Note Do not remove the USB stick while the synchronization is going on.

Step 4 Verify the integrity of the downloaded artifacts and the container images:

```
# create a directory
sudo mkdir -p /mnt/Cisco

# /dev/sdc is the USB drive, same as supplied in get artifacts.py python script
```

```

sudo mount /dev/sdc1 /mnt/Cisco
cd /mnt/Cisco

# execute the verification script
./test-usb

# failures will be explicitly displayed on screen, sample success output below
# sample output of ./test-usb execution with 2.4.x release [root@mgmtnode Cisco]# ./test-usb
INFO: Checking the integrity of this USB stick
INFO: Checking artifact buildnode-K9-13401.iso
INFO: Checking artifact registry-2.6.2-13401.tar.gz
INFO: Checking required layers:
INFO: 605 layer files passed checksum.
[root@mgmtnode Cisco]#

```

Step 5 To resolve download artifact failures, unmount the USB and run the `getartifacts` command again with the `--retry` option:

```
sudo ./getartifacts.py -t <tag_id> -u <username> -p <password> -d </dev/sdc> --retry
```

Step 6 Mount the USB and then run the `test-usb` command to validate all the files are downloaded:

```

# /dev/sdc is the USB drive, same as supplied in get artifacts.py python script
sudo mount /dev/sda1 /mnt/Cisco
cd /mnt/Cisco

# execute the verification script
./test-usb

# In case of failures the out of the above command is explicitly displayed the same on the screen

```

Step 7 After the synchronization finishes, unmount the USB stick:

```
sudo umount /mnt/Cisco
```

Step 8 After the synchronization finishes, remove the USB stick from the staging server then insert it into the management node.

Step 9 Complete the following steps to import the Cisco NFVI installation artifacts onto the management node:

a) Identify the USB on the management node:

```
blkid -L Cisco-VIM
```

b) Mount the USB device on the management node:

```

mount < /dev/sdc > /mnt/
mkdir /root/cvim-update-media
cd /root/cvim-update-media

```

c) Extract the `import_artifacts.py` script:

```
tar --no-same-owner -xvzf /mnt/Cisco/mercury-installer.tar.gz
```

d) Unmount the USB device:

```
umount /mnt/Cisco/
```

e) Import the artifacts:

```

cd /root/cvim-update-media/installer-<2.4.x>/tools/
./import_artifacts.sh

```

f) Change directory and remove `/root/cvim-update-media`

```
cd /root/
rm -fr /root/cvim-update-media
```

Step 10 Execute the update from the old working directory:

```
cd $old_workspace/installer;
ciscovim update --file /var/cisco/artifacts/mercury-installer.tar.gz
```

After the update is complete, use the newly created directory from here onwards (unless a rollback is planned).

Step 11 Commit the update by running the following command:

```
ciscovim commit # from the new workspace
```

Step 12 To revert the update changes before entering the commit command, enter:

```
ciscovim rollback # and then use older workspace
```

Note Do not run any other Cisco VIM actions while the update is in progress.

In Cisco VIM, if updates bring in Kernel changes, then the reboot of the compute node with VNFs in ACTIVE state is postponed. This is done to mitigate the unpredictability of data plane outage when compute nodes go for a reboot for the kernel changes to take effect, during the rolling upgrade process.

At the end of ciscovim update, the Cisco VIM orchestrator displays the following message on the console and logs:

```
Compute nodes require reboot Kernel updated
<compute_1_with_VM_running>
<compute_3_with_VM_running>
<compute_4_with_VM_running>
<compute_12_with_VM_running>
```

After the Kernel update on Management node, reboot the compute node before proceeding. The logs for this run are available in <mgmt._ip_address>:/var/log/mercury/<UUID>

Note As the redundancy in controller and storage nodes are built into the product, the reboot of those nodes are automatic during the software update. Also, computes that does not have any VNFs in ACTIVE state, gets automatically rebooted during software update. To monitor and reboot the compute nodes through ciscovim cli, refer to the sections titled “Managing Reboot of Cisco VIM Nodes: and “Managing Reboot Status of Cisco VIM Nodes”, in the later part of this guide. It should be noted no pod management operation is allowed till reboot of all Cisco VIM nodes are successful.

Updating Cisco VIM Software Using Network Installation

Step 1 From the download site that is provided by your Cisco account representative, download the mercury-installer.gz

```
curl -o mercury-installer.tar.gz
https://{username}:{password}@cvim-registry.com/
mercury-releases/mercury-rhel7-osp10/releases/{release number}/
mercury-installer.tar.gz
```

The link to the tar ball preceding is an example.

Step 2 Execute the update from the old working directory:

Note Do not run any other Cisco VIM actions while the update is in progress.

```
cd /root/installer-<tagid>
ciscovim update --file /root/mercury-installer.tar.gz
```

After the update is complete, use the newly created directory from here onwards (unless a rollback is planned).

Step 3 Commit the update by running the following command:

```
ciscovim commit
```

Step 4 To revert the update changes before entering the commit command, enter:

```
ciscovim rollback # and then use older workspace
```

In Cisco VIM, if updates bring in Kernel changes, then the reboot of the compute node with VNFs in ACTIVE state is postponed. This is done to mitigate the unpredictability of data plane outage when compute nodes go for a reboot for the kernel changes to take effect, during the rolling upgrade process.

At the end of ciscovim update, the Cisco VIM orchestrator displays the following message on the console and logs:

```
Compute nodes require reboot Kernel updated
<compute_1_with_VM_running>
<compute_3_with_VM_running>
<compute_4_with_VM_running>
<compute_12_with_VM_running>
```

After the Kernel update on the Management node, reboot the compute node before proceeding

The logs for this run are available in <mgmt_ip_address>:/var/log/mercury/<UUID>

Note The redundancy in controller, and storage nodes are built into the product, the reboot of those nodes are automatic during the software update. Also, computes that does not have any VNFs in ACTIVE state, gets automatically rebooted during the software update. To monitor and reboot the compute nodes through ciscovim cli, refer to the sections titled “Managing Reboot of Cisco VIM Nodes: and “Managing Reboot Status of Cisco VIM Nodes”, in the later part of this guide. It should be noted no pod management operation is allowed till reboot of all Cisco VIM nodes are successful.

Upgrading Containers in a Running Cisco VIM Cloud

Cisco VIM allows you to upgrade all OpenStack services, infrastructure services such as RabbitMQ, MariaDB, HAProxy, and management node containers such as Cobbler, ELK, VMTP and repo containers. You can upgrade to new releases of OpenStack without redeploying the Cisco NFVI stack from the beginning. During upgrade, you can expect limited service impact as the upgrade is run serially on component by component (one node at a time).

Cisco VIM supports upgrade from a known version of VIM running Cisco VIM 2.2.24 to the current version of Cisco VIM.

As part of the Cisco VIM cloud upgrade:

- The runner.py script is used to automatically upgrade the REST API server managing the VIM orchestrator.

- The `setup_data.yaml` file is automatically translated, so that, the `setup_data.yaml` file is compatible to the target release version.

Before you begin a container update, consider the following:

- Plan for the downtime, as the upgrade involves moving the Kernel version.
- Updates are not supported for registry-related containers and `authorized_keys`.
- Perform a cloud sanity check before initiating the update, to prevent double-faults. A cloud sanity check is performed as the last step of the update.
- Update the CIMC of all the servers to 2.0(13n).

Before you begin a pod upgrade, consider the following:

- No option is available to roll-back after the upgrade. Cisco recommends you to stage the upgrade in the lab and test it to identify and rectify any customer environment specific issues that might occur.
- The `vim_upgrade_orchestrator.py` script for upgrade is available as part of the 2.4.5 artifacts. You have to save a copy of the upgrade script to the `/root/` location before upgrade.
- For disconnected upgrade, one USBs 2.0 (64GB) must be pre-populated with artifacts from 2.4.5.
- Upgrade from 2.2.24 to 2.4.5 is restricted to specific start and end point.
- Upgrade of the cloud is supported in both connected and disconnected mode.
- Upgrade of Unified Management from 2.2.24 to 2.4.5 is not supported. After upgrade, you have to bring up the Unified Management service on its own and register the pod to it.
- Cisco recommends you to not change the install mode during upgrade.
- Upgrade is a one-way operation, there is no rollback option. Hence, planning must be done before upgrade. If you face any issue after upgrade, reach out to Cisco TAC or BU to recover the cloud.

At a high level, the `vim_upgrade_orchestrator.py` script is broken into two logical steps to abort on failure. In case of failure, reach out to Cisco support for recovery. We do not recommend you to recover the cloud on your own.

The following are the two high level steps into which the `vim_upgrade_orchestrator.py` script is broken into:

- **Pre-upgrade Check**

- Registry connectivity (if connected, installation is initiated)
- Setup_data pre check: No UCSM_PLUGIN, sufficient storage pool size
- Backup the `setup_data.yaml` file, before translation
- Check and update `INSTALL_MODE` in the `setup_data.yaml` file (connected or disconnected)
- run cloud sanity on cloud from 2.2.24 workspace
- Check for reachability to all nodes including compute, controller, and storage

- **Upgrade to 2.4.5**

- Upgrade to 2.4.5

- Backup the management node
 - Run sanity test on cloud from 2.4.5
 - Check for reachability to all nodes (compute, controller, and storage)
- Connect to the CIMC of the management node and validate if the boot-order list has SDCARD as the first choice.
 - Power-cycle the management node to complete the management node upgrade.

The following table provides an overview of upgrade methods available to update OpenStack using Cisco VIM. The Internet options refer to management node connectivity to the Internet. If your management server lacks Internet access, you must have a staging server with Internet access to download the Cisco VIM installation artifacts to a USB drive. Ensure that you to select one method and stay with it for the full pod lifecycle.

Upgrade Method	Without Cisco VIM Unified Management
Without Internet	<ul style="list-style-type: none"> • Prepare 2 USB 2.0 (64G) on a staging server and populate them with 2.4.5 artifacts. • Plug both the USB into the management node. • Copy the <code>vim_upgrade_orchestrator.py</code> script and follow the upgrade steps in the <i>Upgrade without Internet</i> procedure.
With Internet	Copy the <code>vim_upgrade_orchestrator.py</code> script and follow the upgrade steps in the <i>Upgrade with Internet</i> procedure.



Note The upgrade of VTS from 2.2.24 to 2.4.5 is not supported. The VTS upgrade support will only be available when VTS 2.6.2 is integrated with Cisco VIM, so that the multi-step upgrade of VTS works. For pods running with VPP, after upgrade, ensure that the switch ports connected to the data plane ports on the server are running in LACP mode.

Prerequisites and Assumptions for VIM Update

During Cisco VIM update, ensure that no interference exists with external monitoring services.

To handle the potential of docker corruption post repo/kernel update, you must follow the below steps during VIM update irrespective of the update methodology (connected or disconnected).

- You must disable NRVIMON monitoring for all server CIMC, only if NRVIMON/Zenoss is used. This prevents the failure of VIM update when Cisco VIM is deprived of CIMC login with valid credentials. Once Cisco VIM software update/commit or any other POD management operation is completed, you can re-enable Zenoss monitoring.
- If ACI fabric is integrated with NFVI, you must disable switch policy enforcement that can shutdown the ToR ports to which the NFVI server interfaces are connected, during software update. This is required

as MAC-moves for floating IP addresses happen during software update with L3 agent failover due to host package update and/or L3 agent container update. Multiple L3 agent failover can result in several Mac-Moves in a short period of time. Fast Mac-moves over a five-minute duration can potentially trigger N9K/ACI Mac-move policy violation, thereby causing an immediate shutdown of the server switchport.

- While updating Cisco VIM software to a version later than 2.4.12, an update of the repository results in a potential docker corruption issue post reboot of compute node. Hence, ensure that you enable the flag DEFER_REPO_UPDATE in setup_data.yaml. To enable the flag, enter the following commands:

```
# check if DEFER_REPO_UPDATE is enabled in setup_data.yaml configuration
grep DEFER_REPO_UPDATE: /root/openstack-configs/setup_data.yaml
grep DEFER_REPO_UPDATE: /root/openstack-configs/.backup_setup_data.yaml
# if not enabled, then add as follows:
echo "DEFER_REPO_UPDATE: True" >> /root/openstack-configs/setup_data.yaml
echo "DEFER_REPO_UPDATE: True" >> /root/openstack-configs/.backup_setup_data.yaml
```

Upgrading VIM Software Using a USB

The following procedure describes how to load the Cisco VIM installation files onto a Cisco NFVI management node that does not have Internet access. Installation files include: buildnode-K9.iso, mercury-installer.tar.gz, nova-libvirt.tar, registry-2.3.1.tar.gz, and respective checksums.

Before you begin

This procedure requires a CentOS 7 staging server (VM, laptop, or UCS server) with a 64 GB USB 2.0 stick. You can download the VIM installation files using the staging server with Internet access (wired access is recommended), and save the files to a USB stick. You can use the USB stick to load the installation files onto the management node. The size of the installation files comes to around 24 GB, so downloading them to the USB stick might take several hours, depending on the speed of your Internet connection, so plan accordingly. Before you begin, disable the CentOS sleep mode.

Step 1 On the staging server, use yum to install the following packages:

- PyYAML (yum install PyYAML)
- python-requests (yum install python-requests)

Step 2 Connect to the Cisco VIM software download site using a web browser and login credentials provided by Cisco account representative and download the **getartifacts.py** script from the external registry.

```
# download the new getartifacts.py file (see example below)
curl -o getartifacts.py -u '<username>:<password>'
https://cvm-registry.com/mercury-releases/cvim24-rhel7-osp10/releases/2.4.1/getartifacts.py

curl -o getartifacts.py-checksum.txt -u '<username>:<password>'
https://cvm-registry.com/mercury-releases/cvim24-rhel7-osp10/releases/2.4.1/getartifacts.py-checksum.txt

# calculate the checksum and verify that with one in getartifacts.py-checksum.txt sha512sum
getartifacts.py

# Change the permission of getartificats.py
chmod +x getartifacts.py
```

Step 3 Run the **getartifacts.py** script. The script formats the USB 2.0 stick and downloads the installation artifacts. Provide the registry username and password, the tag ID, and the USB partition on the staging server.

For example, to identify the USB drive, execute the **lsblk** command before and after inserting the USB stick. (The command displays a list of available block devices.) You can find the USB drive location from the delta output, and provide the entire drive path in the **-d** option instead of any partition.

```
sudo ./getartifacts.py -t <tag_id> -u <username> -p <password> -d </dev/sdc>
```

Note Do not remove the USB stick during synchronization.

Step 4 Verify the integrity of the downloaded artifacts and the container images.

```
# create a directory
sudo mkdir -p /mnt/Cisco
# /dev/sdc is the USB drive, same as supplied in get artifacts.py python script
sudo mount /dev/sdc1 /mnt/Cisco
cd /mnt/Cisco
# execute the verification script
./test-usb

# failures will be explicitly displayed on screen. A sample success output is shown
# sample output of ./test-usb execution with 2.4.x release

[root@mgmtnode Cisco]# ./test-usb
INFO: Checking the integrity of this USB stick
INFO: Checking artifact buildnode-K9-13401.iso
INFO: Checking artifact registry-2.6.2-13401.tar.gz
INFO: Checking required layers:
INFO: 605 layer files passed checksum.
[root@mgmtnode Cisco]#
```

Step 5 To resolve download artifact failures, unmount the USB and run the **getartifacts** command again with the **--retry** option.

```
sudo ./getartifacts.py -t <tag_id> -u <username> -p <password> -d </dev/sdc> --retry
```

Step 6 Mount the USB and run the **test-usb** command to validate if all the files are downloaded.

```
# /dev/sdc is the USB drive, same as supplied in get artifacts.py python script
sudo mount /dev/sdc1 /mnt/Cisco
cd /mnt/Cisco

# execute the verification script
./test-usb

# In case of failures, the output of the above command will explicitly display the failure on the
screen
```

Step 7 After synchronization, unmount the USB stick.

```
sudo umount /mnt/Cisco
```

Step 8 After synchronization, remove the USB stick from the staging server and insert the USB stick into the management node.

Step 9 Insert the pre-populated USBs into the management node of the pod running 2.2.24.

Step 10 Copy the **vim_upgrade_orchestrator.py** script available in CVIM 2.4 artifacts in the **/root/** folder, to the management node of the pod running 2.2.24.

Step 11 Execute the update from the **/root/** location:

```
# cd /root/
# ./vim_upgrade_orchestrator.py -i disconnected [-y] # -y if you don't want any interactive mode
```

After upgrade, start using the newly created directory.

Note Upgrade process takes several hours (> 6 hours), so execute this process in a VNC. Do not run any other Cisco VIM actions during upgrade.

- Step 12** Copy the management node backup created during the upgrade, and paste it into a separate server through rsync (for more information, see [Managing Backup and Restore Operations, on page 351](#)).
- Step 13** Check if the SDCARD is stated as priority 1 in the boot order, from the CIMC of the management node. If not, set it accordingly. Reboot the management node, and wait for it to up.

Upgrading Cisco VIM Software Using Network Installation

- Step 1** From the software download site provided by your Cisco account representative, download the `vim_upgrade_orchestrator.py` `curl -o vim_upgrade_orchestrator.py` file.

For example:

```
https://{username}:{password}@cvim-registry.com/mercury-releases/mercury-rhel7-osp10/releases/{release
number}/vim_upgrade_orchestrator.py
```

- Step 2** Execute the upgrade from the `/root/` directory:

```
$ cd /root/
$ ./vim_upgrade_orchestrator.py -i connected
```

Note During the upgrade process, do not run any other Cisco VIM actions.

After the upgrade, use the newly created folder.

Common Tasks Post Cisco VIM Update

Cisco VIM allows you to upgrade all OpenStack services, infrastructure services such as RabbitMQ, MariaDB, and HAProxy, and management node containers such as Cobbler, ELK, VMTP, and repo containers. You can upgrade to new releases of OpenStack without redeploying the Cisco NFVI stack from the beginning. During upgrade, you can expect limited service impact as the upgrade is run serially on component by component (one node at a time).

- Step 1** Update `httpd` on the management node, only when no other Cisco VIM operations like POD management operation and reconfiguration are in progress on the management node.

```
cd /root/installer-2.4.x/tools/
./update_httpd.sh
```

- Step 2** Update the host packages and reboot the computes with active VMs. When an update is performed from 2.4.x where $x \leq 10$ to a version later than 2.4.10, host kernel also gets updated. To get to the new kernel, servers with active VNFs

must undergo repo-swap and reboot. A standalone option is provided for the kernel update via repo swap. As the compute nodes undergo re-boot, the maintenance downtime for VNFs must be planned for this activity.

- a) Identify the servers that need to undergo both kernel update via repo swap, by executing the below command:

```
# cat /root/openstack-configs/compute_nodes_vms
```

- b) Identify the servers that require repo update and the VM that will undergo an outage, by executing the following command:

```
source /root/openstack-configs/openrc
openstack server list --all-projects --host <compute-hostname>
# example below
openstack server list --all-projects --host PNQVFICEPH02
openstack server list --all-projects --host PNQVFICEPH02 --host PNQVFICEPH03 --host PNQVFICTRL03
```

- c) Plan for VM outage schedule and execute the following commands:

```
# Starting 2.4.16 release, the swap_repo_post_update.py script is in tools dir
# to /root/installer-2.4.16/tools/ directory on the management node
cd /root/installer-2.4.16/tools
python swap_repo_post_update.py -h
python swap_repo_post_update.py --target_node_reboot "comma separated hosts" -y
```

For e.g.

```
python swap_repo_post_update.py --target_node_reboot "PNQVFISPGW03,PNQVFIPCRF02,PNQVFICGDN01"
```

Repeat this step to cover all the compute nodes listed in file /root/openstack-configs/compute_nodes_vms

- Step 3** Take the manual backup of management node post successful upgrade and nodes reboot. Then, copy the backup to a remote server before proceeding further:

```
# don't supply trailing slash in the local directory
rsync -e ssh -go -rtvpX --numeric-ids /var/cisco/<autobackup_dir>
username@remote-server:/path/to/backup-dir/
also, note down the following from management node (for restore, may need with re-image of management
node with ISO):
# Management node hostname
hostname
# br_api address and subnet mask
ip addr show br_api
# br_api/default gateway
ip route
# br_mgmt IP address
ip addr show br_mgmt
# DNS servers
grep nameserver /etc/resolv.conf
# Timezone to be configured
ls -l /etc/localtime
date
# Server root password
```

- Step 4** Reboot the management node, only after the successful completion of CiscoVIM software update with rollback or commit operation. Validate the boot order on the management node CIMC to have localhdd as topmost.

```
# reboot the management node
shutdown -r now
```

- Step 5** Execute cloud-sanity and cloudpulse test for verification, only after successful CiscoVIM software update/commit/rollback completion.

Note Ensure that no other Cisco VIM actions are running prior to execution of the above step.

```
cd ~/installer-2.4.y/tools/
# note down the ID for submitted cloud-sanity request to view results
ciscovim cloud-sanity create test all
ciscovim cloud-sanity list test all
ciscovim cloud-sanity show test all --id <UUID>
# execute cloudpulse test and ensure no failures
cloudpulse run --name all_operator_tests
cloudpulse run --name all_endpoint_tests
# check the cloudpulse result
cloudpulse result
# check details result for specific test based on name or UUID
cloudpulse show all_operator_tests
cloudpulse show all_endpoint_tests
```

Note Ensure that these steps must pass and reports no failure.

Migrating Server Configuration from Bonding to Teaming on Post-Upgrade

From the release Cisco VIM 2.4.2 onwards, the teaming driver is used as the default configuration for link aggregation support where Cisco Nexus N9K acts as ToR.

For the systems running Cisco VIM 2.2.24, the bonding driver is the default configuration for link aggregation support where Cisco Nexus N9K acts as ToR. A standalone option is provided so that the link aggregation support can be migrated from bonding to teaming driver seamlessly.



Note The nodes are re-booted as part of this migration and hence maintenance downtime should be planned for this activity.

To migrate server configuration to teaming driver across the pod, post 2.4.2 upgrade, execute the following command from the upgraded management node during the maintenance window.

```
# cd /root/
# ./vim_upgrade_orchestrator.py -i connected -bond2team
```

When the interfaces of all the nodes are switched from bonding to teaming serially, the nodes are internally rebooted for the changes to take effect. You have no control of when the node will get rebooted to move the VNFs around for avoiding data plane outage. To alleviate unpredictable data plane outage, the command has been extended to support the migration of bonding to teaming configuration on a per node basis. You can plan the migration to the teaming configuration for each node by moving the VNFs around other computes accordingly.

To initiate the migration of bonding to teaming on a per node basis, execute the following command:

```
# cd /root/
# ./vim_upgrade_orchestrator.py -bond2team <"one or more , separated target nodes"> -i
connected
```

The targeted nodes are automatically rebooted and a file named `bond_2_teaming_node_info.txt` in the `/root/openstack-configs/` directory is updated to keep track of the nodes where the migration from bonding to teaming has been done.



Note Reboot the management node to migrate the rest of the pod to use teaming driver, once the script is executed.

Supporting RMA of ToRs with Auto-ToR Configuration

When Cisco VIM cloud uses auto-ToR configuration to manage switch ports, you need to replace the existing switches if one malfunctions.

Consider the following assumptions made during RMA of ToR with auto-ToR configuration:

- When a switch is getting RMAed, it is in a virtual port-channel (vPC) mode with another switch to support full switch redundancy.
- You can replace multiple switches through Cisco VIM CLI, but only one switch from each pair.
- Administrator is responsible for manual configuration of the spine connection and L3 Out for the ToR.



Note When replacing the ToR, ensure that you use same server ports to have minimal changes in the `setup_data`.

To initiate ToR RMA, take a backup of the `setupdata` file and update it manually with the configuration details by running the following command:

```
[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml /root/MyDir/ [root@mgmt1 ~]# #
update the setup_data to include
    the changes associated to the ToR that needs to be RMAs
[root@mgmt1 ~]# cd /root/MyDir/
[root@mgmt1 ~]# vi setup_data.yaml [root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile /root/MyDir/setup_data.yaml -rma_tors
<"," separated target ToRs>
```

VM Resizing

VM resize is the process of changing the flavor of an existing VM. Thus, using VM resize you can upscale a VM according to your needs. The size of a VM is indicated by the flavor based on which the VM is launched.

Resizing an instance means using a different flavor for the instance.

By default, the resizing process creates the newly sized instance on a new node, if more than one compute node exists and the resources are available. By default, the software, allows you to change the RAM size, VDISK size, or VCPU count of an OpenStack instance using **nova resize**. Simultaneous or individual adjustment of properties for the target VM is allowed. If there is no suitable flavor for the new properties of the VM, you can create a new one.

```
nova resize [--poll] <server> <flavor>
```

The resize process takes some time as the VM boots up with the new specifications. For example, the Deploying a Cisco CSR (size in MB) would take approximately 60mins. After the resize process, execute `nova resize-confirm <server>` to overwrite the old VM image with the new one. If you face any issue, you can revert to the old VM using the `nova-resize-revert <server>` command. At this point, you can access the VM through SSH and verify the correct image is configured.



Note The OpenStack **shutdown** the VM before the resize, so you have to plan for a **downtime**.



Note We recommend you not to resize a vdisk to a smaller value, as there is the risk of losing data.

Nova Migrate

The `nova migrate` command is used to move an instance from one compute host to another compute host. The scheduler chooses the destination compute host based on the availability of the zone settings. This process does not assume that the instance has shared storage available on the target host.

To initiate the cold migration of the VM, you can execute the following command:

```
nova migrate [--poll] <server>
```

The VM migration can take a while, as the VM boots up with the new specifications. After the VM migration process, you can execute `nova resize-confirm <server> --to` to overwrite the old VM image with the new one. If you encounter a problem, use the `nova-resize-revert <server>` command to revert to the old VM image. At this point, access the VM through SSH and verify the correct image is configured.



Note The OpenStack **shutdown** the VM before the migrate, so plan for a **downtime**.

Live Migrate

Live-migrating an instance means moving its virtual machine to a different OpenStack Compute server while the instance continues running. The operator can select which host to live migrate the instance. If the destination host is not selected, the nova scheduler chooses the destination compute based on the availability of the zone settings. Live migration cannot be used without shared storage except a booted from volume VM which does not have a local disk.

To initiate the live migration of the VM, you can execute the following command:

```
openstack server migrate <server>--live
```

The VM migration can take a while. The virtual machine status can be checked with the command:

```
openstack server show < server>
```



- Note**
1. With NFV_HOST enabled, you must ensure that the vCPUs are available on the destination host to avoid collision. With cold migration, the vCPUs available on the destination host are automatically selected and assigned to the VM.
 2. If you are trying to live-migrate a VM with config-drive, it is always considered as cold-migration.
 3. In VPP pod, live-migration is not supported as it uses huge pages by default.

Power Management Of Computes (for C-Series)

Before you begin

In Cisco VIM 2.4, the power management function of computes optimizes the overall power consumption of the data center. Powering down the server through an API/CLI helps you to have a power backup.

Step 1 To power off one or more compute nodes, run the following commands:

```
Run ciscovim power-off help command
# ciscovim help power-off
usage: ciscovim power-off --setupfile SETUPFILE [-y] <node1,node2,...>

Power Off compute-nodes

Positional arguments:
  <node1,node2,...>      Power off Compute Nodes

Optional arguments:
  --setupfile SETUPFILE <setupdata_file>. Mandatory for any POD management
                        operation.
  -y, --yes              Yes option to perform the action
```

Step 2 To list all the nodes in the Openstack Cloud run the following command:

```
# ciscovim list-nodes
```

Step 3 Choose one or more *Active* compute node to be powered off

Step 4 Run the following command:

```
# ciscovim power-off <compute-server-1, compute-server-2, ... > --setupfile <path_setup_data.yaml>
```

Step 5 Run the following command to verify that the computes are power off

```
# ciscovim list-nodes
```

Note The Status for compute nodes that are powered off has to be *InActive* state.

Note To prevent cloud destabilization, you must ensure that at least one compute node is in the Active state. Pod management operation that applies to the entire pod (such as a update, reconfigure, and so on) cannot be performed if one or more compute nodes are powered off. Computes which run VMs or which provide other roles (such as All-in-one (AIO) nodes in a micropod) cannot be powered-off using this API. Power error-handling methods are added to ensure that such cases are handled. As part of the power-off action, internally cloud-sanity is run and if the cloud sanity fails, then the power-off action is aborted.

Power On Compute Nodes

Following are the steps to power on the compute nodes:

Step 1 Run the following command to power on one or more compute nodes

```
Run ciscovim power-on help command
# ciscovim help power-on
usage: ciscovim power-on --setupfile SETUPFILE [-y] <node1,node2,...>

Power On compute-nodes

Positional arguments:
  <node1,node2,...>      Power on Compute Nodes

Optional arguments:
  --setupfile SETUPFILE <setupdata_file>. Mandatory for any POD management
                        operation.
  -y, --yes              Yes option to perform the action
```

Step 2 To list all the nodes in the Openstack Cloud:

```
# ciscovim list-nodes
```

Step 3 Choose one or more Active compute node to be powered on

Step 4 Run the following command:

```
# ciscovim power-on <compute-server-1, compute-server-2, ... > --setupfile <path_setup_data.yaml>
```

Step 5 Run the following command to verify the compute(s) are powered on

```
# ciscovim list-nodes
```

Note The Status for compute nodes that were powered on has to be *Active*

Managing Reboot of Cisco VIM Nodes

Cisco VIM 2.4 has a ciscovim CLI to reboot the Cisco VIM nodes. CLI can be used for rebooting the Cisco VIM nodes in general. During software update, core libraries like kernel, glibc, systemd and so on. require rebooting the system to run the latest version. Cisco VIM has the functionality to reboot nodes (if needed) during an update, but we defer the update of compute nodes which are running application VM's.

Reboot the nodes using the CLI before migrating the VM's on another computes as shown in the following steps:

Step 1 Run the following command to Reboot one or more compute nodes:

```
Run ciscovim reboot help command
# ciscovim help reboot
usage: ciscovim reboot [-y] <node1,node2,...>

Reboot compute-nodes

Positional arguments:
  <node1,node2,...>  Reboot Compute Nodes

Optional arguments:
  -y, --yes          Yes option to perform the action
```

Step 2 Run the following command to select one or more compute nodes

```
# ciscovim reboot<compute-server-1, compute-server-2, ... >
```

Note You cannot reboot all the compute nodes simultaneously. At least one node has to be Active to prevent the cloud destabilization. Also, computes on which VMs are running cannot be rebooted, the CLI prevents it (see the following steps on mitigation). The nodes which are associated with multiple roles (For Example: All-in-one (AIO) nodes in a micro-pod or Hyper-converged) can be rebooted one at a time.

Cisco VIM Client Reboot and Remove Compute Using Force Option

When VM's are running on a particular compute node, the operator is not allowed to reboot or remove that compute node. Cisco VIM installer internally checks for the presence of VM's and aborts the operation if VM is running on the target compute node.



Note If *Remove-Compute* failed then next operation only "Remove-Compute" will be allowed to perform. So first user has to check whether any VMs are running on those Computes.

To execute remove-compute operation without any failure, migrate or terminate VMs running on compute nodes and execute remove or reboot operations using "-f/--force" option in Cisco VIM client.

Note the following before executing reboot or remove compute operations with force option.

- If a remove compute operation is executed with force option, the VMs running on that compute node are deleted.
- If a reboot compute operation is executed with force option, the VMs are restored to last running status post successful reboot of that compute node.

Example of Remove Compute

```
# ciscovim help remove-computes
usage: ciscovim remove-computes --setupfile SETUPFILE [-y] [-f] <node1,node2,...>
       Remove compute-nodes from the Openstack cloud

Positional arguments:
<node1,node2,...>  Remove compute nodes

Optional arguments:
--setupfile SETUPFILE  <setupdata_file>. Mandatory for any POD management
                        operation.
-y, --yes              Yes option to perform the action
-f, --force            Force option to remove or reboot
# ciscovim remove-computes --setupfile /tmp/remove_computes_setup_data.yaml gg34-4 -y --force

                        monitoring remove_compute (gg34-4) operation

.....
Cisco VIM Runner logs
.....
```

Example of removing multiple computes

```
# ciscovim remove-computes --setupfile /tmp/remove_computes_setup_data.yaml gg34-1, gg34-2
-y --force
```

Example of reboot compute

```
# ciscovim help reboot
usage: ciscovim reboot [-y] [-f] <node1,node2,...>

Reboot compute-nodes

Positional arguments:
<node1,node2,...>  Reboot Compute Nodes

Optional arguments:
-y, --yes          Yes option to perform the action
-f, --force        Force option to perform the action

# ciscovim reboot gg34-4 -y --force

monitoring reboot (gg34-4) operation

.....
Cisco VIM Runner logs
.....
```

Example of rebooting multiple computes

```
# ciscovim reboot gg34-1, gg34-2 -y --force
```

Managing Reboot Status of Cisco VIM Nodes

Cisco VIM 2.4, has a CLI which helps you to find which CVIM nodes require a reboot after an update. Reboot the nodes after an update so that the cloud is running latest host packages.



Note It is mandatory for the operator to reboot nodes to be able to perform next update or pod management operation.

Run the following command to check the reboot pending status for nodes in the pod (post update):

```
Run ciscovim reboot-status help command
# ciscovim help reboot-status
usage: ciscovim reboot-status
```

List of Openstack Nodes that require a reboot

```
Sample command execution:
# ciscovim reboot-status
```

Fetching Nodes that require a Reboot

```
+-----+-----+
|      Node Name      | Reboot Required |
+-----+-----+
| sjc04-c33-tb2-micropod-1 |          No      |
| sjc04-c33-tb2-micropod-2 |          No      |
| sjc04-c33-tb2-micropod-3 |          No      |
+-----+-----+
```

Cisco UCS Firmware Upgrade

In Cisco VIM 2.4.2, the Cisco Host Upgrade Utility (HUU) tool developed using Cisco Integrated Management Controller (IMC) Python SDK module (imcsdk-0.9.2.0) is leveraged automatically to upgrade all firmware components running on Cisco UCS C-Series servers.



Note The wrapper tool only updates the CIMC bundle packages, as the entire Cisco IMC Software bundle (that includes CIMC, BIOS, adapter and storage controller firmware images through HUU images) is updated by default. Adequate planning is required for CIMC upgrade, as it causes the server to get rebooted.

For Cisco VIM 2.4, the CIMC upgrade tool supports the:

- Upgrade of CIMC bundle images for C-series only.
- Concurrent upgrade of CIMC bundle images on multiple C-series servers.
- Pre-validation check for server type and available HUU images.
- Support of the external http server, Cisco VIM Software Hub, or Cisco VIM Management node for the target CIMC upgrade image mounts.
- Checks if the cloud is deployed successfully, and notifies the user with a proper message.
- Checks if selected hosts have any active VMs running on them and notifies the user with a proper message.

- Generation of consolidated summary on firmware version status, on completing the pre-upgrade and post-upgrade.

**Note**

- Firmware upgrade is supported only on UCS C-series platform and not on UCS B-series and HP platforms.
- If you upgrade CIMC firmware on an existing cloud deployment, it might impact the cloud functionality as the firmware upgrade reboots the host. Hence, ensure that the cloud is operational, post CIMC firmware upgrade.

To check if the cloud is operational, execute the following steps:

- Run the cloud sanity.
- If cloud sanity failure occurs, run cluster recovery and then re-run cloud sanity.

Also for the upgrade operation to work, ensure that the image has the following syntax:
ucs-<server_type>-hhu-<version_number>.iso; for example ucs-c220m4-hhu-2.0.13n.iso or
ucs-c240m4-hhu-2.0.13n.iso;

**Note**

Running the UCS Firmware upgrade on host(s) running active VMs results in downtime on those VMs.

Limitations During Cisco IMC Upgrade

The following are the CVIM management operations which are not allowed when the firmware upgrade is in progress:

- POD management operations: Add, Remove or Replace of nodes
- CVIM Software Update
- CVIM Software Upgrade
- Reconfigure of CVIM features

Tools Usage

The CIMC upgrade utility is a standalone python file (`ucsc_host_upgrade_utility`) which is located under `<cvim_install_dir>/tools/` directory.

To use the tool, execute the following command:

```
[root@hiccup-mgmt-228 tools]# python ucsc_host_upgrade_utility.py -h
usage: ucsc_host_upgrade_utility.py [-h] [--file SETUPFILELOCATION]
                                     [--http-server HTTP_SERVER_IP]
                                     [--sds-server SDS_SERVER_NAME]
                                     [--server-uname UNAME]
                                     [--server-pwd PASSWD]
                                     [--hhu-image-path HUU_IMAGE_PATH]
                                     [--host HOSTS] [--exclude-hosts E_HOSTS]
```

[-y]

Script to perform firmware upgrade

optional arguments:

```
-h, --help          show this help message and exit
--file SETUPFILELOCATION, -f SETUPFILELOCATION
                    Optional, if not defined will read the setup_data.yaml
                    in /root/openstack-configs dir for CIMC information of
                    servers; To override, provide a valid YAML file
                    with the CIMC Credentials.
--http-server HTTP_SERVER_IP, -hs HTTP_SERVER_IP
                    Optional, only needed if a http server is used to host
                    the target CIMC bundle image(s).
--sds-server SDS_SERVER_NAME, -sds SDS_SERVER_NAME
                    Optional, only needed if a Software Distribution
                    Server (SDS) is used to host the target CIMC bundle
                    image(s).
--server-uname UNAME, -u UNAME
                    Optional, only needed if a http server is used to host
                    the target CIMC bundle image(s).
--server-pwd PASSWD, -p PASSWD
                    Optional, only needed if a http server is used to host
                    the target CIMC bundle image(s).
--hvu-image-path HUU_IMAGE_PATH, -path HUU_IMAGE_PATH
                    Comma separated absolute path of the HUU ISO file(s);
                    In the case of a web server hosting the files,
                    provide the absolute path of the URL that includes the
                    file names; that is, exclude the scheme://host/ part
--host HOSTS
                    Comma separated list of host names targeted for CIMC
                    bundle upgrade defined in the target setup_data.yaml
--exclude-hosts E_HOSTS, -e E_HOSTS
                    Comma separated list of hostnames excluded for CIMC
                    bundle upgrade defined in the target setup_data.yaml
-y, -yes
[root@hiccup-mgmt-228 tools]#
```

If the target CIMC upgrade images are available on Cisco VIM Management node, use the below command:

```
python ucsc_host_upgrade_utility.py [--file <setup_data_test.yaml/cimc_servers.yaml>]
-path <hvu_image_paths>
```

If the target CIMC upgrade images are hosted in an external http server that is reachable from the Cisco VIM Management node and CIMC of the servers, use the below command:

```
python ucsc_host_upgrade_utility.py [--file <setup_data_test.yaml/cimc_servers.yaml>]
-hs <http_server_ip/hostname> -u
<https_server_un> -path <http_server_pwd> -path <hvu_image_paths>
```

If the target CIMC upgrade images are hosted in Cisco VIM Software Hub, use the below command:

```
python ucsc_host_upgrade_utility.py --file [setup_data_test.yaml/cimc_servers.yaml] -sds
[Ciso VIM Software Hub_server_ip/hostname] -u
[sds_server_un] -path [sds_server_pwd] -path [hvu_image_paths]
```



Note Pre-requisites to use Ciso VIM Software Hub for hosting the target CIMC bundle image(s) are:

- Ciso VIM Software Hub server must be reachable from the management node over HTTPS.
- Ciso VIM Software Hub server TLS certificate must be trusted by the management node to make TLS connection in verified context.

If `setup_data.yaml` file is not available, you can create it using below command:

```
# UCSC (C-series) sample format of yaml file to specify the CIMC details
SERVERS:
  server-1:
    cimc_info:
      cimc_ip: "cimc-ip-address"
      cimc_username: "cimc-user-name"
      cimc_password: "cimc-password"
  server-2:
    cimc_info:
      cimc_ip: "cimc-ip-address"
      cimc_username: "cimc-user-name"
      cimc_password: "cimc-password"
  server-3:
    cimc_info:
      cimc_ip: "cimc-ip-address"
      cimc_username: "cimc-user-name"
      cimc_password: "cimc-password"
```



CHAPTER 2

Cisco VIM REST API

The following topics explain how to use the Cisco VIM REST API to manage Cisco NFVI.

- [Overview to Cisco VIM REST API, on page 69](#)
- [Cisco VIM REST API Resources, on page 71](#)


Overview to Cisco VIM REST API

Cisco VIM provides a Representational State Transfer (REST) API that is used to install, expand, and update Cisco VIM. Actions performed using the REST APIs are:

- Install Cisco VIM on Cisco NFVI pods
- Add and delete pods to and from Cisco NFVI installations
- Update Cisco VIM software
- Replace controller nodes
- Perform cloud maintenance operations
- Run cloud validations using Virtual Machine ThroughPut (VMTP), a data path performance measurement tool for OpenStack clouds

The following figure shows the workflow of Cisco VIM REST API.

Figure 5: Workflow of Cisco VIM REST API



413787

The Cisco VIM REST API security is provided by the Secure Sockets Layer (SSL) included on the Apache web server. The Pecan-based web application is called by `mod_wsgi`, which runs the Rest API server. The Pecan REST API server requires a username and password to authorize the REST API server requests. Apache handles the authorization process, which authorizes the request to access the Pecan web application. Use the Cisco VIM API to upload a new `setup_data.yaml` file, and start, stop, and query the state of the installation. You can use it to manage the cloud, add and remove compute and Ceph nodes, and replace the controller nodes. A REST API to launch VMTP (L2/L3 data plane testing) and CloudPulse is also provided.

The Cisco VIM REST API is enabled by default in the management node if you are using the supplied Cisco VIM `buildnode.iso`. You can access API server on the `br_api` interface on port 8445. Authentication is enabled by default in the web service.

You can access the API end points using the following URL format:

```
https://<Management_node_api_ip>:8445
```

By default, basic authentication is enabled for the API endpoints in the management node. You can find the authentication credentials in the following file in the management node:

```
/opt/cisco/ui_config.json
```

The following code shows a sample `ui_config.json` file.

```
{
  "Kibana-Url": "http://10.10.10.10:5601",
  "RestAPI-Url": "https:// 10.10.10.10:8445",
  "RestAPI-Username": "admin",
  "RestAPI-Password": "a96e86ccb28d92ceb1df",
  "RestDB-Password": "e32de2263336446e0f57",
  "BuildNodeIP": "10.10.10.10"
}
```

For more information on the Rest API for an end-point, see the *Ciscovim Client RestAPI* section in [Troubleshooting, on page 365](#).

Cisco VIM REST API Resources

Setupdata

REST wrapper for setupdata. Provides methods for listing, creating, modifying, and deleting setupdata.

Retrieving the setupdata

Resource URI

Verb	URI
GET	/v1/setupdata

Example

JSON Request

```
GET /v1/setupdata
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{"setupdatas": [{
  "status": "Active",
  "name": "GG34",
  "uuid": "123"
  "meta": {
    "user": "root"
  },
  "jsondata": {
    .....
  }
}]}
```

Creating the setupdata

Resource URI

Verb	URI
POST	/v1/setupdata

Example

JSON Request

```
POST /v1/setupdata
Accept: application/json
```

```
{
  "name": "GG34",
  "uuid": "123"
  "meta": {
    "user": "root"
  },
  "jsondata": {
    .....
  }
}
```

```

    }
  }

```

JSON Response

```

201 OK
Content-Type: application/json
{
  "status": "Active",
  "name": "GG34",
  "uuid": "123"
  "meta": {
    "user": "root"
  },
  "jsondata": {
    .....
  }
}

```

```

400 Bad Request
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Error"
}

```

```

409 CONFLICT
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Error"
}

```

Retrieving a single setupdata

Resource URI

Verb	URI
GET	/v1/setupdata/(id)

Property:

id—The ID of the setupdata that you want to retrieve.

Example

JSON Request

```

GET /v1/setupdata/123
Accept: application/json

```

JSON Response

```

200 OK
Content-Type: application/json
{
  "status": "Active",
  "name": "GG34",
  "uuid": "123"
}

```

```

        "meta":{
            "user":"root"
        },
        "jsondata":{
            .....
        }
    }
}

404 NOT FOUND
Content-Type: application/json
{
    "debuginfo": null
    "faultcode": "Client"
    "faultstring": "Setupdata could not be found."
}

```

Updating a setupdata

Resource URI

Verb	URI
PUT	/v1/setupdata/(id)

Property:

id—The ID of the setupdata that you want to update.

Example

JSON Request

```

PUT /v1/setupdata/123
Accept: application/json

```

JSON Response

```

200 OK
Content-Type: application/json
{
    "status": "Active",
    "name": "GG34",
    "uuid": "123"
    "meta":{
        "user":"root"
    },
    "jsondata":{
        .....
    }
}

404 NOT FOUND
Content-Type: application/json
{
    "debuginfo": null
    "faultcode": "Client"
    "faultstring": "Setupdata could not be found."
}

```

Deleting a setupdata

Resource URI

Verb	URI
DELETE	/v1/setupdata/(id)

Property:

id—The ID of the setupdata that you want to delete.

Example

JSON Request

```
DELETE /v1/setupdata/123
Accept: application/json
```

JSON Response

```
204 NO CONTENT
Returned on success
```

```
404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Setupdata could not be found."
}
```

```
400 BAD REQUEST
Content-Type: application/json
```

```
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Setupdata cannot be deleted when it is being used by an installation"
}
```

Install resource

REST wrapper for install. Provides methods for starting, stopping, and viewing the status of the installation process.

Return a list of installation

Resource URI

Verb	URI
GET	/v1/install

Example

JSON Request

```
GET /v1/install
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
```

```
{
  "installs": [
    {
      "ceph": "Skipped",
      "uuid": "123",
      "setupdata": "345",
      "vmtpresult": {
        "status": "PASS",
        "EXT_NET": []
      },
      "baremetal": "Success",
      "orchestration": "Success",
      "validationstatus": {
        "status": "PASS",
        "Software_Validation": [],
        "Hardware_Validation": []
      },
      "currentstatus": "Completed",
      "validation": "Success",
      "hostsetup": "Success",
      "vmtp": "Skipped"
    }
  ]
}
```

Create an installation

Resource URI

Verb	URI
POST	/v1/install

Example

JSON Request

```
GET /v1/install
Accept: application/js
{
  "setupdata": "123",
  "stages": [
    "validation",
    "bootstrap",
    "runtimevalidation",
    "baremetal",
    "orchestration",
    "hostsetup",
    "ceph",
    "vmtp"
  ]
}
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
  "ceph": "Skipped",
  "uuid": "123",
  "setupdata": "345",
  "vmtpresult": {
    "status": "PASS",
    "EXT_NET": []
  },
}
```

```

    "baremetal": "Success",
    "orchestration": "Success",
    "validationstatus": "{
      "status": "PASS",
      "Software_Validation": [],
      "Hardware_Validation": []
    }",
    "currentstatus": "Completed",
    "validation": "Success",
    "hostsetup": "Success",
    "vmtp": "Skipped"
  }

409 CONFLICT
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Install already exists"
}

```

Retrieve the installation

Resource URI

Verb	URI
GET	/v1/install/{id}

Property:

id—The ID of the installation that you want to retrieve.

Example

JSON Request

```

GET /v1/install/345
Accept: application/js

```

JSON Response

```

200 OK
Content-Type: application/json
{
  "ceph": "Skipped",
  "uuid": "123",
  "setupdata": "345",
  "vmtpresult": "{
    "status": "PASS",
    "EXT_NET": []
  }",
  "baremetal": "Success",
  "orchestration": "Success",
  "validationstatus": "{
    "status": "PASS",
    "Software_Validation": [],
    "Hardware_Validation": []
  }",
  "currentstatus": "Completed",
  "validation": "Success",

```

```

    "hostsetup": "Success",
    "vmtp": "Skipped"
  }

```

```

404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Install doesn't exists"
}

```

Stop the installation

Resource URI

Verb	URI
DELETE	/v1/install/{id}

Property:

id—The ID of the installation that you want to stop.

Example

JSON Request

```

DELETE /v1/install/345
Accept: application/js

```

JSON Response

```

204 NO CONTENT
Content-Type: application/json

404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Install doesn't exists"
}

```

Nodes

Getting a list of nodes

Resource URI

Verb	URI
GET	/v1/nodes

Example

JSON Request

```

Get /v1/nodes
Accept: application/js

```

JSON Response

```

200 OK
Content-Type: application/json
{
  "nodes": [
    [
      {
        "status": "Active",
        "uuid": "456",
        "setupdata": "123",
        "node_data": "{
          "rack_info": {
            "rack_id": "RackA"
          },
          "cimc_info": {
            "cimc_ip": "10.10.10.10"
          },
          "management_ip": "7.7.7.10"
        }",
        "updated_at": null,
        "mtype": "compute",
        "install": "345",
        "install_logs": "logurl",
        "created_at": "2016-0710T06:17:03.761152",
        "name": " compute-1"
      }
    ]
  ]
}

```

Add New Nodes

The nodes are in compute or block_storage type. Before adding the nodes to the system, the name of the nodes and other necessary information like cimc_ip and rackid must be updated in the setupdata object. If the setupdata object is not updated, the post call does not allow you to add the node.

Resource URI

Verb	URI
POST	/v1/nodes

Example

JSON Request

```

POST /v1/nodes
Accept: application/js
{
  "name" : "compute-5"
}

```

JSON Response

```

201 CREATED
Content-Type: application/json
{
  "status": "ToAdd",
  "uuid": "456",
  "setupdata": "123",

```

```

"node_data": "{
  "rack_info": {
    "rack_id": "RackA"
  },
  "cimc_info": {
    "cimc_ip": "10.10.10.10"
  },
  "management_ip": "7.7.7.10"
}",
"updated_at": null,
"mtype": "compute",
"install": "345",
"install_logs": "logurl",
"created_at": "2016-0710T06:17:03.761152",
"name": " compute-1"
}

```

Retrieve information about a particular node

Resource URI

Verb	URI
GET	/v1/nodes{id}

Property:

id—The ID of the node that you want to retrieve.

Example

JSON Request

```

POST /v1/nodes
Accept: application/js

```

JSON Response

```

200 OK
Content-Type: application/json
{
  "status": "Active",
  "uuid": "456",
  "setupdata": "123",
  "node_data": "{
    "rack_info": {
      "rack_id": "RackA"
    },
    "cimc_info": {
      "cimc_ip": "10.10.10.10"
    },
    "management_ip": "7.7.7.10"
  }",
  "updated_at": null,
  "mtype": "compute",
  "install": "345",
  "install_logs": "logurl",
  "created_at": "2016-0710T06:17:03.761152",
  "name": " compute-1"
}

404 NOT FOUND

```

```
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Node doesn't exists"
}
```

Remove a Node

The node that must be deleted must be removed from the setupdata object. Once the setupdata object is updated, you can safely delete the node. The node object cannot be deleted until it calls the remove node backend and succeeds.

Resource URI

Verb	URI
DELETE	/v1/nodes{id}

Property:

id—The ID of the node that you want to remove.

Example

JSON Request

```
DELETE /v1/nodes/456
Accept: application/js
```

JSON Response

```
204 ACCEPTED
Content-Type: application/json

404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Node doesn't exists"
}
```

To clear the database and delete the entries in the nodes, the delete API is called with special parameters that are passed along with the delete request. The JSON parameters are in the following format.

JSON Request

```
DELETE /v1/nodes/456
Accept: application/js
{
  "clear_db_entry": "True"
}
```

JSON Response

```
204 ACCEPTED
Content-Type: application/json
```

```

404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Node doesn't exists"
}

```



Note This is done only if the node is deleted from the REST API database. The failure reason of the node must be rectified manually apart from the API. True is a string and not a boolean in the preceding line.

Replace a controller

Resource URI

Verb	URI
PUT	/v1/nodes{id}

Property:

id—The ID of the controller that you want to replace.

Example

JSON Request

```

PUT /v1/nodes/456
Accept: application/js

```

JSON Response

```

200 OK
Content-Type: application/json

404 NOT FOUND
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Node doesn't exists"
}

```

Offline validation

REST wrapper does the offline validation of setupdata. Rest Wrapper does only the Software Validation of the input setupdata.

Create an offline validation operation

Resource URI

Verb	URI
POST	/v1/offlinevalidation

Example

JSON Request

```
POST /v1/offlinevalidation
Accept: application/json
{
    "jsondata": "... .."
}
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
    "status": "NotValidated",
    "uuid": "bb42e4ba-c8b7-4a5c-98b3-1f384aae2b69",
    "created_at": "2016-02-03T02:05:28.384274",
    "updated_at": "2016-02-03T02:05:51.880785",
    "jsondata": "{}",
    "validationstatus": {
        "status": "PASS",
        "Software_Validation": [],
        "Hardware_Validation": []
    }
}
```

Retrieve the results of offline validation

Resource URI

Verb	URI
GET	/v1/offlinevalidation

Property:

id—The ID of the node you want to retrieve.

Example

JSON Request

```
GET /v1/offlinevalidation/789
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
    "status": " ValidationSuccess",
    "uuid": "bb42e4ba-c8b7-4a5c-98b3-1f384aae2b69",
    "created_at": "2016-02-03T02:05:28.384274",
    "updated_at": "2016-02-03T02:05:51.880785",
    "jsondata": "{}",
    "validationstatus": {
        "status": "PASS",
        "Software_Validation": [],
        "Hardware_Validation": []
    }
}
```

}

Update

Start an Update Process

Resource URI

Verb	URI
POST	/v1/update

Parameters:

- fileupload - "tar file to upload"
- filename - "Filename being uploaded"

Example

JSON Request

```
curl -sS -X POST --form
"fileupload=@Test/installer.good.tgz" --form
"filename=installer.good.tgz"
https://10.10.10.8445/v1/update
```



Note This curl request is done as a form request.

JSON Response

```
200 OK
Content-Type: application/json
{
  "update_logs": "logurl",
  "update_status": "UpdateSuccess",
  "update_filename": "installer-4579.tgz",
  "created_at": "2016-07-10T18:33:52.698656",
  "updated_at": "2016-07-10T18:54:56.885083"
}

409 CONFLICT
Content-Type: application/json
{
  "debuginfo": null
  "faultcode": "Client"
  "faultstring": "Uploaded file is not in tar format"
}
```

Roll back an update

Resource URI

Verb	URI
PUT	/v1/update

Example

JSON Request

```
PUT /v1/update
Accept: application/json
{
  "action": "rollback"
}
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "update_logs": "logurl",
  "update_status": "ToRollback",
  "update_filename": "installer-4579.tgz",
  "created_at": "2016-07-10T18:33:52.698656",
  "updated_at": "2016-07-10T18:54:56.885083"
}
```

Commit an update

Resource URI

Verb	URI
PUT	/v1/update

Example

JSON Request

```
PUT /v1/update
Accept: application/json
{
  "action": "commit"
}
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "update_logs": "logurl",
  "update_status": "ToCommit",
  "update_filename": "installer-4579.tgz",
  "created_at": "2016-07-10T18:33:52.698656",
  "updated_at": "2016-07-10T18:54:56.885083"
}
```

Retrieve the details of an update

Resource URI

Verb	URI
GET	/v1/update

Example

JSON Request

```
GET /v1/update
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "update_logs": "logurl",
  "update_status": "UpdateSuccess",
  "update_filename": "installer-4579.tgz",
  "created_at": "2016-07-10T18:33:52.698656",
  "updated_at": "2016-07-10T18:54:56.885083"
}
```

Secrets

Retrieve the list of secrets that are associated with the OpenStack Setup

You can retrieve the set of secret password that are associated with the OpenStack setup using the preceding api. This gives the list of secrets for each service in OpenStack.

Resource URI

Verb	URI
GET	/v1/secrets

Example

JSON Request

```
GET /v1/secrets
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "HEAT_KEYSTONE_PASSWORD": "xxxxx",
  "CINDER_KEYSTONE_PASSWORD": "xxxxxx",
  ....
  "RABBITMQ_PASSWORD": "xxxxxx"
}
```

OpenStack Configs

Retrieve the list of OpenStack configs associated with the OpenStack Setup

You can retrieve the set of OpenStack configs associated with the OpenStack setup using the preceding api. This gives the current settings of different configs such as verbose logging, debug logging for different OpenStack services.

Resource URI

Verb	URI
------	-----

GET	/v1/openstack_config
-----	----------------------

Example

JSON Request

```
GET /v1/openstack_config
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "CINDER_DEBUG_LOGGING": false,
  "KEYSTONE_DEBUG_LOGGING": false,
  ...
  ...
  "NOVA_VERBOSE_LOGGING": true
}
```

Version

Retrieve the version of the Cisco Virtualized Infrastructure Manager.

Resource URI

Verb	URI
GET	/v1/version

Example

JSON Request

```
GET /v1/version
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{"version": "1.9.1"}
```

Health of the Management Node

Retrieve the health of the Management node

This API is used to retrieve the health of the management node. It checks various parameters such as partitions, space and so on.

Resource URI

Verb	URI
GET	/v1/health

Example

JSON Request

```
GET /v1/health
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "status": "PASS",
  "BuildNode Validation": {
    "Check Docker Pool Settings": {"status": "Pass", "reason": "None"}
    ...
  }
}
```

Hardware Information

REST wrapper to do hardware information of setupdata. This returns the hardware information of all hardware available in the setupdata.

Create a Hwinfo operation

Resource URI

Verb	URI
GET	/v1/hwinfo

Example

JSON Request

```
POST /v1/hwinfo
Accept: application/json
{
  "setupdata": "c94d7973-2fcc-4cd1-832d-453d66e6b3bf"
}
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
  "status": "hwinfoscheduled",
  "uuid": "928216dd-9828-407b-9739-8a7162bd0676",
  "setupdata": "c94d7973-2fcc-4cd1-832d-453d66e6b3bf",
  "created_at": "2017-03-19T13:41:25.488524",
  "updated_at": null,
  "hwinforeresult": ""
}
```

Retrieve the results of Hwinfo Operation

Resource URI

Verb	URI
GET	/v1/hwinfo/{id}

Property:

id—The ID of the node you want to query.

Example

JSON Request

```
GET /v1/hwinfo/789
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
{
  "status": "hwinfosuccess",
  "uuid": "928216dd-9828-407b-9739-8a7162bd0676",
  "setupdata": "c94d7973-2fcc-4cd1-832d-453d66e6b3bf",
  "created_at": "2017-03-19T13:41:25.488524",
  "updated_at": "2017-03-19T13:42:05.087491",
  "hwinforesult": "{\"172.29.172.73\": {\"firmware\": .....
  .....
  .....
}
```

Release mapping Information

This api is used to see the list of Features included and list of options which can be reconfigured in the Openstack Setup.

Retrieve the release mapping information

Resource URI

Verb	URI
GET	/v1/releasemapping

JSON Request

```
GET /v1/releasemapping
Accept: application/json
```

JSON Response

```
200 OK
Content-Type: application/json
[
  {
    "SWIFTSTACK": {
      "feature_status": true,
    },
    "desc": "swift stack feature"
  }
  },.....
  .....
}
```

POST Install operations

The following are the post install operations that can be performed, after the successful installation of OpenStack. It uses a common api. Following is an Example:

1. reconfigure,
2. reconfigure -regenerate passwords
3. reconfigure -setpasswords,setopenstack_configs
4. check-fernet-keys
5. resync-fernet-keys

6. rotate-fernet-keys

Create a post install operation

Resource URI

Verb	URI
POST	/v1/misc

Example

JSON Request

```
POST /v1/misc
Accept: application/json
{"action": {"reconfigure": true}}
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
  "uuid": "7e30a671-bacf-4e3b-9a8f-5a1fd8a46733",
  "created_at": "2017-03-19T14:03:39.723914",
  "updated_at": null,
  "operation_status": "OperationScheduled",
  "operation_logs": "",
  "operation_name": "{\"reconfigure\": true}"
}
```

Retrieve a status of the post install operation

Resource URI

Verb	URI
GET	/v1/misc

Example

JSON Request

```
GET /v1/misc
Accept: application/json
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
  "uuid": "7e30a671-bacf-4e3b-9a8f-5a1fd8a46733",
  "created_at": "2017-03-19T14:03:39.723914",
  "updated_at": "2017-03-19T14:03:42.181180",
  "operation_status": "OperationRunning",
  "operation_logs": "xxxxxxxxxxxxxxxxxxxx",
  "operation_name": "{\"reconfigure\": true}"
}
```

In VIM Rest APIs exist to support NFVBench, query hardware information and to get a list of optional and mandatory features that the pod supports.

Following are the API details:

NFVBench Network Performance Testing

Create NFVBench Run

Starts the network performance test with provided configuration.

REST API To Create Fixed Rate Test

Verb	URI
Post	v1/nfvbench/create_ndr_pdr_test

Example

JSON Request

```
POST Request URL
/v1/nfvbench/create_fixed_rate_test
JSON Request:
{"nfvbench_request":
{
  "duration_sec": 20,
  "traffic_profile": [
    {
      "name": "custom",
      "l2frame_size": [
        "64",
        "IMIX",
        "1518"
      ]
    }
  ],
  "traffic": {
    "bidirectional": true,
    "profile": "custom"
  },
  "flow_count": 1000
}
}
```

JSON Response

```
201 CREATED
Content-Type: application/json
{
  "status": "not_run",
  "nfvbench_request":
  \{
    "duration_sec": 20,
    "traffic_profile": [
      {
        "name": "custom",
        "l2frame_size": [
          "64",
          "IMIX",
          "1518"
        ]
      }
    ]
  },
  "traffic": {
    "bidirectional": true,
    "profile": "custom"
  },
}
```

```

    "flow_count": 1000
  },
  "created_at": "2017-08-16T06:14:54.219106",
  "updated_at": null,
  "nfvbench_result": "",
  "test_name": "Fixed_Rate_Test"
}

```

Status Polling

Polling of NFVbench run status which is one of nfvbench_running, nfvbench_failed, nfvbench_completed.

Resource URI

Verb	URI
GET	v1/nfvbench/<test_name>

REST API To Get Fixed Rate Test Result

```

GET Request URL
/v1/upgrade/get_fixed_rate_test_result
JSON Response:
Check If NFVbench Test is running
200 OK
Content-Type: application/json
{
  "status": "nfvbench_running",
  "nfvbench_request": '{"traffic": {"bidirectional": true, "profile": "custom"},
"rate": "1000000pps",
"traffic_profile": [{"l2frame_size": ["1518"], "name": "custom"}], "duration_sec": 60,
"flow_count": 1000}',
  "nfvbench_result": ""
  "created_at": "2017-05-30T21:40:40.394274",
  "updated_at": "2017-05-30T21:40:41.367279",
}

```

```

Check If NFVbench Test is completed
200 OK
Content-Type: application/json
{
"status": "nfvbench_completed",
"nfvbench_request": '{"traffic": {"bidirectional": true, "profile": "custom"},
"rate": "1000000pps",
"traffic_profile": [{"l2frame_size": ["1518"], "name": "custom"}], "duration_sec": 60,
"flow_count": 1000}',
"nfvbench_result": '{"status": "PROCESSED", "message": {"date": "2017-08-15 23:15:04",
"nfvbench_version": "0.9.3.dev2", ...}'
"created_at": "2017-05-30T21:40:40.394274",
"updated_at": "2017-05-30T22:29:56.970779",
}

```

REST API to create NDR/PDR Test

```

POST Request URL
/v1/nfvbench/create_ndr_pdr_test

Accept: application/json
{"nfvbench_request":
{
  "duration_sec": 20,
  "traffic_profile": [
    {
      "name": "custom",
      "l2frame_size": [

```

```

        "64",
        "IMIX",
        "1518"
    ]
}
],
"traffic": {
    "bidirectional": true,
    "profile": "custom"
},
"flow_count": 1000
}
}

```

JSON Response

201 CREATED

Content-Type: application/json

```

{
    "status": "not_run",
    "nfvbench_request":
    \{
        "duration_sec": 20,
        "traffic_profile": [
            {
                "name": "custom",
                "l2frame_size": [
                    "64",
                    "IMIX",
                    "1518"
                ]
            }
        ],
        "traffic": {
            "bidirectional": true,
            "profile": "custom"
        },
        "flow_count": 1000
    },
    "created_at": "2017-08-16T07:18:41.652891",
    "updated_at": null,
    "nfvbench_result": "",
    "test_name": "NDR_PDR_Test"
}

```

REST API To Get NDR/PDR Test Results

GET Request URL

/v1/ nfvbench/get_ndr_pdr_test_result

JSON Response:

If NFVbench NDR/PDR test is running

200 OK

Content-Type: application/json

```

{
    "status": "nfvbench_running",
    "nfvbench_request": '{"duration_sec": 20,
    "traffic": {"bidirectional": true, "profile": "custom"},
    "traffic_profile": [{"l2frame_size": ["64", "IMIX", "1518"], "name": "custom"}]',
    "flow_count": 1000}',
    "nfvbench_result": ""
    "created_at": "2017-08-16T07:18:41.652891",
    "updated_at": "2017-09-30T22:29:56.970779",
}

```

```

If NFVbench NDR/PDR test is completed
  200 OK
  Content-Type: application/json
  {
    "status": "nfvbench_completed",
    "nfvbench_request": '{"duration_sec": 20,
"traffic": {"bidirectional": true, "profile": "custom"},
"traffic_profile": [{"l2frame_size": ["64", "IMIX", "1518"], "name": "custom"}], "flow_count":
1000}',
    "nfvbench_result": '{"status": "PROCESSED",...}'
"created_at": "2017-08-16T07:18:41.652891",
"updated_at": "2017-09-30T22:29:56.970779",
  }

```

REST API to Get Node Hardware Information

Rest API helps you to get the hardware information of all the nodes in the POD through CIMC/UCSM.

- Total Memory
- Firmware Info (Model, Serial Number)
- CIMC IP

```

GET Request URL
/v1/hwinfo
Output Response
{
  "hwinforesult": [{"control-server-2": {"memory": {"total_memory": "131072"},
"firmware": {"serial_number": "FCH1905V16Q", "fw_model": "UCSC-C220-M4S"},
"cimc_ip": "172.31.230.100", "storage": {"num_storage": 4},
"cisco_vic_adapters": {"product_name": "UCS VIC 1225"},
"cpu": {"number_of_cores": "24"}, "power_supply": {"power_state": "on"}}
...
}

```

REST API to Get Mandatory Features Mapping

```

POST Request URL
/v1/releasemapping/mandatory_features_mapping

```

```

JSON Response:
{
  "mandatory": {
    "networkType": {
      "C": {
        "feature_status": true,
        "values": [{"name": "VXLAN/Linux Bridge", "value": "VXLAN/Linux Bridge"}],
        "insight_label": "Tenant Network",
        "desc": "Tenant Network"
      },
      "B": {
        "feature_status": true,
        "values": [{"name": "VXLAN/Linux Bridge", "value": "VXLAN/Linux Bridge"}],
        "insight_label": "Tenant Network",
        "desc": "Tenant Network"
      }
    },
    "cephMode": {
      "all": {
        "feature_status": true,

```

```

        "values": [{"name": "Central", "value": "Central"}],
        "insight_label": "Ceph Mode",
        "desc": "Ceph Mode"
    },
},
"podType": {
    "C": {
        "feature_status": true,
        "values": [{"name": "Fullon", "value": "fullon"}],
        "insight_label": "POD Type",
        "desc": "POD Type"
    },
    "B": {
        "feature_status": true,
        "values": [{"name": "Fullon", "value": "fullon"}],
        "insight_label": "POD Type",
        "desc": "POD Type"
    }
},
"installMode": {
    "all": {
        "feature_status": true,
        "values": [{"name": "Connected", "value": "connected"}, ],
        "insight_label": "Install Mode",
        "desc": "Install Mode"
    }
},
},
"platformType": [{"name": "B-series", "value": "B"}, {"name": "C-series", "value":
"C"}],
"postinstalllinks": {
    "view_cloudpulse": {"alwayson": true, "feature_status": true, "platformtype": "all",
"insight_label": "Run VMTP", "desc": "Cloudpluse"},
    "password_reconfigure": {"alwayson": true, "feature_status": true, "platformtype":
"all", "insight_label": "Reconfigure Passwords", "desc": "Reconfigure Passwords"}
}
}
}

```

REST API to Get Optional Features Mapping

POST Request URL
/v1/releasemapping/optional_features_mapping

JSON Response:

```

[
  {
    "SWIFTSTACK": {
      "feature_status": true,
      "insight_label": "Swiftstack",
      "repeated_redeployment": true,
      "reconfigurable": ["cluster_api_endpoint", "reseller_prefix", "admin_password",
"protocol"],
      "desc": "swift stack feature"
    }
  },
  {
    "heat": {
      "feature_status": true,
      "insight_label": "Heat",
      "repeated_redeployment": false,
      "reconfigurable": ["all"],
      "desc": "Openstack HEAT service"
    }
  }
],

```

```
.... other features
]
```

Cloud sanity information

REST wrapper to run cloud-sanity test suites. The cloud-sanity extension to the VIM REST API enables support for managing cloud-sanity test actions

Create a cloud-sanity test

Verb	URI
Post	/v1/cloud-sanity/create

Example

JSON Request

```
POST /v1/cloudsanity/create
Accept: application/json
{"cloudsanity_request": {"command": "create",
                        "action": "test",
                        "test_name": "cephmon",
                        "uuid": ""}}
```

test_name can be all,management,control,compute,cephmon,cephosd

JSON Response

```
201 Created
{
  'cloudsanity_request': "{u'action': u'test', u'command': u'create', u'uuid':
'5dff1662-3d33-4901-808d-479927c01dde',
  u'test_name': u'cephmon'}",
  'cloudsanity_result': '',
  'created_at': '2018-01-26T20:32:20.436445',
  'status': 'not_run',
  'test_name': 'cephmon',
  'updated_at': ''
}
```

List cloud-sanity test results

Verb	URI
GET	/v1/cloud-sanity

JSON Request

```
GET /v1/cloudsanity
```

JSON Response

```
200 OK
{ '0b91746f-90b4-4355-a748-727c2e5c59c5': { 'action': 'test',
                                           'created_at': '2018-01-25 12:08:22',
                                           'status': 'cloudsanity_completed',
                                           'test_name': 'management',
                                           'uuid': '0b91746f-90b4-4355-a748-727c2e5c59c5' },
  '5695cb31-39e4-4be2-9dee-09e7daffc2e7': { 'action': 'test',
                                           'created_at': '2018-01-25 12:03:06',
                                           'status': 'cloudsanity_completed',
                                           'test_name': 'compute',
```

```

      'uuid': '5695cb31-39e4-4be2-9dee-09e7daffc2e7'},
'5dff1662-3d33-4901-808d-479927c01dde': { 'action': 'test',
      'created_at': '2018-01-26 20:32:20',
      'status': 'cloudsanity_completed',
      'test_name': 'cephmon',
      'uuid': '5dff1662-3d33-4901-808d-479927c01dde'},
'7946255d-df58-4432-b729-20cf16eb5ba5': { 'action': 'test',
      'created_at': '2018-01-25 12:05:56',
      'status': 'cloudsanity_completed',
      'test_name': 'cephosd',
      'uuid': '7946255d-df58-4432-b729-20cf16eb5ba5'},
'797d79ba-9ee0-4e11-9d9e-47791dd05e07': { 'action': 'test',
      'created_at': '2018-01-25 12:05:11',
      'status': 'cloudsanity_completed',
      'test_name': 'cephmon',
      'uuid': '797d79ba-9ee0-4e11-9d9e-47791dd05e07'},
'962e2c8e-c7b0-4e24-87c1-528cad84002c': { 'action': 'test',
      'created_at': '2018-01-26 18:52:31',
      'status': 'cloudsanity_completed',
      'test_name': 'control',
      'uuid': '962e2c8e-c7b0-4e24-87c1-528cad84002c'},
'd0111530-ee3b-45df-994c-a0917fd18e11': { 'action': 'test',
      'created_at': '2018-01-26 18:46:23',
      'status': 'cloudsanity_completed',
      'test_name': 'control',
      'uuid': 'd0111530-ee3b-45df-994c-a0917fd18e11'}}

```

List specific cloud-sanity test results

Verb	URI
GET	/v1/cloud-sanity/list/?test_name={all,management,control,compute,cephmon,cephosd}

JSON Request

```

GET /v1/cloudsanity/list/?test_name=cephmon
Accept: application/json

```

JSON Response

```

200 OK
{ '5dff1662-3d33-4901-808d-479927c01dde': { 'action': 'test',
      'created_at': '2018-01-26 20:32:20',
      'status': 'cloudsanity_completed',
      'test_name': 'cephmon',
      'uuid': '5dff1662-3d33-4901-808d-479927c01dde'},
'797d79ba-9ee0-4e11-9d9e-47791dd05e07': { 'action': 'test',
      'created_at': '2018-01-25 12:05:11',
      'status': 'cloudsanity_completed',
      'test_name': 'cephmon',
      'uuid': '797d79ba-9ee0-4e11-9d9e-47791dd05e07'}}

```

Show cloud-sanity test results

Verb	URI
GET	/v1/cloud-sanity/show/?uuid=<uuid>

JSON Request

```
GET /v1/cloudsanity/show/?uuid=d0111530-ee3b-45df-994c-a0917fd18e11
```

JSON Response

```
200 OK
{ 'action': 'test',
  'cloudsanity_request':
    '{u'action': u'test',
     u'command': u'create',
     u'uuid': 'd0111530-ee3b-45df-994c-a0917fd18e11',
     u'test_name': u'control'}",
  'cloudsanity_result':
    '{"status": "PROCESSED",
     "message": {"status": "Pass",
                 "message": "[PASSED] Cloud Sanity Control Checks Passed",
                 "results": {"control": {"ping_all_controller_nodes": "PASSED",
                                         "check_rabbitmq_is_running": "PASSED",
                                         "check_rabbitmq_cluster_status": "PASSED",
                                         "check_nova_service_list": "PASSED",
                                         "ping_internal_vip": "PASSED",
                                         "disk_maintenance_raid_health": "PASSED",
                                         "check_mariadb_cluster_size": "PASSED",
                                         "disk_maintenance_vd_health": "PASSED"}}}}',
  'created_at': '2018-01-26 18:46:23',
  'status': 'cloudsanity_completed',
  'test_name': 'control',
  'updated_at': '2018-01-26 18:47:58',
  'uuid': 'd0111530-ee3b-45df-994c-a0917fd18e11'}
```

Delete cloud-sanity test results

Verb	URI
DELETE	/v1/cloud-sanity/delete/?uuid=<uuid>

JSON Request

```
GET /v1/cloudsanity/delete/?uuid=444aa4c8-d2ba-4379-b035-0f47c686d1c4
```

JSON Response

```
200 OK
{
  "status": "deleted",
  "message": "UUID 444aa4c8-d2ba-4379-b035-0f47c686d1c4 deleted from database",
  "uuid": "444aa4c8-d2ba-4379-b035-0f47c686d1c4",
  "error": "None"
}
```

Disk Maintenance information

REST wrapper to query information about RAID disks on Pod nodes. This returns the RAID disk information of all or a selection of RAID disks available in the Pod.

The disk management extension to the VIM REST API enables support for Disk Management actions

Create a Check disk operation

Resource URI

Verb	URI
POST	/v1/diskmgmt/check_disks

Example

JSON Request

```
POST /v1/diskmgmt/check_disks Accept: application/json
'{"diskmgmt_request": {"command": "create",
  "action": "check-disks",
  "role": "control",
  "locator": "False",
  "json_display": "False",
  "servers": "", "uuid": ""}}
```

JSON Response

```
201 Created
Content-Type: application/json
{
  'action': 'check-disks',
  'created_at': '2018-03-08T02:03:18.170849+00:00',
  'diskmgmt_request': "{u'uuid': '0729bdea-cc19-440f-8339-ab21e76be84b',
    u'json_display': u'False',
    u'servers': u'',
    u'locator': u'False',
    u'role': u'control',
    u'action': u'check-disks',
    u'command': u'create'}",
  'diskmgmt_result': '',
  'status': 'not_run',
  'updated_at': 'None'
}
```

Create a replace disk operation

Verb	URI
POST	/v1/diskmgmt/replace_disks

Example

JSON Request

```
POST /v1/diskmgmt/replace_disks
Accept: application/json
'{"diskmgmt_request": {"command": "create",
  "action": "replace-disks",
  "role": "control",
  "locator": "False",
  "json_display": "False",
  "servers": "", "uuid": ""}}
```

JSON Response

```
201 Created
Content-Type: application/json
{
  "status": "not_run",
  "diskmgmt_request": "{u'uuid': 'cb353f41-6d25-4190-9386-330e971603c9',
    u'json_display': u'False',
```

```

        u'servers': u'',
        u'locator': u'False',
        u'role': u'control',
        u'action': u'replace-disks',
        u'command': u'create'}",
"created_at": "2018-03-09T12:43:41.289531+00:00",
"updated_at": "",
"diskmgmt_result": "",
"action": "replace-disks"}

```

List check disk operation

Verb	URI
GET	/v1/diskmgmt/list/?action= {check-disks,replace-disks &role={all,management,control,compute}

Example

JSON Request

```
GET /v1/diskmgmt/list/?action=check-disks&role=all
```

JSON Response

```

200 OK
Content-Type: application/json
{
  '0be7a55a-37fe-43a1-a975-cbf93ac78893': {
    'action': 'check-disks',
    'created_at': '2018-03-05 14:45:45+00:00',
    'role': 'compute',
    'status': 'diskmgmt_completed',
    'uuid':
'0be7a55a-37fe-43a1-a975-cbf93ac78893'},
  '861d4d73-ffee-40bf-9348-13afc697ee3d': {
    'action': 'check-disks',
    'created_at': '2018-03-05 14:44:47+00:00',
    'role': 'control',
    'status': 'diskmgmt_completed',
    'uuid':
'861d4d73-ffee-40bf-9348-13afc697ee3d'},
  'cdfd18c1-6346-47a2-b0f5-661305b5d160': {
    'action': 'check-disks',
    'created_at': '2018-03-05 14:43:50+00:00',
    'role': 'all',
    'status': 'diskmgmt_completed',
    'uuid':
'cdfd18c1-6346-47a2-b0f5-661305b5d160'}
}
}

```

Show a completed diskmgmt operation

Verb	URI
GET	v1/diskmgmt/show/?uuid=<uuid>

Example

JSON Request

```
GET /v1/diskmgmt/show/?uuid=d24036c6-4557-4c12-8695-a92f6f9315ed
```

JSON Response

```

200 OK
Content-Type: application/json
{
  'action': 'check-disks',
  'created_at': '2018-03-07 21:46:41+00:00',
  'diskmgmt_request': "{u'uuid': 'd24036c6-4557-4c12-8695-a92f6f9315ed',
    u'json_display': False,
    u'servers': u'f24-michigan-micro-2',
    u'locator': False,
    u'role': u'compute',
    u'action': u'check-disks',
    u'command': u'create'}",
  'diskmgmt_result': '{"status": "PROCESSED", "message": [{"\Overall_Status\': \'PASS\',
  \'Result\': {\fcfg_disks_results_list\': [], \'spare_disks_results_list\': [],
  \'raid_results_list\': [{\RAID level\': \'RAID1\', \'Disk Med\': \'HDD\', \'server\':
  \'7.7.7.6\', \'RAID type\': \'HW\', \'host\': \'f24-michigan-micro-2\', \'role\':
  \'block_storage control compute\', \'VD health\': \'Opt1\', \'Num VDs\': 1, \'Num PDs\':
  8, \'RAID health\': \'Opt\'}], \'bad_disks_results_list\': [], \'rbld_disks_results_list\':
  [], \'add_as_spare_disks_results_list\': []}]}}',
  'role': 'compute',
  'status': 'diskmgmt_completed',
  'updated_at': '2018-03-07 21:47:35+00:00',
  'uuid': 'd24036c6-4557-4c12-8695-a92f6f9315ed'
}

```

Delete a completed diskmgmt operation

Verb	URI
DELETE	v1/diskmgmt/delete/?uuid=<uuid>

Example

JSON Request

```
DELETE /v1/diskmgmt/delete/?uuid=d24036c6-4557-4c12-8695-a92f6f9315ed
```

JSON Response

```

200 OK
Content-Type: application/json
{
  "status": "deleted",
  "message": "UUID d24036c6-4557-4c12-8695-a92f6f9315ed deleted from database",
  "uuid": "d24036c6-4557-4c12-8695-a92f6f9315ed",
  "error": "None"
}

```

OSD Maintenance information

REST wrapper to query information about OSD on Pod storage nodes. This returns to the OSD status information of all or a selection of OSDs available in the Pod.

Create a OSD disk operation

Verb	URI
POST	/v1/osdmgmt/check_osds

Example

JSON Request

```
POST /v1/osdmgmt/osdmgmt/check_osds
{"osdmgmt_request": {"command": "create",
                    "action": "check-osds",
                    "locator": "False",
                    "json_display": "False",
                    "servers": "",
                    "osd": "None",
                    "uuid": ""}}
```

JSON Response

```
201 Created
Content-Type: application/json
{
  'action': 'check-osds',
  'created_at': '2018-03-08T21:26:15.329195+00:00',
  'osdmgmt_request': "{u'uuid': '9c64ee52-bed5-4b69-91a2-d589411dd223', u'json_display':
u'False', u'servers': u'', u'locator': u'False', u'command': u'create', u'action':
u'check-osds', u'osd': u'None'}",
  'osdmgmt_result': '',
  'status': 'not_run',
  'updated_at': 'None'
}
```

Create a replace OSD operation

Verb	URI
POST	v1/osdmgmt/replace_osd

Example

JSON Request

```
POST /v1/osdmgmt/replace_osd
Accept: application/json
{"osdmgmt_request": {"command": "create",
                    "action": "replace-osd",
                    "locator": "False",
                    "json_display": "False",
                    "servers": "f24-michigan-micro-1",
                    "osd": "osd.9",
                    "uuid": ""}}
```

JSON Response

```
201 Created
Content-Type: application/json
{
  "status": "not_run",
  "osdmgmt_request": "{u'uuid': '5140f6fb-dca3-4801-8c44-89b293405310', u'json_display':
u'False', u'servers': u'f24-michigan-micro-1', u'locator': u'False', u'command': u'create',
u'action': u'replace-osd', u'osd': u'osd.9'}",
  "created_at": "2018-03-09T15:07:10.731220+00:00",
  "updated_at": null,
  "action": "replace-osd",
  "osdmgmt_result": ""
}
}
```

List check OSD operation

Verb	URI
GET	v1/osdmgmt/list/?action={check-osds,replace-osd}

Example

JSON Request

```
GET /v1/osdmgmt/list/?action=check-osds
```

JSON Response

```
200 OK
Content-Type: application/json
{
  '4efd0be8-a76c-4bc3-89ce-142de458d844': {
    'action': 'check-osds',
    'created_at': '2018-03-08 21:31:01+00:00',
    'status': 'osdmgmt_running',
    'uuid':
  '4efd0be8-a76c-4bc3-89ce-142de458d844'},
  '5fd4f9b5-786a-4a21-a70f-bffac70a3f3f': {
    'action': 'check-osds',
    'created_at': '2018-03-08 21:11:13+00:00',
    'status': 'osdmgmt_completed',
    'uuid':
  '5fd4f9b5-786a-4a21-a70f-bffac70a3f3f'},
  '9c64ee52-bed5-4b69-91a2-d589411dd223': {
    'action': 'check-osds',
    'created_at': '2018-03-08 21:26:15+00:00',
    'status': 'osdmgmt_completed',
    'uuid':
  '9c64ee52-bed5-4b69-91a2-d589411dd223'}
}
```

Show a completed osdmgmt operation

Verb	URI
GET	v1/osdmgmt/show/?uuid=<uuid>

Example

JSON Request

```
GET /v1/osdmgmt/show/?uuid=9c64ee52-bed5-4b69-91a2-d589411dd223
```

JSON Response

```
200 OK
Content-Type: application/json
{
  'action': 'check-osds',
  'created_at': '2018-03-08 21:26:15+00:00',
  'osdmgmt_request': "{u'uuid': '9c64ee52-bed5-4b69-91a2-d589411dd223', u'json_display':
u'False', u'servers': u'', u'locator': u'False', u'command': u'create', u'action':
u'check-osds', u'osd': u'None'}",
  'osdmgmt_result': '{"status": "PROCESSED", "message": [{"\\Overall_Status\\': \\PASS\\',
\\Result\\': { ommitted for doc }}}',
  'status': 'osdmgmt_completed',
  'updated_at': '2018-03-08 21:27:16+00:00',
  'uuid': '9c64ee52-bed5-4b69-91a2-d589411dd223'
```

}

}

Delete a completed osdmgmt operation

Verb	URI
DELETE	v1/osdmgmt/delete/?uuid=<uuid>

Example**JSON Request**

```
DELETE /v1/osdmgmt/delete/?uuid=9c64ee52-bed5-4b69-91a2-d589411dd223
```

JSON Response

```
200 OK
Content-Type: application/json
{
  'error': 'None',
  'message': 'UUID 9c64ee52-bed5-4b69-91a2-d589411dd223 deleted from database',
  'status': 'deleted',
  'uuid': '9c64ee52-bed5-4b69-91a2-d589411dd223'
}
}
```

Hardware Management Utility

REST wrapper to control the execution of or query information from the hardware validation utility.

Create a Validate Operation

Verb	URI
POST	/v1/hardwaremgmt/validate

JSON Request

```
POST /v1/hardwaremgmt/validate
{"hwmgmt_request": {"command": "create",
                    "action": "validate",
                    "hosts": "None",
                    "file": "None",
                    "feature_list": "all",
                    "uuid": ""}}
```

feature_list is a comma separated list of valid features for the given POD

JSON Response

```
201 Created
Content-Type: application/json
{
  'action': 'validate',
  'created_at': '2018-03-08T22:01:22.195232+00:00',
  'hwmgmt_request': "{u'feature_list': u'all', u'command': u'create', u'file': None,
u'action': u'validate', u'hosts': None, u'uuid': '89e094d8-b246-4620-afca-ba3529385cac'}",
  'hwmgmt_result': '',
  'status': 'not_run',
  'updated_at': 'None'
}
```

Create a Validate Operation for Failure

Verb	URI
GET	/v1/hardwaremgmt/resolve_failures

JSON Request

```
POST /v1/hardwaremgmt/resolve_failures
{
  "hwmgmt_request": {
    "command": "create",
    "action": "resolve-failures",
    "hosts": "None",
    "file": "None",
    "feature_list": "all",
    "uuid": ""
  }
}
```

feature_list is a comma separated list of valid features for the given POD

JSON Response

```
201 Created
Content-Type: application/json
{
  "status": "not_run",
  "created_at": "2018-03-09T15:47:36.503712+00:00",
  "hwmgmt_request": "{u'feature_list': u'all', u'command': u'create', u'file': None,
u'action': u'resolve-failures', u'hosts': None, u'uuid':
'49dc1dc9-3170-4f68-b152-0f99bd19f7b1'}",
  "updated_at": "",
  "action": "resolve-failures",
  "hwmgmt_result": ""
}
```

Create a Validate Operation

Verb	URI
GET	v1/hardwaremgmt/list

JSON Request

```
GET /v1/hardwaremgmt/list
```

JSON Response

```
200 OK
Content-Type: application/json
{
  '89e094d8-b246-4620-afca-ba3529385cac': {
    'action': 'validate',
    'created_at': '2018-03-08 22:01:22+00:00',
    'feature_list': 'all',
    'status': 'hardwaremgmt_completed',
    'uuid':
'89e094d8-b246-4620-afca-ba3529385cac'},
  '9f70e872-a888-439a-8661-2d2f36a4f4b1': {
    'action': 'validate',
    'created_at': '2018-03-08 20:34:32+00:00',
    'feature_list': 'all',
    'status': 'hardwaremgmt_completed',
    'uuid':
'9f70e872-a888-439a-8661-2d2f36a4f4b1'}
}
```

Show a completed hardwaremgmt operation

Verb	URI
GET	/v1/hardwaremgmt/show /?uuid=<uuid>

JSON Request

```
GET /v1/hardwaremgmt/show/?uuid=9f70e872-a888-439a-8661-2d2f36a4f4b
```

JSON Response

```
200 OK
Content-Type: application/json
{
  'action': 'validate',
  'created_at': '2018-03-08 20:34:32+00:00',
  'feature_list': 'all',
  'hwmgmt_request': "{u'feature_list': u'all', u'hosts': None, u'file': None, u'action':
u'validate', u'command': u'create', u'uuid': '9f70e872-a888-439a-8661-2d2f36a4f4b1'}",
  'hwmgmt_result': '{"status": "PROCESSED", "message": "Validate of all completed",
"results": [{"status": "PASS", "results": [{"status": "PASS", "name": "CIMC Firmware Version
Check", "err": null}, {"status": "PASS", "name": "All Onboard LOM Ports Check", "err":
null}, {"status": "PASS", "name": "PCIe Slot: HBA Status Check", "err": null}, {"status":
"PASS", "name": "Server Power Status Check", "err": null}, {"status": "PASS", "name": "NFV
Config Check", "err": null}, {"status": "PASS", "name": "Physical Drives Check", "err":
null}, {"status": "PASS", "name": "PCIe Slot(s) OptionROM Check", "err": null}, {"status":
"PASS", "name": "Intel Network Adapter Check", "err": null}]}',
  'status': 'hardwaremgmt_completed',
  'updated_at': '2018-03-08 20:38:02+00:00',
  'uuid': '9f70e872-a888-439a-8661-2d2f36a4f4b1'
```

Delete a completed hardwaremgmt operation

Verb	URI
DELETE	/v1/hardwaremgmt/delete/?uuid=<uuid>

JSON Request

```
DELETE /v1/hardwaremgmt/delete/?uuid=9f70e872-a888-439a-8661-2d2f36a4f4b1
```

JSON Response

```
200 OK
Content-Type: application/json
{
  'error': 'None',
  'message': 'UUID 9f70e872-a888-439a-8661-2d2f36a4f4b1 deleted from database',
  'status': 'deleted',
  'uuid': '9f70e872-a888-439a-8661-2d2f36a4f4b1'
}
```




CHAPTER 3

Monitoring Cisco NFVI Performance

The following topics tell you how to display logs to monitor Cisco VIM performance.

- [Logging and Monitoring in Cisco NFVI, on page 107](#)
- [Displaying Cisco VIM Log Files Using the CLI, on page 109](#)
- [Logging Into the Kibana Dashboard, on page 112](#)
- [Rotation of the Cisco VIM Logs, on page 122](#)
- [Snapshot Manager Tool for Elasticsearch, on page 122](#)
- [Remote NFS Backup for Elasticsearch Snapshots, on page 124](#)
- [Network Performance Test with NFVBench, on page 124](#)

Logging and Monitoring in Cisco NFVI

Cisco VIM uses a combination of open source tools to collect and monitor the Cisco OpenStack services including Elasticsearch, Fluentd, and the Kibana dashboard (EFK).

In VIM, we have moved our platform to use Fluentd, instead of logstash. However, to maintain backwards compatibility, the code, and documentation refers to ELK, instead of EFK at various places. In VIM, these two acronyms are interchangeable, however it refers to the presence of EFK in the offering. OpenStack services that followed by EFK include:


- **MariaDB**—A relational database management system which is based on MySQL. All the OpenStack components store their data in MariaDB.
- **HAProxy**—HAProxy is a free open source software that provides a high-availability load balancer, and proxy server for TCP and HTTP-based applications that spreads requests across multiple servers.
- **Keystone**—Keystone is an OpenStack project that provides identity, token, catalog, and policy services for use specifically by projects in the OpenStack.
- **Glance**—An OpenStack project that allows you to upload and discover data assets that are meant for use with other services.
- **Neutron**—An OpenStack project that provides the network connectivity between interface devices, such as vNICs, managed by other OpenStack services, such as Nova.
- **Nova**—An OpenStack project that is designed to provide massively scalable, on demand, self-service access to compute resources.

- HTTP—The Apache HTTP server Project, an effort to develop and maintain an open-source HTTP server.
- Cinder—An OpenStack block storage service that is designed to present storage resources to the users that are consumed by the OpenStack compute project (Nova).
- Memcached—A general purpose distributed memory caching system.
- CloudPulse—Is an OpenStack tool that checks the health of the cloud. CloudPulse includes operator and end-point tests.
- Heat—The main OpenStack Orchestration program. Heat implements an orchestration engine to launch multiple composite cloud applications that is based on text file templates.
- Other OpenStack services—RabbitMQ, Ceph, Open vSwitch, Linux bridge, Neutron VTS (optional), and others.
- VMTP—Integrated control and data plane log for testing the cloud.
- NFVBench—Network performance benchmarking tool.

A Fluentd container resides on each control, compute, and storage nodes. They forward log to the Fluentd-aggr server residing on the management node.

The following figure shows a high-level schematic of the Fluent service assurance architecture.

Figure 6: EFK Service Assurance Architecture



The EFK flow includes:

- Fluentd extracts the relevant data from the logs and tags them so that Kibana can use it later to display useful information about those logs.
- Fluentd sends the logs from all the compute, controller, and storage nodes to the Fluentd-aggr server on the management node.
- Fluentd-aggr in the management node sends the structured logs into the Elasticsearch database.
- Elasticsearch stores the data, indexes it, and supports fast queries against a large amount of log data.
- Kibana visualizes the data that is stored in Elasticsearch using a custom dashboard. You can also add filters to the data to visualize interesting fragments of the log data.

Displaying Cisco VIM Log Files Using the CLI

Cisco VIM log file location depends on the node and log type. Installer logs are found in the management node under the `/var/log/mercury/<install_uid>/` directory. The last 20 log directories are tarred and kept in this directory. These files contain logs related to bootstrap, build orchestration, baremetal, common setup, and OpenStack orchestration.

If the installer fails, look at the last tar.gz file for logs, for example:

```
[root@mgmtnode mercury]# ls -lrt
total 20
drwxr-xr-x. 2 root root    80 Jul 19 23:42 573f2b7f-4463-4bfa-b57f-98a4a769aced
drwxr-xr-x. 2 root root 4096 Jul 20 03:29 installer
drwxr-xr-x. 2 root root    79 Jul 20 03:29 e9117bc5-544c-4bda-98d5-65bffa56a18f
drwxr-xr-x. 2 root root    79 Jul 20 04:54 36cdf8b5-7a35-4e7e-bb79-0cfb1987f550
drwxr-xr-x. 2 root root    79 Jul 20 04:55 bd739014-fdf1-494e-adc0-98b1fba510bc
drwxr-xr-x. 2 root root    79 Jul 20 04:55 e91c4a6c-ae92-4fef-8f7c-cafa9f5dc1a3
drwxr-xr-x. 2 root root    79 Jul 20 04:58 1962b2ba-ff15-47a6-b292-25b7fb84cd28
drwxr-xr-x. 2 root root    79 Jul 20 04:59 d881d453-f6a0-448e-8873-a7c51d8cc442
drwxr-xr-x. 2 root root    78 Jul 20 05:04 187a15b6-d425-46a8-a4a2-e78b65e008b6
drwxr-xr-x. 2 root root 4096 Jul 20 06:47 d0346cdd-5af6-4058-be86-1330f7ae09d1
drwxr-xr-x. 2 root root    79 Jul 20 17:09 f85c8c6c-32c9-44a8-b649-b63fdb11a79a
drwxr-xr-x. 2 root root    67 Jul 20 18:09 179ed182-17e4-4f1f-a44d-a3b6c16cf323
drwxr-xr-x. 2 root root    68 Jul 20 18:13 426cb05f-b1ee-43ce-862d-5bb4049cc957
drwxr-xr-x. 2 root root    68 Jul 20 18:13 1d2eec9d-f4d8-4325-9eb1-7d96d23e30fc
drwxr-xr-x. 2 root root    68 Jul 20 18:13 02f62a2f-3f59-46a7-9f5f-1656b8721512
drwxr-xr-x. 2 root root    68 Jul 20 18:14 c7417be9-473e-49da-b6d0-d1ab8fb4b1fc
drwxr-xr-x. 2 root root    68 Jul 20 18:17 b4d2077b-c7a9-46e7-9d39-d1281fba9baf
drwxr-xr-x. 2 root root    68 Jul 20 18:35 21972890-3d45-4642-b41d-c5fadfeba21a
drwxr-xr-x. 2 root root    80 Jul 20 19:17 d8b1b54c-7fc1-4ea6-83a5-0e56ff3b67a8
drwxr-xr-x. 2 root root    80 Jul 20 19:17 23a3cc35-4392-40bf-91e6-65c62d973753
drwxr-xr-x. 2 root root    80 Jul 20 19:17 7e831ef9-c932-4b89-8c81-33a45ad82b89
drwxr-xr-x. 2 root root    80 Jul 20 19:18 49ea0917-f9f4-4f5d-82d9-b86570a02dad
drwxr-xr-x. 2 root root    80 Jul 20 19:18 21589a61-5893-4e30-a70e-55ad0dc2e93f
drwxr-xr-x. 2 root root    80 Jul 20 19:22 6ae6d136-7f87-4fc8-92b8-64cd542495bf
drwxr-xr-x. 2 root root 4096 Jul 20 19:46 1c6f4547-c57d-4dcc-a405-ec509306ee25
drwxr-xr-x. 2 root root    68 Jul 20 21:20 c6dcc98d-b45b-4904-a217-d25001275c85
drwxr-xr-x. 2 root root    68 Jul 20 21:40 ee58d5d6-8b61-4431-9f7f-8cab2c331637
drwxr-xr-x. 2 root root 4096 Jul 20 22:06 243cb0f8-5169-430d-a5d8-48008a00d5c7
drwxr-xr-x. 2 root root 4096 Jul 20 22:16 188d53da-f129-46d9-87b7-c876b1aea70c
```

Cisco VIM autobackup logs are found in the following location:

```
# CVIM autobackup logs (auto-backup enabled by default)
/var/log/mercury/autobackup_2.2.x_2018-03-19_15-11-10.log

# Cobbler apache log (may be needed for PXE troubleshooting)
/var/log/cobblerhttpd/access_log
/var/log/cobblerhttpd/error_log

# VMTP logs
/var/log/vmtp/vmtp.log
```

Cisco VIM RestAPI log location

```
# CVIM RestAPI logs
/var/log/mercury_restapi/restapi.log

# CIM RestAPI apache logs (TCP port 8445)
/var/log/httpd/mercury_access.log
/var/log/httpd/mercury_error.log

# CIM RestAPI log-directory logs (TCP port 8008)
/var/log/httpd/access_log
/var/log/httpd/error_log
```

EFK log location

```
# Elasticsearch-fluentd-Kibana
/var/log/elasticsearch/
/var/log/fluentd-aggr/
/var/log/kibana/
/var/log/curator/
```

```
# HAProxy TLS certificate expiration check
/var/log/curator/certchecker.log
```

Viewing Cisco VIM Logs

```
# list logs sorted reverse on time
ls -lrt /var/log/mercury/
# untar logs
tar xvzf /var/log/mercury/<UUID>/mercury_install_2018-3-20_10-2.tar.gz -C /tmp/
```

Cisco VIM Configuration Files

```
# example configuration files
/root/openstack-configs/setup_data.yaml.B_Series_EXAMPLE
/root/openstack-configs/setup_data.yaml.C_Series_EXAMPLE

# system maintained setup files - do not modify directly
# always supply user copy of setup_data.yaml
# when using ciscovim client
/root/openstack-configs/setup_data.yaml

# system inventory in pretty format
/root/openstack-configs/mercury_servers_info

# passwords store
/root/openstack-configs/secrets.yaml

# openstack configuration file
/root/openstack-configs/openstack_config.yaml

# RestAPI password
/opt/cisco/ui_config.json

# Insight password
/opt/cisco/insight/secrets.yaml
```

Enabling debug logs for certain OpenStack Services

```
# openstack config file
/root/openstack-configs/openstack_config.yaml

# help
ciscovim help

# list openstack keys
ciscovim list-openstack-configs

# help on reconfigure sub-command
ciscovim help reconfigure

# how to execute subcommand, example below
# important note: reconfigure requires a maintenance window
ciscovim reconfigure --setopenstackconfig KEYSTONE_DEBUG_LOGGING,CINDER_DEBUG_LOGGING
```

On controller and compute nodes, all services are run within their respective Docker™ containers.

To list the Docker containers in the node, execute the following:

```
[root@control-server-2 ~]# docker ps -a
CONTAINER ID        IMAGE                                     PORTS                NAMES
258b2cald46a       172.31.228.164:5000/mercury-rhel7-osp8/nova-scheduler:4780
"/usr/bin/my_init /no" 25 minutes ago    Up 25 minutes      novascheduler_4780
ffe70809bbe0       172.31.228.164:5000/mercury-rhel7-osp8/nova-novncproxy:4780
"/usr/bin/my_init /st" 25 minutes ago    Up 25 minutes      novanovncproxy_4780
```

```
12b92bcb9dc0          172.31.228.164:5000/mercury-rhel7-osp8/nova-consoleauth:4780
"/usr/bin/my_init /st" 26 minutes ago   Up 26 minutes
```

.....

```
novaconsoleauth_4780
7295596f5167          172.31.228.164:5000/mercury-rhel7-osp8/nova-api:4780
"/usr/bin/my_init /no" 27 minutes ago   Up 27 minutes          novaapi_4780
```

To view the Docker logs of any container, execute the following on the corresponding host:

```
ls -l /var/log/<service_name>/<log_filename>
e.g. ls -l /var/log/keystone/keystone.log
```

To get into a specific container, execute the following commands:

```
[root@control-server-2 ~]# alias | grep container
      root@control-server-2 ~]# source /root/.bashrc
#execute the alias:
      [root@control-server-2 ~]# novaapi
novaapi_4761 [nova@control-server-2 /]$
novaapi_4761 [nova@control-server-2 /]$ exit
exit
```

If the Docker status indicates a container is down (based on output of “docker ps -a”), collect the Docker service logs as well:

```
cd /etc/systemd/system/multi-user.target.wants/
ls docker* # get the corresponding service name from the output
systemctl status <service_name> -n 1000 > /root/filename # redirects the output to the file
```

For storage nodes running Ceph, execute the following to check the cluster status:

```
ceph -v # on monitor nodes (controller), show's ceph version
ceph -s # on monitor nodes (controller), show cluster status
ceph osd lspools #on monitor nodes (controller),list pools
ceph mon stat # summarize monitor status
ceph-disk list # on OSD / storage nodes; List disks, partitions, and Ceph OSDs
rbd list images # on monitor nodes (controller); dump list of image snapshots
rbd list volumes # on monitor nodes (controller); dump list of volumes
```

Logging Into the Kibana Dashboard

Kibana is an open source data visualization platform that is used to explore Cisco VIM logs.

To log into the Kibana dashboard:

Step 1 Using a terminal client, use SSH to log into your management node and enter the password to login.

The following command shows the management node has an IP address of 17.0.0.2:

```
# ssh root@17.0.0.2
root@17.0.0.2's password
```

Step 2 In the SSH terminal session, locate the line containing KIBANA_PASSWORD in /root/installer-{tag-id}/openstack-configs/secrets.yaml. Note the value of the KIBANA_PASSWORD. It is used in Step 4.

```
cat /root/installer-{tag-id}/openstack-configs/secrets.yaml
...
KIBANA_PASSWORD: <note this value>
...
```


Step 3 Navigate to the `http://<management_node_ip_address>:5601`.

Note Kibana uses the HTTPS + TLS to provide a secure connection between the browser and the Kibana service. By default Kibana uses the certificate located at `/var/www/mercury/mercury.<cert|key>` or you can provide your own certificates in `/root/openstack-configs/` directory (using the same `mercury.<cert|key>` file names).

Note If you are accessing Kibana for the first time, by default it shows self-signed certificate. Some browsers display the warning message *Your connection is not private*. Click **Proceed** to access the Kibana link. A window dialog box appears.

Step 4 Enter the Username and Password:

Authentication Required




Username

Password

User Name: admin


Password: <value of ELK_PASSWORD from Step 2>. The Kibana dashboard appears which displays the Cisco VIM service and installer logs.



Step 5 Click the Dashboard to choose the desired dashboard.

Note We recommend you not to use visualize/Timelion/DevTools or Management options on the left side.

Figure 7: Lists of Dashboards




The following are the list of dashboards:

- **Hostlogs Dashboard:** Provides log information of the system for the cloud nodes. This displays entries from the host logs-* index in Elasticsearch. It contains the log from /var/log/messages file on each server.
- **Installer Dashboard:** Provides information about the management node and the installation process. It can only read uncompressed files. Hence, it reads the files prior to the cloud installation. This displays entries from the installer-* index in Elasticsearch.
- **OpenStack Dashboard:** (openstack-* index) Provides log information about all the OpenStack processes. This displays entries from the openstack-* index in Elasticsearch.
- **VMTP Dashboard:** Provides log information about the VMTP runs performed against the cloud. It displays entries from the vmtp-* index in Elasticsearch.

For Example: if you click **OpenStack Dashboard** link the following screen appears.

Figure 8: OpenStack Dashboard



You can switch on from one dashboard to another by selecting the appropriate dashboard from the right top bar menu.

All dashboards have generic and specific fields.

The generic ones are:


- Title: Title is seen at the top left of the page. Title shows which dashboard is being displayed. For Example: OpenStack Dashboard.
- Time: Time is seen at the top right of the page. Time indicates the time schedule for the log information. You can modify the time to indicate absolute, relative time in the past or specify automatically refresh rates.
- Search bar: Search bar is an input field where you can enter a query in the Lucene syntax format to filter the logs by specific fields (which depend on the fields for the index being selected)
- Add a filter tab: Use this tab to introduce filters graphically.

For more information on using Kibana, see the *Kibana documentation* (Version 5.5.1).


Cisco VIM stores the OpenStack logs in Elasticsearch. The Elasticsearch snapshots all the indices (where the data is stored) which are rotated on a periodic basis. You may not see the older data in Kibana if the data is rotated out and/or deleted.

Logs keep being visualized in Kibana as they are being updated in Elasticsearch on the Discover tab. To debug something on kibana, you can program the Kibana dashboard to auto-refresh at specific intervals (by default is off). To enable auto-refresh, click the date at the top right corner of the dashboard and click Auto-refresh to configure the desired value.

Figure 9: Auto-Refresh




you can click **play/pause** button on the top navigator bar to continue/pause the refreshing of logs events:



a) Few examples on usage of filters in Openstack dashboard to gather useful information

- On the Hostlogs Dashboard, in the Events by Host panel, choose a hostname and click the + or - symbol that appears close to the hostname to include or exclude that server from the filter. Then, click the desired slice on the Events By Service panel to add the docker service to the section.
- Under the **Search** field, you see included sections in green and excluded sections in red.

Figure 10: Hostlogs Dashboard




Time	logdate	host	program	message
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.342 8 ERROR oslo.messaging.drivers.impl_rabbit [] Failed to consume message from queue: (0, 0) (403) ACCESS_REFUSED - Login was refused using authentication mechanism AMQPPLAIN. For details see the broker logfile.
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.467 8 DEBUG neutron.plugins.ml2.drivers.openvswitch.agent.ovs_neutron_agent [req-809cbc46-3eaa-492f-a352-f81b34f82210 - - - -] Agent rpc_loop - iteration:1397 started rpc_loop /usr/lib/python2.7/site-packages/neutron/plugins/ml2/drivers/openvswitch/agent/ovs_neutron_agent.py:1965
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.472 8 DEBUG neutron.agent.linux.utils [req-809cbc46-3eaa-492f-a352-f81b34f82210 - - - -] Running command: [ps, '-ppid', '85', '-o', 'pid='] create_process /usr/lib/python2.7/site-packages/neutron/agent/linux/utils.py:89
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.055 8 ERROR oslo.messaging.drivers.impl_rabbit [] [5d14257f-d6f1-4b33-8532-4d80421b66ea] AMQP server on 10.23.222.122:5672 is unreachable: <AMQPError: unknown error>. Trying again in 1 seconds. Client port: None
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.096 8 ERROR oslo.messaging.drivers.impl_rabbit [] [9521d890-240f-46a4-9ff6-5037ad52d6b6] AMQP server on 10.23.222.122:5672 is unreachable: <AMQPError: unknown error>. Trying again in 1 seconds. Client port: None
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.574 8 DEBUG neutron.agent.linux.utils [req-809cbc46-3eaa-492f-a352-f81b34f82210 - - - -] Exit code: 0 execute /usr/lib/python2.7/site-packages/neutron/agent/linux/utils.py:150
September 6th 2017, 19:09:4	-	bing-compute-2	docker	2017-09-07 02:09:44.470 8 DEBUG neutron.plugins.ml2.drivers.openvswitch.agent.openflow.native.ofswitch [req-809cbc46-3eaa-492f-a352-f81b34f82210 - - - -] ofctl request: version=0x4,msg_type=0x12,msg_len=0x38,aid=0x49b523cb,OFFFlowStatsRequest(cookie=0,cookie_mask=0,flags=0,match=OFFMatchOam_fields=(),out_group=4294967295,out_port=4294967295,table_id=23,type=1) result TOFFFlowStatsReslvbody+

b) To know the log events in the Openstack for a given VM by writing the filter directly on the Search field:

Note The uuid of the VM is identified by executing `openstack nova list` or looking at the horizon website.


- Write the Lucene query (`service:nova and service:neutron and message:<uuid>`) in the **Search** field which is on top of the Dashboard. `<uuid>` is the number got from Horizon or nova list for the identifier of the instance VM.

Figure 11: Search Query Page




- For example, if the user wants to know the DHCP events of the Openstack Neutron add filters by clicking outer circle of pie chart::
 - On the OpenStack Dashboard, the Openstack - Events By Service panel has a pie chart with the inner section for the services and the outer sections for the service_subtypes. To add filters for selecting all the events in a service (for example, neutron), click on the inner section of the pie. To add filters for selecting the service_subtypes (for example, dhcp), click on the outer circle of the pie.

Figure 12: Events by Service



- You can scroll down the OpenStack Dashboard to see the OpenStack - Errors and the OpenStack - Events panel. The OpenStack - Errors panel displays the error messages. If there are no errors, the **No results found** message is displayed.




- Without knowing the Lucene Syntax, you can set the filter criteria in the **Search** field using the **Add a filter +** option.

Following are the steps to add a filter:


- Click Add a filter (+).
- Set the filter criteria by choosing appropriate label and operators from the drop-down lists, and entering keywords and click Save.

Figure 13: Add Filters Page



Set the filter criteria by choosing appropriate label and operators from the drop-down lists, and entering keywords.

Figure 14: Choosing Appropriate Labels



Rotation of the Cisco VIM Logs

Cisco VIM stores all logs in Elasticsearch. Elasticsearch indices are rotated on a periodic basis to prevent the disk space overflow by creating snapshots. The following lists show the Snapshots that are defined in `openstack_config.yaml`:

```
# vi ~/openstack-configs/openstack_config.yaml
...
# Elk rotation parameters
elk_rotation_frequency: "monthly" # Available: "daily", "weekly", "fortnightly", "monthly"
elk_rotation_size: 2 # Unit is in Gigabytes (float is allowed)
elk_rotation_del_older: 10 # Delete older than 10 units (where units depends on the
value set on elk_rotation_frequency)
...
```

You can change the frequency of the rotation by changing the values. For more information on how to set the Elasticsearch parameters through VIM API or CLI, refer to the section *Reconfiguring Passwords and OpenStack Configurations*.

Cisco VIM uses the open source Elasticsearch Curator tool to manage the Elasticsearch indices and snapshots. For more information about Elasticsearch handles snapshots, look at the official information on Elastic.co (Version 5.4) <https://www.elastic.co/guide/en/elasticsearch/client/curator/5.4/index.html>.

Snapshot Manager Tool for Elasticsearch

The `snapshot_mgr.sh` tool wraps up the Elasticsearch Curator APIs. This tool helps you to access the snapshots of the logs that are maintained by the Elasticsearch.

Run the following command to view the snapshot logs which is in the tools directory of the installer.

```
# ./tools/snapshot_mgr.py --help
usage: snapshot_mgr.py [options]
```

Snapshot Manager handles snapshot logs maintained by Elasticsearch

optional arguments:

```
-h, --help          show this help message and exit
--list              display all snapshots in Elasticsearch
--display GET_SS   get details of the snapshot called <GET_SS>
--create            create a snapshot
--restore RESTORE_SS restore snapshot named <RESTORE_SS>
--delete DELETE_SS delete the snapshot called <DELETE_SS>
--autodelete threshold_warning threshold_low threshold_high
autodelete snapshots until reach a disk space
threshold
```

Snapshot list gives you the details of the snapshot performed on the system like the UUID, the name the snapshot, end time of the snapshot, the state and the indices where it was snapshotted:

```
# ./snapshot_mgr.py --list
```

indices_snapshotted	uuid	snapshot_name	time_snapshot_ended	state	failures
hostlogs-2018.03.02	6WGVUnKjQbGtZYzfC0yeEg	curator-20180304140002	2018-03-04 14:00:04	SUCCESS	-

```
| U4IVWJNnQW6PdFWxpRUC-A | curator-20180304150001 | 2018-03-04 15:00:04 | SUCCESS |
hostlogs-2018.03.03
| 5RxDuhnETC6TW4XSPDNZlw | curator-20180304160001 | 2018-03-04 16:00:24 | SUCCESS |
installer-2018.03.03, installer-2018.03.01, installer-2018.03.02, openstack-2018.03.02,
hostlogs-2018.03.04, installer-2018.03.04 | - |
| k2gZYwLeRPO98bJZslI2pw | curator-20180305040002 | 2018-03-05 04:00:32 | SUCCESS |
openstack-2018.03.03, hostlogs-2018.03.04, installer-2018.03.04
```

To view the details of the individual snapshot run the display option command.:

```
# ./tools/snapshot_mgr.py --display curator-20180304140002
{ 'duration_in_millis': 1944,
  'end_time': '2018-03-04T14:00:04.019Z',
  'end_time_in_millis': 1520172004019,
  'failures': [],
  'indices': ['hostlogs-2018.03.02'],
  'shards': { 'failed': 0, 'successful': 5, 'total': 5},
  'snapshot': 'curator-20180304140002',
  'start_time': '2018-03-04T14:00:02.075Z',
  'start_time_in_millis': 1520172002075,
  'state': 'SUCCESS',
  'uuid': '6WGVUnKjQbGtZYzfC0yeEg',
  'version': '6.0.0',
  'version_id': 6000099}
```

To create a snapshot run the following command:

```
# ./tools/snapshot_mgr.py --create
Executing: curl PUT
http://localhost:9200/_snapshot/es_backup/3a9b90c2979b46bf9c7b3f9223074d5d?wait_for_completion=true
-d
{ 'indices': 'installer-*,hostlogs-*,openstack-*,vmtp-*', 'ignore_unavailable': 'true',
  'include_global_state': 'false' }
Response: {u'snapshot': {u'uuid': u'BSznQj1SQ9mjxxxk9swTirQ', u'duration_in_millis': 46496,
  u'start_time':
  u'2018-03-06T16:37:49.774Z', u'shards': {u'successful': 35, u'failed': 0, u'total': 35},
  u'version_id': 6000099,
  u'end_time_in_millis': 1520354316270, u'state': u'SUCCESS', u'version': u'6.0.0',
  u'snapshot': u'3a9b90c2979b46bf9c7b3f9223074d5d', u'end_time': u'2018-03-06T16:38:36.270Z',

  u'indices': [u'installer-2018.03.06', u'vmtp-2018.03.02', u'hostlogs-2018.03.06',
  u'hostlogs-2018.03.05',
  u'installer-2018.03.05', u'openstack-2018.03.05', u'openstack-2018.03.06'],
  u'failures': [], u'start_time_in_millis': 1520354269774}}
```

Run the following command to delete a snapshot:

```
# ./tools/snapshot_mgr.py --delete 3a9b90c2979b46bf9c7b3f9223074d5d
Executing: curl DELETE
http://localhost:9200/_snapshot/es_backup/3a9b90c2979b46bf9c7b3f9223074d5d -d None
Response: {u'acknowledged': True}
```

Restore the indices of a snapshot back to the Elasticsearch database by using the restore option. Run the following command to restore:

```
# ./snapshot_mgr.py --restore curator-20180306050001
Executing: curl POST
http://localhost:9200/hostlogs-2018.03.04,installer-2018.03.05,installer-2018.03.04,
openstack-2018.03.04,hostlogs-2018.03.05,openstack-2018.03.02/_close -d None
```

Remote NFS Backup for Elasticsearch Snapshots

Cisco VIM 2.4, supports remote NFS backup of the Elasticsearch snapshots. This allows you to empty the disk space in the Elasticsearch snapshots. You can use the snapshot manager tool to manually create, list, show, and delete snapshots.

Remote NFS backup of the Elasticsearch snapshots.feature can be configured by adding the following section to the `setup_data.yaml` configuration file:

```
ES_REMOTE_BACKUP: # Set if Elasticsearch backups can use a remote host
  service: 'NFS' # Set if an remote NFS server is used
  remote_host: <ip_addr> # IP of the NFS server
  remote_path: /root/es_remote # Path to location of the backups in the remote server
```

Important considerations about the remote NFS directory on the remote server (specified by the `remote_path` config option):

- This directory allows the `elasticsearch` user (pid number 2020) and group `mercury` (pid 500) to read, and write. Otherwise, Curator cannot copy the snapshots to the remote NFS directory.
- It is good if the folder is empty and is used only by Cisco VIM.
- Cisco VIM does not delete the information in this directory after `unbootstrap`.

You can enable or disable this feature by running `reconfigure`. Also it can change the `remote_host` ip or the `remote_path` by doing `reconfigure`.

Network Performance Test with NFVBench

NFVBench is a network performance benchmarking tool integrated with Cisco VIM. For more details, refer to NFVBench section of *Chapter 1* in the admin guide for details.



CHAPTER 4

Managing Cisco NFVI Security

The following topics describe Cisco NFVI network and application security and best practices.

- [Verifying Management Node Network Permissions, on page 125](#)
- [Verifying Management Node File Permissions, on page 126](#)
- [Viewing Administrator Access Attempts, on page 126](#)
- [Verifying SELinux, on page 127](#)
- [Validating Port Listening Services, on page 127](#)
- [Validating Non-Root Users for OpenStack Services, on page 128](#)
- [Verifying Password Strength, on page 128](#)
- [Reconfiguring Passwords and OpenStack Configurations, on page 129](#)
- [Enabling CVIMMON Post Pod Installation, on page 133](#)
- [Enabling NFVIMON Post Pod Install, on page 133](#)
- [Reconfiguring CIMC Password on an Existing Install, on page 135](#)
- [Increasing Provider and Tenant VLAN Ranges, on page 136](#)
- [Fernet Key Operations, on page 137](#)
- [Managing Certificates, on page 138](#)
- [Reconfiguring TLS Certificates, on page 138](#)
- [Enabling Keystone v3 on an Existing Install, on page 139](#)
- [Cisco VIM Monitor Alerting Rules Customization, on page 145](#)
- [Alert Manager and Receiver Customization, on page 148](#)

Verifying Management Node Network Permissions

The Cisco NFVI management node stores sensitive information related to Cisco NFVI operations. Access to the management node can be restricted to requests coming from IP addresses known to be used by administrators. The administrator source networks is configured in the setup file, under **[NETWORKING]** using the **admin_source_networks** parameter.

To verify this host based firewall setting, log into the management node as an admin user and list the rules currently enforces by iptables. Verify that the source networks match the values configured. If no source networks have been configured, then all source traffic is allowed. However, note that only traffic destined to ports with known admin services is allowed to pass. The **admin_source_networks** value can be set at install time or changed through a reconfigure.

```
[root@control-server-1 ~]# iptables -list
Chain INPUT (policy ACCEPT)
```

```

target      prot opt source                destination
ACCEPT      icmp -- anywhere              anywhere
ACCEPT      tcp  -- 10.0.0.0/8            anywhere
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:ssh
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:https
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:https
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:4979
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:4979
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:esmagent
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:esmagent
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:8008
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:8008
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:copy
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:copy
ACCEPT      tcp  -- 10.0.0.0/8            anywhere      tcp dpt:22250
ACCEPT      tcp  -- 172.16.0.0/12         anywhere      tcp dpt:22250
ACCEPT      all  -- anywhere              anywhere      state RELATED,ESTABLISHED
DROP        all  -- anywhere              anywhere

```

Verifying Management Node File Permissions

The Cisco NFVI management node stores sensitive information related to Cisco NFVI operations. These files are secured by strict file permissions. Sensitive files include `secrets.yaml`, `openrc`, `*.key`, and `*.pem`. To verify the file permissions, log into the management node as an admin user and list all of the files in the `~/openstack-configs/` directory. Verify that only the owner has read and write access to these files. For example:

```

[root@control-server-1 ~]# ls -l ~/openstack-configs
total 172
-rw-----. 1 root root 3272 Jun 21 17:57 haproxy.key
-rw-----. 1 root root 5167 Jun 21 17:57 haproxy.pem
-rw-----. 1 root root 223 Aug 8 18:09 openrc
-rw-----. 1 root root 942 Jul 6 19:44 secrets.yaml

[...]

```

Viewing Administrator Access Attempts

As the UCS servers are part of the critical Cisco NFVI infrastructure, Cisco recommends monitoring administrator login access periodically.

To view the access attempts, use the `journalctl` command to view the log created by ssh. For example:

```

[root@control-server-1 ~]# journalctl -u sshd
-- Logs begin at Tue 2016-06-21 17:39:35 UTC, end at Mon 2016-08-08 17:25:06 UTC. --
Jun 21 17:40:03 hh23-12 systemd[1]: Started OpenSSH server daemon.
Jun 21 17:40:03 hh23-12 systemd[1]: Starting OpenSSH server daemon...
Jun 21 17:40:03 hh23-12 sshd[2393]: Server listening on 0.0.0.0 port 22.
Jun 21 17:40:03 hh23-12 sshd[2393]: Server listening on :: port 22.
Jun 21 17:40:43 hh23-12 sshd[12657]: Connection closed by 171.70.163.201 [preauth]
Jun 21 17:41:13 hh23-12 sshd[12659]: Accepted password for root from 171.70.163.201 port 40499
Jun 21 17:46:41 hh23-12 systemd[1]: Stopping OpenSSH server daemon...
Jun 21 17:46:41 hh23-12 sshd[2393]: Received signal 15; terminating.
Jun 21 17:46:41 hh23-12 systemd[1]: Started OpenSSH server daemon.
Jun 21 17:46:41 hh23-12 systemd[1]: Starting OpenSSH server daemon...
Jun 21 17:46:41 hh23-12 sshd[13930]: Server listening on 0.0.0.0 port 22.
Jun 21 17:46:41 hh23-12 sshd[13930]: Server listening on :: port 22.

```

```

Jun 21 17:50:45 hh23-12 sshd[33964]: Accepted password for root from 171.70.163.201 port
40545
Jun 21 17:56:36 hh23-12 sshd[34028]: Connection closed by 192.168.212.20 [preauth]
Jun 21 17:57:08 hh23-12 sshd[34030]: Accepted publickey for root from 10.117.212.20 port
62819
Jun 22 16:42:40 hh23-12 sshd[8485]: Invalid user user1 from 10.117.212.20
Jun 22 16:42:40 hh23-12 sshd[8485]: input_userauth_request: invalid user user1 [preauth]
s

```

Verifying SELinux

To minimize the impact of a security breach on a Cisco NFVI server, the Cisco VM enables SELinux (Security Enhanced Linux) to protect the server resources. To validate that SELinux is configured and running in enforcing mode, use the `sestatus` command to view the status of SELinux and verify that its status is enabled and in enforcing mode. For example:

```

[root@mgmt1 ~]# /usr/sbin/sestatus -v
SELinux status:                enabled
SELinuxfs mount:              /sys/fs/selinux
SELinux root directory:      /etc/selinux
Loaded policy name:           targeted
Current mode:                 enforcing
Mode from config file:       permissive
Policy MLS status:           enabled
Policy deny_unknown status:  allowed
Max kernel policy version:   28

```

Validating Port Listening Services

To prevent access by unauthorized users and processes, Cisco NFVI has no extra services listening on network ports. To verify this, use the `netstat -plnt` command to get a list of all services listening on the node and verify that no unauthorized services are listening. For example:

```

[root@-control-server-1 ~]# netstat -plnt
Active Internet connections (only servers)
Proto Recv-Q Send-Q Local Address           Foreign Address         State       PID/Program
name
tcp      0      0 23.23.4.101:8776        0.0.0.0:*                LISTEN     24468/python2
tcp      0      0 23.23.4.101:5000        0.0.0.0:*                LISTEN     19874/httpd
tcp      0      0 23.23.4.101:5672        0.0.0.0:*                LISTEN     18878/beam.smp

tcp      0      0 23.23.4.101:3306        0.0.0.0:*                LISTEN     18337/mysqld
tcp      0      0 127.0.0.1:11211         0.0.0.0:*                LISTEN     16563/memcached
tcp      0      0 23.23.4.101:11211      0.0.0.0:*                LISTEN     16563/memcached
tcp      0      0 23.23.4.101:9292        0.0.0.0:*                LISTEN     21175/python2
tcp      0      0 23.23.4.101:9999        0.0.0.0:*                LISTEN     28555/python
tcp      0      0 23.23.4.101:80          0.0.0.0:*                LISTEN     28943/httpd
tcp      0      0 0.0.0.0:4369            0.0.0.0:*                LISTEN     18897/epmd

tcp      0      0 127.0.0.1:4243          0.0.0.0:*                LISTEN     14673/docker

tcp      0      0 0.0.0.0:22              0.0.0.0:*                LISTEN     2909/ssh

tcp      0      0 23.23.4.101:4567        0.0.0.0:*                LISTEN     18337/mysqld
tcp      0      0 23.23.4.101:15672       0.0.0.0:*                LISTEN     18878/beam.smp
tcp      0      0 0.0.0.0:35672           0.0.0.0:*                LISTEN     18878/beam.smp

```

```

tcp        0      0 127.0.0.1:25          0.0.0.0:*        LISTEN     4531/master
tcp        0      0 23.23.4.101:35357    0.0.0.0:*        LISTEN     19874/httpd
tcp        0      0 23.23.4.101:8000     0.0.0.0:*        LISTEN     30505/python
tcp        0      0 23.23.4.101:6080     0.0.0.0:*        LISTEN     27996/python2
tcp        0      0 23.23.4.101:9696     0.0.0.0:*        LISTEN     22396/python2
tcp        0      0 23.23.4.101:8004     0.0.0.0:*        LISTEN     30134/python
tcp        0      0 23.23.4.101:8773     0.0.0.0:*        LISTEN     27194/python2
tcp        0      0 23.23.4.101:8774     0.0.0.0:*        LISTEN     27194/python2
tcp        0      0 23.23.4.101:8775     0.0.0.0:*        LISTEN     27194/python2
tcp        0      0 23.23.4.101:9191     0.0.0.0:*        LISTEN     20752/python2
tcp6      0      0 :::9200               :::*              LISTEN     18439/xinetd
tcp6      0      0 :::4369               :::*              LISTEN     18897/epmd
tcp6      0      0 :::22                 :::*              LISTEN     2909/sshd
tcp6      0      0 :::1:25               :::*              LISTEN     4531/master

```

Validating Non-Root Users for OpenStack Services

To prevent unauthorized access, Cisco NFVI runs OpenStack processes as a non-root user. To verify OpenStack processes are not running as root, use the `ps` command to get a list of all node processes. In the following example the user is 162:

```

[root@control-server-1 ~]# ps -aux | grep nova-api
162      27194  0.6  0.0 360924 132996 ?        S    Aug08   76:58 /usr/bin/python2
/usr/bin/nova-api
162      27231  0.0  0.0 332192  98988 ?        S    Aug08    0:01 /usr/bin/python2
/usr/bin/nova-api
162      27232  0.0  0.0 332192  98988 ?        S    Aug08    0:01 /usr/bin/python2
/usr/bin/nova-api
162      27233  0.0  0.0 332192  98988 ?        S    Aug08    0:01 /usr/bin/python2
/usr/bin/nova-api

```

Verifying Password Strength

Cisco NFVI passwords can be generated in two ways during installation:

- The Cisco NFVI installer generates unique passwords automatically for each protected service.
- You can provide an input file containing the passwords you prefer.

Cisco-generated passwords are unique, long, and contain a mixture of uppercase, lowercase, and numbers. If you provide the passwords, password strength is your responsibility.

You can view the passwords by displaying the `secrets.yaml` file. For example:

```
[root@mgmt1 ~]# cat ~/openstack-configs/secrets.yaml
ADMIN_USER_PASSWORD: QaZ12n13wvvNY7AH
CINDER_DB_PASSWORD: buJL8pAfytoJ0Icm
CINDER_KEYSTONE_PASSWORD: AYbcB8mx6a5Ot549
CLOUDPULSE_KEYSTONE_PASSWORD: HAT6vbl7Z56yZLtN
COBBLER_PASSWORD: bax81eYFyyDon0ps
CPULSE_DB_PASSWORD: aYGSzURpGChztbMv
DB_ROOT_PASSWORD: bjb3Uvwus6cvaNe5
KIBANA_PASSWORD: c50e57Dbm7LF0dRV
[...]
```

Reconfiguring Passwords and OpenStack Configurations



Note This section is not applicable, if you have installed the optional Cisco Virtual Topology System. For information about use of passwords when VTS is installed, see *Installing Cisco VTS* section in the *Cisco NFV Infrastructure 2.4 Installation Guide*.

You can reset some configurations after installation including the OpenStack service password and debugs, TLS certificates, and ELK configurations. Two files, `secrets.yaml` and `openstack_config.yaml` which are located in `:/root/installer-{tag id}/openstack-configs/`, contain the passwords, debugs, TLS file location, and ELK configurations. Also, Elasticsearch uses disk space for the data that is sent to it. These files can grow in size, and Cisco VIM has configuration variables that establishes the frequency and file size under which they are rotated.

Cisco VIM installer generates the OpenStack service and database passwords with 16 alphanumeric characters and stores those in `/root/openstack-configs/secrets.yaml`. You can change the OpenStack service and database passwords using the password reconfigure command on the deployed cloud. The command identifies the containers affected by the password change and restarts them so the new password can take effect.



Note Always schedule the password reconfiguration in a maintenance window as the container restart might disrupt the control plane.

Run the following command to view the list of passwords and configurations:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 installer-xxxx]# ciscovim help reconfigure
usage: ciscovim reconfigure [--regenerate_secrets] [--setpassword <secretkey>]
                             [--setopenstackconfig <option>]
```

Reconfigure the openstack cloud

Optional arguments:

```
--regenerate_secrets           Regenerate All Secrets
--setpassword <secretkey>     Set of secret keys to be changed.
--setopenstackconfig <option> Set of Openstack config to be changed.
```

```
[root@mgmt1 ~]# ciscovim list-openstack-configs
```

Name	Option
CINDER_DEBUG_LOGGING	False
KEYSTONE_DEBUG_LOGGING	False
CLOUDPULSE_VERBOSE_LOGGING	True
MAGNUM_VERBOSE_LOGGING	True

```

|     NOVA_DEBUG_LOGGING           |           True           |
| NEUTRON_VERBOSE_LOGGING         |           True           |
| external_lb_vip_cert             | /root/openstack-configs/haproxy.pem |
| GLANCE_VERBOSE_LOGGING          |           True           |
|                                   |                           |
| elk_rotation_frequency           |           monthly        |
| CEILOMETER_VERBOSE_LOGGING      |           True           |
| elk_rotation_del_older           |           10             |
| HEAT_DEBUG_LOGGING              |           False          |
| KEYSTONE_VERBOSE_LOGGING        |           True           |
| external_lb_vip_cacert           | /root/openstack-configs/haproxy-ca.crt |
| MAGNUM_DEBUG_LOGGING            |           True           |
| CINDER_VERBOSE_LOGGING          |           True           |
| elk_rotation_size                |           2              |
| CLOUDPULSE_DEBUG_LOGGING        |           False          |
| NEUTRON_DEBUG_LOGGING           |           True           |
| HEAT_VERBOSE_LOGGING            |           True           |
| CEILOMETER_DEBUG_LOGGING        |           False          |
| GLANCE_DEBUG_LOGGING            |           False          |
| NOVA_VERBOSE_LOGGING            |           True           |
+-----+-----+
[root@mgmt1 installer-xxxx]#
[root@mgmt1 installer-xxxx]# ciscovim list-password-keys
+-----+-----+
| Password Keys                    |
+-----+-----+
| COBBLER_PASSWORD                 |
| CPULSE_DB_PASSWORD               |
| DB_ROOT_PASSWORD                 |
| KIBANA_PASSWORD                  |
| GLANCE_DB_PASSWORD               |
| GLANCE_KEYSTONE_PASSWORD         |
| HAPROXY_PASSWORD                 |
| HEAT_DB_PASSWORD                 |
| HEAT_KEYSTONE_PASSWORD           |
| HEAT_STACK_DOMAIN_ADMIN_PASSWORD |
| HORIZON_SECRET_KEY               |
| KEYSTONE_ADMIN_TOKEN             |
| KEYSTONE_DB_PASSWORD             |
| METADATA_PROXY_SHARED_SECRET     |
| NEUTRON_DB_PASSWORD              |
| NEUTRON_KEYSTONE_PASSWORD        |
| NOVA_DB_PASSWORD                 |
| NOVA_KEYSTONE_PASSWORD           |
| RABBITMQ_ERLANG_COOKIE           |
| RABBITMQ_PASSWORD                |
| WSREP_PASSWORD                   |
+-----+-----+
[root@mgmt1 installer-xxxx]#

```

You can change specific password and configuration identified from the available list.

Run the reconfiguration command as follows:

```

[root@mgmt1 ~]# ciscovim help reconfigure
usage: ciscovim reconfigure [--regenerate_secrets] [--setpassword <secretkey>]
                             [--setopenstackconfig <option>]

```

Reconfigure the Openstack cloud

Optional arguments:

```

--regenerate_secrets           Regenerate All Secrets
--setpassword <secretkey>     Set of secret keys to be changed.
--setopenstackconfig <option> Set of Openstack config to be changed.

```

```
[root@mgmt1 ~]# ciscovim reconfigure --setpassword ADMIN_USER_PASSWORD,NOVA_DB_PASSWORD
--setopenstackconfig HEAT_DEBUG_LOGGING,HEAT_VERBOSE_LOGGING
Password for ADMIN_USER_PASSWORD:
Password for NOVA_DB_PASSWORD:
Enter T/F for option HEAT_DEBUG_LOGGING:T
Enter T/F for option HEAT_VERBOSE_LOGGING:T
```

The password must be alphanumeric and can be maximum 32 characters in length.

Following are the configuration parameters for OpenStack:

Configuration Parameter	Allowed Values
CEILOMETER_DEBUG_LOGGING	T/F (True or False)
CEILOMETER_VERBOSE_LOGGING	T/F (True or False)
CINDER_DEBUG_LOGGING	T/F (True or False)
CINDER_VERBOSE_LOGGING	T/F (True or False)
CLOUDPULSE_DEBUG_LOGGING	T/F (True or False)
CLOUDPULSE_VERBOSE_LOGGING	T/F (True or False)
GLANCE_DEBUG_LOGGING	T/F (True or False)
GLANCE_VERBOSE_LOGGING	T/F (True or False)
HEAT_DEBUG_LOGGING	T/F (True or False)
HEAT_VERBOSE_LOGGING	T/F (True or False)
KEYSTONE_DEBUG_LOGGING	T/F (True or False)
KEYSTONE_VERBOSE_LOGGING	T/F (True or False)
MAGNUM_DEBUG_LOGGING	T/F (True or False)
MAGNUM_VERBOSE_LOGGING	T/F (True or False)
NEUTRON_DEBUG_LOGGING	T/F (True or False)
NEUTRON_VERBOSE_LOGGING	T/F (True or False)
NOVA_DEBUG_LOGGING	T/F (True or False)
NOVA_VERBOSE_LOGGING	T/F (True or False)
elk_rotation_del_older	Days after which older logs are purged
elk_rotation_frequency	Available options: "daily", "weekly", "fortnightly", "monthly"
elk_rotation_size	Gigabytes (entry of type float/int is allowed)
external_lb_vip_cacert	Location of HAProxy CA certificate

external_lb_vip_cert	Location of HAProxy certificate
NOVA_RAM_ALLOCATION_RATIO	Mem oversubscription ratio (from 1.0 to 4.0)
NOVA_CPU_ALLOCATION_RATIO	CPU allocation ratio (from 1.0 to 16.0)
ES_SNAPSHOT_AUTODELETE	Elastic search auto-delete configuration, can manage the following: period: ["hourly", "daily", "weekly", "monthly"] # Frequency of cronjob to check for disk space threshold_warning: <1-99> # % of disk space occupied to display warning message threshold_low: <1-99> # % of disk space occupied after cleaning up snapshots threshold_high: <1-99> # % of disk space when starting to delete snapshots

Alternatively, you can regenerate all passwords using regenerate_secrets command option as follows:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --regenerate_secrets
```

In addition to the services passwords, you can change the debug and verbose options for Heat, Glance, Cinder, Nova, Neutron, Keystone and Cloudpulse in /root/openstack-configs/openstack_config.yaml. You can modify the other configurations including the ELK configuration parameters, API and Horizon TLS certificates, Root CA, NOVA_EAMALLOCATION_RATIO and ES_SNAPSHOT_AUTODELETE. When reconfiguring these options (For Example API and TLS), some control plane downtime will occur, so plan the changes during maintenance windows.

The command to reconfigure these elements are:

```
ciscovim reconfigure
```

The command includes a built-in validation to ensure that you do not enter typos in the secrets.yaml or openstack_config.yaml files.

When reconfiguration of password or enabling of openstack-services fails, all subsequent pod management operations are blocked. In such case, you can contact Cisco TAC to resolve the situation.



Note

- For pod operations, OpenStack uses the service accounts such as admin, cinder, glance, heat, heat_domain_admin, neutron, nova, placement, and cloudpulse. These accounts use passwords to authenticate each other for standard operations. You must not change the password used by these accounts, other than using the ciscovim reconfigure operation. To enforce this behavior, starting Cisco VIM 2.4.5, the "change password" panel is disabled on the Horizon dashboard for these accounts.
- You should create personal OpenStack user accounts for those who need OpenStack admin or member access. You can change the passwords for these accounts through the Horizon dashboard, OpenStack CLI, or OpenStack client interface.

Enabling CVIMMON Post Pod Installation

CVIMMON, an extensive monitoring solution, is designed to monitor a single pod from a single management system. Cisco VIM can be optionally installed with CVIMMON, to monitor the health and performance of the NFV infrastructure. CVIMMON is enabled by extending the `setup_data.yaml` with relevant information on an existing pod, using the `reconfigure` option.

Post installation of Cisco VIM 2.4.3 or later versions, you can enable CVIMMON and CVIM-TRAP (SNMP, SERVER_MON) using the `reconfigure` option.



Note CVIM-TRAP can be enabled, only if CVIMMON exists. Once the CVIMMON or CVIM-TRAP is enabled, it cannot be disabled again.

To enable the CVIMMON and SNMP features or to change the individual parameters in CVIMMON and SNMP:

1. Take a backup of `setup_data` file and update it manually with the configuration details by entering the following command:

```
# cd /root/  
# mkdir MyDir  
# cp /root/openstack-configs/setup_data.yaml /root/MyDir  
# cd /root/MyDir
```

2. Edit the setup data.
3. Save the file and execute the below command. For sample configuration, see *Enabling CVIMMON on Cisco VIM* section of *CVIM Installation Guide*

```
#ciscovim --setupfile /root/MyDir/setup_data.yaml reconfigure
```



Note Migration from SNMPv2 to SNMPv3 is only supported, but not vice-versa.

Enabling NFVIMON Post Pod Install

You can optionally install Cisco VIM with a third-party software known as NFVIMON, which is used to monitor the health and performance of the NFV infrastructure. The NFVIMON feature enables extensive monitoring and performance data for various components of the cloud infrastructure including Cisco UCS blade and rack servers, service profiles, Nexus top of rack switches, fabric connections and also the OpenStack instances. The monitoring system is designed such that it can monitor single or multiple Pods from a single management system. NFVIMON can be enabled by extending the `setup_data.yaml` with relevant information on an existing pod, through the `reconfigure` option.

NFVIMON consists of 4 components: dispatcher, collector, Resource Manager (RM) and control-center with Cisco Zenpacks (CC). As NFVIMON is a third party software, care has been taken to make sure its integration into VIM is loosely coupled and the VIM automation only deals with installing the minimal software piece

(dispatcher) needed to monitor the pod. The installing of the other NFVIMON components (collector, Resource Manager (RM) and control-center with Cisco Zenpacks (CC)), are Cisco Advance Services led activity and those steps are outside the scope of the current install guide.

Before you Begin

Ensure that you have engaged with Cisco Advance Services on the planning and installation of the NFVIMON accessories along with its network requirements. Also, the image information of collector, Resource Manager (RM) and control-center with Cisco Zenpacks (CC) is available only through Cisco Advance Services. At a high level, have a node designated to host a pair of collector VM for each pod, and a common node to host CC and RM VMs, which can aggregate and display monitoring information from multiple pods. In terms of networking, the collectors VMs need to have 2 interfaces: an interface in br_mgmt of the VIM, and another interface that is routable, which can reach the VIM Installer REST API and the RM VMs. As the collector VM is sitting in an independent node, 4 IPs from the management network of the pod should be pre-planned and reserved. Install steps of the collector, Resource Manager (RM) and control-center with Cisco Zenpacks (CC) are Cisco Advance Services led activity.

Installation of NFVIMON Dispatcher

The dispatcher is the only component in NFVIMON offering that is managed by VIM orchestrator. While the dispatcher acts as a conduit to pass openstack information of the pod to the collectors, it is the Cisco NFVI Zenpack sitting in the CC/RM node, that gathers the node level information. To enable dispatcher as part of the VIM Install, update the setup_data with the following information:

```
#Define the PODNAME
PODNAME: <PODNAME with no space>; ensure that this is unique across all the pods
NFVIMON:
  MASTER:                # Master Section
    admin_ip: <IP address of Control Centre VM>
  COLLECTOR:            # Collector Section
management_vip: <VIP for ceilometer/dispatcher to use> #Should be unique across the VIM
Pod; Should be part of br_mgmt network
  Collector_VM_Info:
  -
    hostname: <hostname of Collector VM 1>
    password: <password_for_collector_vm1> # max length of 32
    ccuser_password: <password from master for 'ccuser' (to be used for self monitoring)>
  # max length of 32
    admin_ip: <ssh_ip_collector_vm1> # Should be part of br_api network
    management_ip: <mgmt_ip_collector_vm1> # Should be part of br_mgmt network
  -
    hostname: <hostname of Collector VM 2>
    password: <password_for_collector_vm2> # max length of 32
    ccuser_password: <password from master for 'ccuser' (to be used for self monitoring)>
  # max length of 32
    admin_ip: <ssh_ip_collector_vm2> # Should be part of br_api network
    management_ip: <mgmt_ip_collector_vm2> # Should be part of br_mgmt network
  DISPATCHER:
    rabbitmq_username: admin # Pod specific user for dispatcher module in
ceilometer-collector
```

To monitor ToR, ensure that the following TORSWITCHINFO sections are defined in the setup_data.yaml.

```
TORSWITCHINFO:
  SWITCHDETAILS:
  -
    hostname: <switch_a_hostname>: # Mandatory for NFVIMON if switch monitoring is
needed
    username: <TOR switch username> # Mandatory for NFVIMON if switch monitoring is
needed
```

```

        password: <TOR switch password> # Mandatory for NFVBENCH; Mandatory for NFVIMON
if switch monitoring is needed
        ssh_ip: <TOR switch ssh ip> # Mandatory for NFVIMON if switch monitoring is
needed
        ....
-
        hostname: <switch_b_hostname>: # Mandatory for NFVIMON if switch monitoring is
needed
        username: <TOR switch username> # Mandatory for NFVIMON if switch monitoring is
needed
        password: <TOR switch password> # Mandatory for NFVIMON if switch monitoring is
needed
        ssh_ip: <TOR switch ssh ip> # Mandatory for NFVIMON if switch monitoring is
needed
        ....

```

To initiate the integration of NFVIMON on an existing pod, copy the setupdata into a local dir and update it manually with information listed above, and then run the reconfiguration command as follows:

```

[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to include NFVIMON related
info)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>

```

**Note**

- Unconfiguration of this feature is not supported.
- NFVIMON is supported only on a pod running with Keystone v2.
- NFVIMON needs root privileges as the non-root admin keys cannot be used for monitoring.

Reconfiguring CIMC Password on an Existing Install

Cisco VIM, allows you to reconfigure the CIMC password on an existing install along with OpenStack services.

**Note**

You must have a C-series pod, up and running with Cisco to reconfigure the CIMC password.

Step 1

Update the `cimc_password` in the CIMC-COMMON section, and/or the individual `cimc_password` for each server and then run the reconfigure option provided by `Ciscovimclient`.

```

CIMC-COMMON:
  cimc_username: "admin"
  cimc_password: <"new password">
:
:
SERVERS:
:
control-server-2:

```

```
cimc_info: {'cimc_ip': '<ip_addr>',
           'cimc_username': 'admin',
           'cimc_password': '<update with new password>} # only needed if each server has specific
password
```

Step 2 To change the CIMC password for the pod, copy the setupdata into a local location and update it manually with the CIMC password as shown in the snippet above. The new password must satisfy atleast three of the following conditions:

Note Do not change CIMC password directly into the exiting /root/openstack-configs/setup_data.yaml file.

- Must contain at least one lower case letter.
- Must contain at least one upper case letter.
- Must contain at least one digit between 0 to 9.
- One of these special characters !\$#@%^_+=*&
- Your password has to be 8 to 14 characters long.

Step 3 Run the vim reconfiguration command, to post update the setup_data as follows:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
[root@mgmt1 ~]# cp <my_setup_data.yaml> <my_setup_data_original.yaml>
[root@mgmt1 ~]# vi my_setup_data.yaml (update the relevant CIMC setup_data to include LDAP info)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --cimc_password --setupfile /root/MyDir/<my_setup_data.yaml>
```

Note After successful completion of the CIMC Password, reconfigure operation triggers an auto-back when the management node auto-back recovery feature is enabled. If the CIMC Password reconfigure fails, contact Cisco TAC to recover from the failure.

Increasing Provider and Tenant VLAN Ranges

Cisco VIM, provides the flexibility of increasing the provider and tenant VLAN ranges after the post pod installation. Increasing provider and tenant VLAN ranges applies to C-series and B-series pod that is enabled with Cisco UCS Manager plugin. B-series pod running without Cisco UCS Manager plugin, cannot use this feature because of the inherent day-0 networking configuration to be done in FI.



Note You should have the tenant and provider networks enabled on the pod from day-0.

To increase provider and tenant VLAN ranges enter the TENANT_VLAN_RANGES and/or PROVIDER_VLAN_RANGES in the setup_data.yaml file and run the reconfigure command through Ciscovimclient as follows:

```
TENANT_VLAN_RANGES: old_vlan_info, new_vlan_info
or/and
PROVIDER_VLAN_RANGES: old_vlan_info, new_vlan_info
```

To change the pod, copy the setupdata into a local dir and update it manually by running the following command:

```
[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir [root@mgmt1 ~]# cd MyDir
```

Update the setup_data, by running the following command:

```
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml> [root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data with the right info)
```

Run the re-configuration command as follows:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ./ciscovimclient/ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>
```

Fernet Key Operations

Keystone fernet token format is based on the cryptographic authentication method - Fernet. Fernet is an implementation of Symmetric Key Encryption. Symmetric key encryption is a cryptographic mechanism that uses the same cryptographic key to encrypt plaintext and the same cryptographic key to decrypt ciphertext. Fernet authentication method also supports multiple keys where it takes a list of symmetric keys, performs all encryption using the first key in a list and attempts to decrypt using all the keys from that list.

The Cisco NFVI pods uses Fernet keys by default. The following operations can be carried out in Cisco NFVI pods.

To check if the fernet keys are successfully synchronized across the keystone nodes.

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim help check-fernet-keys
usage: ciscovim check-fernet-keys
```

Check whether the fernet keys are successfully synchronized across keystone nodes.

To set the fernet key frequency:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim help period-rotate-fernet-keys
usage: ciscovim period-rotate-fernet-keys <SET_PERIOD_ROTATION_FERNET_KEYS>
Set the frequency of fernet keys rotation on keystone
Positional arguments:
  <SET_PERIOD_ROTATION_FERNET_KEYS>
Frequency to set for period rotation
```

To forcefully rotate the fernet keys:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim help rotate-fernet-keys
usage: ciscovim rotate-fernet-keys
Trigger rotation of the fernet keys on keystone
```

To resync the fernet keys across the keystone nodes:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim help resync-fernet-keys
usage: ciscovim resync-fernet-keys
Resynchronize the fernet keys across all the keystone nodes
```

Managing Certificates

When TLS protection is configured for the OpenStack APIs, the two certificate files, `haproxy.pem` and `haproxy-ca.crt`, are stored in the `/root/openstack-configs/` directory. Clients running on servers outside of the deployed cloud to verify cloud authenticity need a copy of the root certificate (`haproxy-ca.crt`). If a well-known certificate authority has signed the installed certificate, no additional configuration is needed on client servers. However, if a self-signed or local CA is used, copy `haproxy-ca.crt` to each client. Following instructions specific to the client operating system or browser to install the certificate as a trusted certificate.

Alternatively, you can explicitly reference the certificate when using the OpenStack CLI by using the environment variable `OS_CACERT` or command line parameter `-cacert`.

While Cisco NFVI is operational, a daily check is made to monitor the expiration dates of the installed certificates. If certificates are not nearing expiration, an informational message is logged. As the certificate approaches expiration, an appropriate warning or critical message is logged.

```
2017-04-24T13:56:01 INFO Certificate for OpenStack Endpoints at 192.168.0.2:5000 expires
in 500 days
```

It is important to replace the certificates before they expire. After Cisco NFVI is installed, you can update the certificates by replacing the `haproxy.pem` and `haproxy-ca.crt` files and running the reconfigure command:

```
cd ~/installer-xxxx; ciscovim reconfigure
```

Reconfiguring TLS Certificates

Cisco VIM provides a way to configure TLS certificates on-demand for any reason. For Example: certificate expiration policies governing certificate management.

Reconfiguration of certificates in general is supported in the following components:

- Cisco VIM Rest API endpoints:

Steps to be performed to reconfigure certificate files are as follows:

- Copy the new key, CA root and certificate files into the `~/openstack-configs` folder under the following filenames

```
cp <new-ca-root-cert> ~/openstack-configs/mercury-ca.crt
cp <new-key-file> ~/openstack-configs/mercury.key
cp <new-cert-file> ~/openstack-configs/mercury.crt
```

- Once copied run the reconfigure steps as under:

```
cd ~/installer-xxxx/tools
./restapi.py -a reconfigure-tls
```

- OpenStack API endpoints

Steps to be performed to reconfigure certificate files are as follows:

- Copy the new key, CA root and certificate files into the `~/openstack-configs` folder under the following filenames

```
cp <new-ca-root-cert> ~/openstack-configs/haproxy-ca.crt
cp <new-cert-file> ~/openstack-configs/haproxy.pem
```

- Once copied run the reconfigure steps as follows:

```
cd ~/installer-xxxx; ciscovim reconfigure
```

- SwiftStack Service through Horizon and CinderBackup Service.
 - Reconfiguring TLS certificates for SwiftStack mainly involves client side certificate updates. The CA root certificate in both these cases is updated for components within OpenStack that are clients of the SwiftStack service in general.
 - Copy the new CA root certificate to the ~/openstack-configs folder and run reconfigure.

```
cp <new-ca-root-cert> ~/openstack-configs/haproxy-ca.crt
cd ~/installer-xxxx; ciscovim reconfigure
```

- Logstash service and Fluentd (client-side certificates).
 - For the Logstash service on the management node, both the key and certificate file are reconfigured as part of the reconfigure operation.
 - For the Fluentd service on the controllers, compute and storage nodes, the certificate file are reconfigured as part of the reconfigure operation.
 - Copy of the key and certificate files to the ~/openstack-configs folder on the management node and run reconfigure operation.

```
cp <new-key-file> ~/openstack-configs/logstash-forwarder.key
cp <new-cert-file> ~/openstack-configs/logstash-forwarder.crt
cd ~/installer-xxxx; ciscovim reconfigure
```

Enabling Keystone v3 on an Existing Install

To continue enhancing our security portfolio, and multi-tenancy with the use of domains, Keystone v3 support has been added in Cisco VIM from an authentication end-point. It should be noted that Keystone v2 and v3 are mutually exclusive. The administrator has to decide during install time the authentication end-point version to go with. By default, VIM orchestrator picks keystone v2 as the authentication end-point. So one can enable Keystonev3 as an install option on day-0 (see 2.4 CiscoVIM install guide), or enable it as a reconfigure option after the pod is installed. To enable Keystone v3 after the pod is installed, one needs to define the following under the optional service section in the setup_data.yaml file.

```
# Optional Services:
OPTIONAL_SERVICE_LIST:
- keystonev3
```

To initiate the integration of Keystone v3 on an existing pod, copy the setupdata into a local dir and update it manually, then run reconfiguration command as follows:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to include keystone v3 info)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim --setupfile ~/MyDir/<my_setup_data.yaml> reconfigure
```

It should be noted that un-configuration of this feature is not supported today. Additionally, re-versioning Keystone API from v3 to v2 is also not supported.

LDAP/AD support with Keystone v3

With the introduction of KeystoneV3, the openstack service authentication can now be delegated to an external LDAP/AD server. In Cisco VIM, this feature has been introduced optionally if the authorization is done by Keystone v3. Just like Keystonev3, this feature can be enabled on an existing pod running Cisco VIM. To avail of this feature post pod deployment, the setup_data needs to be augmented with the following information during the installation of the pod.

An important pre-requisite for enabling AD/LDAP integration is that the AD/LDAP endpoint MUST be reachable from all the Controller nodes that run OpenStack Keystone Identity Service.

```
LDAP:
  domain: <Domain specific name>
  user_objectclass: <objectClass for Users> # e.g organizationalPerson
  group_objectclass: <objectClass for Groups> # e.g. groupOfNames
  user_tree_dn: '<DN tree for Users>' # e.g. 'ou=Users,dc=cisco,dc=com'
  group_tree_dn: '<DN tree for Groups>' # e.g. 'ou=Groups,dc=cisco,dc=com'
  suffix: '<suffix for DN>' # e.g. 'dc=cisco,dc=com'
  url: '<ldap:// host:port>' # e.g. 'ldap://172.26.233.104:389'
or
url: '<ldaps|ldap>://[<ip6-address>]:[port] '
e.g.ldap://[2001:420:293:2487:d1ca:67dc:94b1:7e6c]:389 ---> note the mandatory "[. ]"
around the ipv6 address
  user: '<DN of bind user>' # e.g. 'dc=admin,dc=cisco,dc=com', Optional but need to added
along with password.
  password: <password> # e.g. password of bind user, Optional but need to be added along
with DN of bind user.

user_filter = (memberOf=CN=os-users,OU=OS-Groups,DC=mercury,DC=local)
user_id_attribute = sAMAccountName
user_name_attribute = sAMAccountName
user_mail_attribute = mail # Optional
group_tree_dn = ou=OS-Groups,dc=mercury,dc=local
group_name_attribute = sAMAccountName
group_filter: '(&(objectClass=group)(|(cn=server-ops)(cn=admin)))' # Optional
group_member_attribute: memberId # Optional
group_id_attribute: gidNumber # Optional
group_members_are_ids: True # Optional
chase_referrals: <True or False> # Optional
```

Condition for LDAP user and password parameters are as follows:

- 1 – Can be optional
- 2 – Should be mutually inclusive
- 3 – If defined, it cannot be empty

To initiate the integration of LDAP with Keystone v3 on an existing pod, copy the setupdata into a local dir and update it manually with the relevant LDAP and Keystone v3 (if absent from before) configuration, then run reconfiguration command as follows:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to include LDAP info)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>
```

The reconfigure feature supports a full or partial reconfiguration of the LDAP integration service.



Note All the parameters within the LDAP stanza are configurable with the exception of the domain parameter.

Integrating identity with LDAP over TLS: The automation supports keystone integration with LDAP over TLS. In order to enable TLS, the CA root certificate must be presented as part of the /root/openstack-configs/haproxy-ca.crt file. The url parameter within the LDAP stanza must be set to ldaps.

Additionally, the url parameter supports the following format: url: '<ldaps | ldap>://<FQDN | IP-Address>:[port]'

The protocol can be one of the following: ldap for non-ssl and ldaps when TLS has to be enabled.

The ldap host can be a fully-qualified domain name (FQDN) or an IPv4 or v6 Address depending on how the SSL certificates are generated. .

The port number is optional and if not provided assumes that the ldap services are running on the default ports. For Example: 389 for non-ssl and 636 for ssl. However, if these are not the defaults, then the non-standard port numbers must be provided. Except for the domain, all other item values can be changed via the 'reconfigure' option.

Moving Netapp transport from http to https

For deployments, with NETAPP running over http protocol you can migrate it to https, post-deployment.

Step 1 To initiate the change, copy the setupdata into a local dir and update it manually the name/value pair in the netapp section:

```
NETAPP:
...
...
server_port: 443
transport_type: https
...
netapp_cert_file: <root ca path for netapp cluster only if protocol is https>
```

Step 2 Execute the following commands to update the netapp section:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir [root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to netapp section as listed above)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>
```

Replacing ACI Controller in Cisco VIM

The Opflex ML2 plugin (in Unified mode) integrated with Cisco VIM manages the tenant VLANs dynamically, as VMs come and go in the cloud. In addition, we support an administrator driven automated workflow to provision the provider networks. This feature is supported on a C-series based Fullon or Micropod running with Cisco VIC 1227 and Intel NIC x710 with redundancy at NIC level. While the integration of ACI into Cisco VIM is a day-0 activity, Cisco VIM supports the replacement of the ACI controller in the ACI cluster and the expansion of the leaf switches to increase the fabric.

Step 1 To update the `setup_data`, follow the below steps:

```

APICINFO:
apic_hosts: '<ip1|host1>:[port], <ip2|host2>:[port], <ip3|host3>:[port]\'
# max of 3, min of 1, not 2; reconfigurable

```

Since the APIC manages the Leaf switches, its mandatory to define the new Leaf switches (in pairs) in the following format:

```

TORSWITCHINFO: (mandatory)

SWITCHDETAILS:
:
:
-
hostname: <leaf-hostname-1>
vpc_peer_keepalive: <leaf-hostname-2>
vpc_domain: 1 # Must be unique across pairs
br_mgmt_port_info: 'eth1/27' # br_mgmt_* attributes must exist on at least one pair
br_mgmt_vlan_info: '3401'
node_id: <int> # unique across switches
-
hostname: <leaf-hostname-2>
vpc_peer_keepalive: <leaf-hostname-1>
vpc_domain: 1
br_mgmt_port_info: 'eth1/27' # br_mgmt_* attributes must exist on at least one pair
br_mgmt_vlan_info: '3401'
node_id: <int> # unique across switches

```

Step 2 To initiate the change in ACI config on an existing pod, copy the setupdata into a local dir and update it manually with the relevant `apic_hosts` and/or new TORSWITCH information, then run reconfiguration commands follows:

```

[root@mgmt1 ~]# cd /root/ [root@mgmt1 ~]# mkdir MyDir [root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml> [root@mgmt1 ~]# vi
my_setup_data.yaml (update the setup_data to include ACI info)
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>

```

Hardening Cisco VIM Deployment

If you want to harden the Cisco VIM deployment, set up the firewalls ahead of the external interfaces.

The following tables provide information about the expected traffic from the management interfaces of Cisco VIM.

Table 12: Management Nodes

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
br_api	incoming	HTTPS	TCP	8445	RestAPI	
br_api	incoming	HTTPS	TCP	8008	RestAPI logs	

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
br_api	incoming	HTTPS	TCP	9000	Unified Management UI	
br_api	incoming	HTTPS	TCP	5601	Kibana	
br_api	incoming	SSH	TCP	22	SSH	
br_api	incoming	HTTPS	TCP	3000	Grafana	Technical preview
br_api	outgoing	NTP	UDP	123	NTP	
br_api	outgoing	DNS	UDP	53	DNS	
br_api	outgoing	Syslog	UDP	514	Syslog	User configurable. Default value is 514.
br_mgmt	incoming	HTTP	TCP	7081	Fluentd-aggr	From all nodes to mgmt node
localhost	outgoing	HTTP	TCP	9090	Prometheus	Technical preview
localhost	outgoing	HTTP	TCP	9093	Alertmanager	Technical preview
localhost	incoming/outgoing	HTTP	TCP	1162	SMCMMON	Technical preview
br_api	incoming	SNMP	UDP	162	SNMP	Technical preview. Userdefined. Default value is 162
br_api	incoming	HTTP	TCP	22	SERVER_MON	Technical preview; from CIMC of the UCS servers.
br_api	incoming	LDAP	TCP	389	LDAP	Default: 389 or defined in setup_data
br_api	incoming	LDAPS	TCP	636	LDAPS	Default: 636 or defined in setup_data

Table 13: Controller Nodes

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
external_lb_vip	incoming	HTTP	TCP	80	Redirects to 443	
external_lb_vip	incoming	HTTPS	TCP	443	Horizon	
external_lb_vip	incoming	HTTPS	TCP	8774	Nova	
external_lb_vip	incoming	HTTPS	TCP	6080	NovaNoVNC Proxy	
external_lb_vip	incoming	HTTPS	TCP	9696	Neutron	
external_lb_vip	incoming	HTTPS	TCP	8776	Cinder	
external_lb_vip	incoming	HTTPS	TCP	9292	Galance	
external_lb_vip	incoming	HTTPS	TCP	8000	Heat	
external_lb_vip	incoming	HTTPS	TCP	8004	Heat	
external_lb_vip	incoming	HTTPS	TCP	9999	Cloudpulse	
external_lb_vip	incoming	HTTPS	TCP	8777	Ceilometer	
external_lb_vip	incoming	HTTPS	TCP	8778	Placement	
external_lb_vip	incoming	HTTPS	TCP	5000	Keystone	
br_mgmt	incoming	HTTP	TCP	156272	RabbitMQ monitoring	From management node only
br_mgmt	incoming	LDAP	TCP	389	LDAP	Default: 389 or defined in setup_data
br_mgmt	incoming	LDAPS	TCP	636	LDAPS	Default: 636 or defined in setup_data
br_mgmt	outgoing	HTTP	TCP	7081	Fluentd	To management node

Table 14: Cisco VIM Software Hub Server Node

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
br_public	outgoing	NTP	UDP	123	NTP	

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
br_public	incoming	HTTPS	TCP	443	HTTPD	Browsing artifacts on a web browser
br_private	incoming	HTTPS	TCP	8441	HTTPD	Reverse proxy for docker registry
br_public	incoming	SSH	TCP	22	SSH	

Table 15: Unified Management Node

Interface	Direction	Protocol	UDP/TCP	Port	Application	Note
br_api	outgoing	HTTPS	TCP	8445	Unified Management	Connect to Cisco VIM management node RestAPI
br_api	incoming	HTTPS	TCP	9000	HTTPD	UI
br_api	incoming	SSH	TCP	22	SSH	

Cisco VIM Monitor Alerting Rules Customization

Cisco VIM monitor is deployed with a set of built-in alerting rules that cover the most important error conditions that can occur in the pod. You can view the alerts from the Grafana user interface or Alerting dashboard or send them optionally to a number of supported receivers.

After deployment, the pod administrators can customize the alerting rules based on their requirements.

Alerting Rules Customization

The alerting rules define how alerts should be triggered based on conditional expressions on any available metric. For example, you can trigger an alert when any performance metric such as CPU usage, network throughput or disk usage reaches certain threshold.

You can add new alerting rules and modify or delete the pre-built existing alerting rules by following the below steps:

1. Create a custom alerting rule configuration file named `custom_alerting_rules.yml` under the management node `openstack-configs` directory.
2. Add the new rules, modified rules and deleted rules in that file using your favorite editor (see the file format below)
3. Verify that the custom alerting rule file is valid using a provided tool.
4. Once validated, issue a standard reconfiguration using the `ciscovim cli`.

Custom Alerting Rule File Format

The `custom_alerting_rules.yml` file must follow the format defined in this section. This format is identical to the one used by the Prometheus configuration file, with a few additional semantic extensions to support deletion and modification of pre-built existing rules.

General Format

The group entry contains a list of groups identified by (`group_name`), where each group can include one or more rules. Use the labels to determine the severity and other snmp trap attributes.

Following are the limitations to set labels:

- `severity`, `snmp_fault_code`, and `snmp_fault_severity` must be set to one of the values specified in the example below.
- `snmp_fault_source` should indicate the metric used in the alert expression
- `snmp_node` must not be changed.
- `snmp_podid` must be same as the pod name specified in `setup_data.yml`

```
groups:
- name: {group_name}
  rules:
  - alert: {alert_name}
    annotations:
      description: {alert_description}
      summary: {alert_summary}
    expr: {alert_expression}
    for: {pending_time}
    labels:
      severity: {informational/warning/critical}
      snmp_fault_code:
{other/resourceUsage/resourceThreshold/serviceFailure/hardwareFailure/networkConnectivity}
      snmp_fault_severity: {emergency/critical/major/alert/informational}
      snmp_fault_source: {fault_source}
      snmp_node: '{{ $labels.instance }}'
      snmp_podid: {pod_id}
```

Addition of Alerting Rules

Any alert rule specified under a group other than **change-rules** group or **delete-rules** group is populated to the merged output file. You can prioritize the custom rules over the pre-existing rules if there are two alerts with the same name in both the files, such that only the one from custom file is kept as a result of the merge.

Modification of Alerting Rules

You can modify any pre-existing rule using the following syntax:

```
groups:
- name: change-rules
  rules:
  - alert: {alert_name}
    expr: {new_alert_expression}
    annotations:
      summary: {new_alert_summary}
```

The above merge script finds only the group named **change-rules** and modifies the expression and/or summary of the corresponding alert.

If the alert to be changed does not exist, it will not be created and no changes are performed.

Deletion of Alerting Rule

You can delete any built-in rule using the following construct:

```
groups:
- name: delete-rules
  rules:
  - alert: {alert_name/regular_expression}
```

The above merge script finds only the group named **delete-rules** and deletes the pre-existing rules that match the alert name or regular expressions.

If the alert to be deleted does not exist, no changes are performed.

Example

The following custom configuration file includes examples of new alerting rule, modified alerting rule and deleted alerting rules:

```
groups:
- name: cpu
  rules:
  - alert: cpu_idle
    annotations:
      description: CPU idle usage is too high - resources under-utilized
      summary: CPU idle too high
    expr: cpu_usage_idle > 80
    for: 5m
    labels:
      severity: informational
      snmp_fault_code: resourceUsage
      snmp_fault_severity: informational
      snmp_fault_source: cpu_usage_idle
      snmp_node: '{{ $labels.instance }}'
      snmp_podid: pod7
  - alert: cpu_iowait
    annotations:
      description: CPU iowait usage is too high
      summary: CPU iowait too high
    expr: cpu_usage_iowait > 10
    for: 3m
    labels:
      severity: warning
      snmp_fault_code: resourceUsage
      snmp_fault_severity: alert
      snmp_fault_source: cpu_usage_iowait
      snmp_node: '{{ $labels.instance }}'
      snmp_podid: pod7
- name: change-rules
  rules:
  - alert: disk_used_percent
    expr: disk_used_percent > 99
    annotations:
      summary: Disk used > 99%
  - alert: reboot
    annotations:
```

```

    summary: Server rebooted
  - alert: system_n_users
    expr: system_n_users > 10
- name: delete-rules
  rules:
  - alert: disk_filling_up_in_4h
  - alert: mem.*

```

Validation Script

Validate any custom configuration file prior to reconfiguration, by executing the following CLI command from any location on the management node:

```
check_alerting_rules (no additional parameters are required)
```

The validation script uses the prometheus "promtool", but skips some of its checks to allow the modification and deletion of rules. It also checks if the provided SNMP severities and fault codes are supported. When no custom file is present, the expected location is mentioned in the output.

Output of validation script in case of success

```

# check_alerting_rules
check_promtool.py: checking /prometheus/custom_alerting_rules.yml
check_promtool.py: success:
check_promtool.py: regular expressions for rules to be deleted: 2
check_promtool.py: rules to be changed: 3
check_promtool.py: rules to be added: 2

```

Output of validation script in case of failure

```

# check_alerting_rules
check_promtool.py: checking custom-rules.yml
check_promtool.py: failure:
check_promtool.py: group "new_group", rule 0, "new_alert": could not parse expression:
parse error at char 8:
    could not parse remaining input "@$"..."
check_promtool.py: group "new_group2", rule 0, "new_alert_3": could not parse expression:
parse error at char 7:
    bad number or duration syntax: "1"
# check_alerting_rules
check_promtool.py: checking /prometheus/custom_alerting_rules.yml
check_promtool.py: failure:
check_promtool.py: line 36: field custom_field not found in type rulefmt.Rule

```

Alert Manager and Receiver Customization

The Alert Manager component in Cisco VIM Monitor is in charge of routing, grouping, and inhibiting alerts that are sent by the Prometheus alert rules engine to the appropriate receivers.

The default configuration in Cisco VIM Monitor allows every alert to be forwarded as SNMP traps to the SNMP managers through SNMP agent if enabled in the Cisco VIM configuration file.

After deployment, you can add custom alert routes, alert grouping, alert inhibitions and receivers by following the below steps:

1. Create a custom alert manager rules configuration file named `alertmanager_custom_config.yml`.

2. Edit the content using your favorite editor (see format below).
3. Copy that file to the management node `openstack-configs` directory.
4. Verify that the custom alerting rules file is valid using a provided tool.
5. Once validated, issue a standard reconfiguration using the `ciscovim cli`.

Supported Receivers

The Alert Manager supports the following list of receivers:

- webhook
- pagerduty
- e-mail
- pushover
- wechat
- opsgenie
- victorops

You can find the configuration details for each receiver in the Prometheus Alert Manager documentation (publicly available online).

Alert Manager Custom Configuration File Format

General Format

The following listing shows the general format of the alert manager configuration file. Most custom configuration files should only include a small subset of the available options.

```
global:
  # ResolveTimeout is the time after which an alert is declared resolved
  # if it has not been updated.
  [ resolve_timeout: <duration> | default = 5m ]

  # The default SMTP From header field.
  [ smtp_from: <tmpl_string> ]
  # The default SMTP smarthost used for sending emails, including port number.
  # Port number usually is 25, or 587 for SMTP over TLS (sometimes referred to as STARTTLS).
  # Example: smtp.example.org:587
  [ smtp_smarthost: <string> ]
  # The default hostname to identify to the SMTP server.
  [ smtp_hello: <string> | default = "localhost" ]
  [ smtp_auth_username: <string> ]
  # SMTP Auth using LOGIN and PLAIN.
  [ smtp_auth_password: <secret> ]
  # SMTP Auth using PLAIN.
  [ smtp_auth_identity: <string> ]
  # SMTP Auth using CRAM-MD5.
  [ smtp_auth_secret: <secret> ]
  # The default SMTP TLS requirement.
  [ smtp_require_tls: <bool> | default = true ]
```

```

# The API URL to use for Slack notifications.
[ slack_api_url: <secret> ]
[ victorops_api_key: <secret> ]
[ victorops_api_url: <string> | default =
"https://alert.victorops.com/integrations/generic/20131114/alert/" ]
[ pagerduty_url: <string> | default = "https://events.pagerduty.com/v2/enqueue" ]
[ opsgenie_api_key: <secret> ]
[ opsgenie_api_url: <string> | default = "https://api.opsgenie.com/" ]
[ hipchat_api_url: <string> | default = "https://api.hipchat.com/" ]
[ hipchat_auth_token: <secret> ]
[ wechat_api_url: <string> | default = "https://qyapi.weixin.qq.com/cgi-bin/" ]
[ wechat_api_secret: <secret> ]
[ wechat_api_corp_id: <string> ]

# The default HTTP client configuration
[ http_config: <http_config> ]

# Files from which custom notification template definitions are read.
# The last component may use a wildcard matcher, e.g. 'templates/*.tmpl'.
templates:
  [ - <filepath> ... ]

# The root node of the routing tree.
route: <route>

# A list of notification receivers.
receivers:
  - <receiver> ...

# A list of inhibition rules.
inhibit_rules:
  [ - <inhibit_rule> ... ]

```

Default Built-in Configuration File

The default configuration file defines a generic route for all alerts to the SNMP agent running on the management node.

```

:
global:
  resolve_timeout: 5m

route:
  group_by: ['alertname', 'cluster', 'service']
  group_wait: 30s
  group_interval: 5m
  repeat_interval: 8737h

# A default receiver
receiver: snmp

receivers:
- name: 'snmp'
  webhook_configs:
  - send_resolved: true
    url: 'http://localhost:1161/alarms'

```

SNMP Trap Receivers

You can send the SNMP traps to SNMP managers enabled in the Cisco VIM configuration file `setup_data.yaml`. Refer to the corresponding section in the documentation for more information.

Example: inhibit (mute) alerts matching a set of labels

This is the general format for inhibit alerts. You can set a regex to match both the source and target alerts and to filter the alerts per label name.

```
# Matchers that have to be fulfilled in the alerts to be muted.
target_match:
  [ <labelname>: <labelvalue>, ... ]
target_match_re:
  [ <labelname>: <regex>, ... ]

# Matchers for which one or more alerts have to exist for the
# inhibition to take effect.
source_match:
  [ <labelname>: <labelvalue>, ... ]
source_match_re:
  [ <labelname>: <regex>, ... ]

# Labels that must have an equal value in the source and target
# alert for the inhibition to take effect.
[ equal: '[' <labelname>, ... ']' ]
```

This is an example of inhibit all alerts `docker_container` in containers that are down (which has the alert `docker_container_down` on).

```
inhibit_rules:
- target_match_re:
    alertname: 'docker_container.+
  source_match:
    alertname: 'docker_container_down'
    equal: ['job', 'instance']
```

Example: Inhibit alerts if other alerts are active

The below configuration inhibits all warning alerts if the relative alert is critical.

```
# We use this to mute any warning-level notifications if the same alert is
# already critical.

inhibit_rules:
- source_match:
    severity: 'critical'
  target_match:
    severity: 'warning'
  # Apply inhibition if the alertname is the same.
  equal: ['alertname', 'cluster', 'service']
```

Validation Script

When a new configuration is set, execute the `check_alertmanager_config` from anywhere in the management node and ensure that you get a **SUCCESS** in the output from the configuration POV.

```
> check_alertmanager_config
Checking '/var/lib/cvim_mon/alertmanager_custom_config.yml' SUCCESS
Found:
- global config
- route
- 0 inhibit rules
- 1 receivers
- 0 templates
```




CHAPTER 5

Managing Cisco NFVI Storage

This chapter describes basic architectural concepts that will help you understand the Cisco NFVI data storage architecture and data flow. It also provides techniques you can use to monitor the storage cluster health and the health of all systems that depend on it

- [Cisco NFVI Storage Architecture, on page 153](#)
- [Verifying and Displaying Ceph Storage Pools, on page 154](#)
- [Checking the Storage Cluster Health, on page 155](#)
- [Checking Glance Connectivity, on page 156](#)
- [Verifying Glance and Ceph Monitor Keyrings, on page 157](#)
- [Verifying Glance Image ID on Ceph, on page 158](#)
- [Checking Cinder Connectivity, on page 158](#)
- [Verifying Cinder and Ceph Monitor Keyrings, on page 159](#)
- [Verifying the Cinder Volume ID on Ceph, on page 160](#)
- [Checking Nova Connectivity, on page 161](#)
- [Verifying Nova and Ceph Monitor Keyrings, on page 161](#)
- [Verifying Nova Instance ID, on page 162](#)
- [Displaying Docker Disk Space Usage, on page 163](#)
- [Reconfiguring SwiftStack Integration, on page 164](#)
- [Reconfiguring Administrator Source Networks, on page 165](#)
- [Password Reset for Cisco VIM Management Node, on page 166](#)


Cisco NFVI Storage Architecture

OpenStack has multiple storage back ends. Cisco NFVI uses the Ceph back end. Ceph supports both block and object storage and is therefore used to store VM images and volumes that can be attached to VMs. Multiple OpenStack services that depend on the storage backend include:

- Glance (OpenStack image service)—Uses Ceph to store images.
- Cinder (OpenStack storage service)—Uses Ceph to create volumes that can be attached to VMs.
- Nova (OpenStack compute service)—Uses Ceph to connect to the volumes created by Cinder.

The following figure shows the Cisco NFVI storage architecture component model.

Figure 15: Cisco NFVI Storage Architecture



41-1023

Verifying and Displaying Ceph Storage Pools

Ceph is configured with four independent pools: images, volumes, vms, and backups. (A default rbd pool is used internally.) Each Ceph pool is mapped to an OpenStack service. The Glance service stores data in the images pool, and the Cinder service stores data in the volumes pool. The Nova service can use the vms pool to boot ephemeral disks directly from the Ceph cluster depending on how the NOVA_BOOT_FROM option in the `~/openstack-configs/setup_data.yaml` was configured prior to Cisco NFVI installation. If NOVA_BOOT_FROM is set to ceph before you run the Cisco NFVI installation, the Nova service boot up from the Ceph vms pool. By default, NOVA_BOOT_FROM is set to local, which means that all VM ephemeral disks are stored as files in the compute nodes. Changing this option after installation does not affect the use of the vms pool for ephemeral disks.

The Glance, Cinder, and Nova OpenStack services depend on the Ceph cluster for backend storage. Therefore, they need IP connectivity to the controller nodes. The default port used to connect Glance, Cinder, and Nova to the Ceph cluster is 6789. Authentication through cephx is required, which means authentication tokens, called keyrings, must be deployed to the OpenStack components for authentication.

To verify and display the Cisco NFVI Ceph storage pools:

-
- Step 1** Launch a SSH session to a controller node, for example:
- ```
[root@management-server-cisco ~]# ssh root@controller_server-1
```
- Step 2** Navigate to the Ceph Monitor container:
- ```
[root@controller_server-1 ~]# cephmon
```

Step 3 List the Ceph pools:

```
cephmon_4612 [root@controller_server-1 ~]# ceph osd lspools
0 rbd,1 images,2 volumes,3 vms,4 backups,
```

Step 4 List the images pool content:

```
cephmon_4612 [ceph@controller_server-1 /]$ rbd list images
a4963d51-d3b7-4b17-bf1e-2ebac07e1593
```

Checking the Storage Cluster Health

Cisco recommends that you perform a few verifications to determine whether the Ceph cluster is healthy and is connected to the Glance, Cinder, and Nova OpenStack services, which have Ceph cluster dependencies. The first task to check the health of the cluster itself by completing the following steps:

Step 1 From the Cisco NFVI management node, launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 2 Navigate to the Ceph Monitor container:

```
[root@controller_server-1 ~]# cephmon
```

Step 3 Check the Ceph cluster status:

```
cephmon_4612 [ceph@controller_server-1 ceph]$ ceph status
```

Sample response:

```
cluster dbc29438-d3e0-4e0c-852b-170aaf4bd935
health HEALTH_OK
monmap e1: 3 mons at {ceph-controller_server-1=20.0.0.7:6789/0,
ceph-controller_server-2=20.0.0.6:6789/0,ceph-controller_server-3=20.0.0.5:6789/0}
election epoch 8, quorum 0,1,2 ceph-controller_server-3,
ceph-controller_server-2,ceph-controller_server-1
osdmap e252: 25 osds: 25 up, 25 in
pgmap v593: 1024 pgs, 5 pools, 406 MB data, 57 objects
2341 MB used, 61525 GB / 61527 GB avail
1024 active+clean
```

This example displays three monitors, all in good health, and 25 object storage devices (OSDs). All OSDs show as up and in the cluster.

Step 4 To see a full listing of all OSDs sorted by storage node, enter:

```
cephmon_4612 [ceph@controller_server-1 ceph]$ ceph osd tree
```

Sample response:

ID	WEIGHT	TYPE	NAME	UP/DOWN	REWEIGHT	PRIMARY-AFFINITY
-1	60.18979	root	default			
-2	18.96994	host	controller_server-2			
1	2.70999	osd	osd.1	up	1.00000	1.00000
5	2.70999	osd	osd.5	up	1.00000	1.00000
6	2.70999	osd	osd.6	up	1.00000	1.00000

```

11 2.70999          osd.11          up 1.00000      1.00000
12 2.70999          osd.12          up 1.00000      1.00000
17 2.70999          osd.17          up 1.00000      1.00000
20 2.70999          osd.20          up 1.00000      1.00000
-3 18.96994        host controller_server-1
 0 2.70999          osd.0           up 1.00000      1.00000
 4 2.70999          osd.4           up 1.00000      1.00000
 8 2.70999          osd.8           up 1.00000      1.00000
10 2.70999          osd.10          up 1.00000      1.00000
13 2.70999          osd.13          up 1.00000      1.00000
16 2.70999          osd.16          up 1.00000      1.00000
18 2.70999          osd.18          up 1.00000      1.00000
-4 18.96994        host controller_server-3
 2 2.70999          osd.2           up 1.00000      1.00000
 3 2.70999          osd.3           up 1.00000      1.00000
 7 2.70999          osd.7           up 1.00000      1.00000
 9 2.70999          osd.9           up 1.00000      1.00000
14 2.70999          osd.14          up 1.00000      1.00000
15 2.70999          osd.15          up 1.00000      1.00000
19 2.70999          osd.19          up 1.00000      1.00000
-5 3.27997         host controller_server-4
21 0.81999          osd.21          up 1.00000      1.00000
22 0.81999          osd.22          up 1.00000      1.00000
23 0.81999          osd.23          up 1.00000      1.00000
24 0.81999          osd.24          up 1.00000      1.00000

```

What to do next

After you verify the Ceph cluster is in good health, check that the individual OpenStack components have connectivity and their authentication tokens—keyrings—match the Ceph Monitor keyrings. The following procedures show how to check the connectivity and authentication between Ceph and Glance, Ceph and Cinder, and Ceph and Nova.

Checking Glance Connectivity

The Glance API container must be connected to the Cisco NFVI controller nodes. Complete the following steps to verify the Glance to controller node connectivity:

Step 1 From the management node, examine the IP addresses of controller node:

```
[root@management-server-cisco ~]# cat /root/openstack-configs/mercury_servers_info
```

Step 2 From the management node, launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 3 Navigate to the Glance API container:

```
[root@controller_server-1 ~]# glanceapi
```

Step 4 Check the Glance API container connectivity to the storage IP address of the controller node different from the one entered in Step 2:

```
glanceapi_4612 [glance@controller_server-1 /]$ curl <storage_ip_of_another_controller>:6789
glanceapi_4612 [glance@controller_server-1 /]$ curl controller_server-2:6789 ceph v027?
```

If the connection is successful, you can see the message “ceph v027?” and do Ctrl-C to terminate the connection:

If the connection is not successful, you can see the following message:

```
glanceapi_4612 [glance@controller_server-1 /]$ curl 7.0.0.16:6789 curl: (7)
Failed connect to controller_server-2:6789; Connection refused
```

The above message indicates that the Ceph monitor running on the target controller node controller_server-2 is not listening on the specified port or there is no route to it from the Glance API container.

Checking one controller node should be enough to ensure one connection path available for the Glance API. However, because Cisco NFVI controller nodes run as part of an HA cluster, you should run Step 3 above targeting all the controller nodes in the Cisco NFVI pod.

What to do next

After you verify the Glance API connectivity to all Cisco NFVI controller nodes, check the Glance keyring to ensure it matches the Ceph monitor keyring.

Verifying Glance and Ceph Monitor Keyrings

Complete the following steps to verify the Glance API keyring matches the Ceph Monitor keyring.

Step 1 Launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 2 Navigate to the Glance API container:

```
[root@controller_server-1 ~]# glanceapi
```

Step 3 Check the Glance keyring content, for example:

```
glanceapi_4612 [glance@controller_server-1 /]$ cat /etc/ceph/client.glance.keyring
[client.glance]
key = AQA/pY1XBAnHMBAAeS+0Wmh9PLZe1XqkIW/p0A==
```

Step 4 On management node, check the CEPH cluster UUID

```
[root@management-server-cisco ~]# cat /root/openstack-configs/ceph/fetch/ceph_cluster_uuid.conf
0e96e7f2-8175-44b3-ac1a-4f62de12ab9e
```

Step 5 Display the Ceph Glance keyring content:

```
[root@management-server-cisco ~]# cat
/root/openstack-configs/ceph/fetch/0e96e7f2-8175-44b3-ac1a-4f62de12ab9e/etc/ceph/ceph.client.glance.keyring

[mon.]

key = AQA/pY1XBAnHMBAAeS+0Wmh9PLZe1XqkIW/p0A==
```

Verify the keyring matches the Glance API keyring displayed in Step 3.

What to do next

A final check to ensure that Ceph and Glance are connected is to actually import a Glance image using Horizon or the Glance CLI. After you import an image, compare the IDs seen by Glance and by Ceph. They should match, indicating Ceph is handling the backend for Glance.

Verifying Glance Image ID on Ceph

The following steps verify Ceph is properly handling new Glance images by checking that the image ID for a new Glance image is the same as the image ID displayed in Ceph.

Step 1 From the management node, load the OpenStack authentication variables:

```
[root@management-server-cisco ~]# source ~/openstack-configs/openrc
```

Step 2 Import any Glance image. In the example below, a RHEL 7.1 qcow2 image is used.

```
[root@management-server-cisco images]# openstack image create
"rhel" --disk-format qcow2 --container-format bare --file rhel-guest-image-7.1-20150224.0.x86_64.qcow2
```

Step 3 List the Glance images:

```
[root@management-server-cisco images]# openstack image list | grep rhel
| a4963d51-d3b7-4b17-bf1e-2ebac07e1593 | rhel
```

Step 4 Navigate to the Ceph Monitor container:

```
[root@controller_server-1 ~]# cephmon
```

Step 5 Display the contents of the Ceph images pool:

```
cephmon_4612 [ceph@controller_server-1 ceph]$ rbd list images | grep
a4963d51-d3b7-4b17-bf1e-2ebac07e1593
a4963d51-d3b7-4b17-bf1e-2ebac07e1593
```

Step 6 Verify that the Glance image ID displayed in Step 3 matches the image ID displayed by Ceph.

Checking Cinder Connectivity

The Cinder volume container must have connectivity to the Cisco NFVI controller nodes. Complete the following steps to verify Cinder volume has connectivity to the controller nodes:

Step 1 From the management node, examine the IP addresses of controller node:

```
[root@management-server-cisco ~]# cat /root/openstack-configs/mercury_servers_info
```

Step 2 From the management node, launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 3 Navigate to the Cinder volume container:

```
[root@controller_server-1 ~]# cindervolume
```

Step 4 Check the Cinder volume container connectivity to the storage IP address of the controller node different from the one entered in Step 1:

```
cindervolume_4612 [cinder@controller_server-1 /]$ curl 7.0.0.16:6789
```

If the connection is successful, you can see the following message:

```
cindervolume_4612 [cinder@controller_server-1 /]$ curl controller_server-2:6789 ceph v027?
```

If the connection is not successful, you can see the following message:

```
cindervolume_4612 [cinder@controller_server-1 /]$ curl 7.0.0.16:6789 curl: (7) Failed connect to controller_server-2:6789; Connection refused
```

The above message indicates that the Ceph monitor running on the target controller node controller_server-2 is not listening on the specified port or there is no route to it from the Cinder volume container.

Checking one controller node should be enough to ensure one connection path is available for the Cinder volume. However, because Cisco NFVI controller nodes run as part of an HA cluster, repeat Step 3 targeting all the controller nodes in the Cisco NFVI pod.

What to do next

After you verify the Cinder volume connectivity to all Cisco NFVI controller nodes, check the Cinder keyring to ensure it matches the Ceph monitor keyring.

Verifying Cinder and Ceph Monitor Keyrings

Complete the following steps to verify the Cinder volume keyring matches the Ceph Monitor keyring.

Step 1 From the management node, launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 2 Navigate to the Cinder volume container:

```
[root@controller_server-1 ~]# cindervolume
```

Step 3 Check the Cinder keyring content, for example:

```
cindervolume_4612 [cinder@controller_server-1 /]$ cat /etc/ceph/client.cinder.keyring
[client.cinder]
key = AQA/pY1XBAnHMBAAeS+0Wmh9PLZelXqkIW/p0A==
```

Step 4 On management node, check the CEPH cluster UUID:

```
[root@management-server-cisco ~]# cat /root/openstack-configs/ceph/fetch/ceph_cluster_uuid.conf
0e96e7f2-8175-44b3-ac1a-4f62de12ab9e
```

Step 5 Display the Ceph Cinder keyring content:

```
[root@management-server-cisco ~]# cat
/root/openstack-configs/ceph/fetch/0e96e7f2-8175-44b3-acla-4f62de12ab9e/etc/ceph/ceph.client.cinder.keyring
[client.cinder]
key = AQA/pY1XBAnHMBAAeS+0Wmh9PLZe1XqkIW/p0A==
```

Verify whether the keyring matches with the Cinder volume keyring displayed in Step 3.

What to do next

As a final Ceph and Cinder connectivity verification, import a Cinder image using Horizon or the Cinder CLI. After you import the image, compare the IDs seen by Cinder and by Ceph. If the IDs match, it indicates that Ceph is handling the backend for Cinder.

Verifying the Cinder Volume ID on Ceph

The following steps verify Ceph is properly handling new Cinder volumes by checking that the volume ID for a new Cinder volume is the same as the volume ID displayed in Ceph.

Step 1 From the management node, load the OpenStack authentication variables:

```
[root@management-server-cisco ~]# source ~/openstack-configs/openrc
```

Step 2 Create an empty volume:

```
[root@management-server-cisco ~]# openstack volume create --size 5 ciscovoll
```

The preceding command creates a new 5 GB Cinder volume named ciscovoll.

Step 3 List the Cinder volumes:

```
[[root@management-server-cisco ~]# openstack volume list
+-----+-----+-----+-----+-----+
| ID                | Name          | Status   | Size | Attached to |
+-----+-----+-----+-----+-----+
| 3017473b-6db3-4937-9cb2-bd0ba1bf079d | ciscovoll    | available | 5    |              |
+-----+-----+-----+-----+-----+
```

Step 4 Navigate to the Ceph Monitor container:

```
[root@controller_server-1 ~]# cephmon
```

Step 5 Display the contents of the Ceph volumes pool:

```
cephmon_4612 [ceph@controller_server-1 ceph]$ rbd list volumes
volume-3017473b-6db3-4937-9cb2-bd0ba1bf079d
```

Step 6 Verify that the Cinder volume ID displayed in Step 3 matches the volume ID displayed by Ceph, excluding the "volume-" prefix.

Checking Nova Connectivity

The Nova libvirt container must have connectivity to the Cisco NFVI controller nodes. Complete the following steps to verify Nova has connectivity to the controller nodes:

Step 1 From the management node, examine the IP addresses of controller node:

```
[root@management-server-cisco ~]# cat /root/openstack-configs/mercury_servers_info
```

Step 2 From the management node, launch a SSH session to a controller node, for example:

```
[root@management-server-cisco ~]# ssh root@Computenode_server-1
```

Step 3 Navigate to the Nova libvirt container:

```
[root@compute_server-1 ~]# libvirt
```

Step 4 Check the Nova libvirt container connectivity to the storage IP address of the controller node different from the one entered in Step 1:

```
novalibvirt_4612 [root@compute_server-1 /]$ curl 7.0.0.16:6789
```

If the connection is successful, you can see a message `ceph v027?`

```
novalibvirt_4612 [root@compute_server-1 /]$ curl controller_server-1:6789
ceph v027?
```

If the connection is not successful, the following message is displayed:

```
novalibvirt_4612 [root@compute_server-1 /]$ curl 7.0.0.16:6789
curl: (7) Failed connect to controller_server-1:6789; Connection refused
```

The above message indicates that the Ceph monitor running on the target controller node `controller_server-1` is not listening on the specified port or there is no route to it from the Nova libvirt container.

Checking one controller node should be enough to ensure one connection path available for the Nova libvirt. However, because Cisco NFVI controller nodes run as part of an HA cluster, you should run Step 3 above targeting all the controller nodes in the Cisco NFVI pod.

What to do next

After you verify the Nova libvirt connectivity to all Cisco NFVI controller nodes, check the Nova keyring to ensure it matches the Ceph monitor keyring.

Verifying Nova and Ceph Monitor Keyrings

Complete the following steps to verify the Nova libvirt keyring matches the Ceph Monitor keyring.

Step 1 From the management node, launch a SSH session to a compute node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 2 Navigate to the Nova libvirt container:

```
[root@compute_server-1 ~]# libvirt
```

Step 3 Extract the libvirt secret that contains the Nova libvirt keyring:

```
novalibvirt_4612 [root@compute_server-1 /]# virsh secret-list
UUID                               Usage ...
-----
b5769938-e09f-47cb-bdb6-25b15b557e84  ceph client.cinder ...
```

Step 4 Get the keyring from the libvirt secret:

```
novalibvirt_4612 [root@controller_server-1 /]# virsh secret-get-value
b5769938-e09f-47cb-bdb6-25b15b557e84
AQBAPYlXQCBEBEAARoXvmiwmlSMEyEoXKl/sQA==
```

Step 5 On management node, check the CEPH cluster UUID:

```
[root@management-server-cisco ~]# cat /root/openstack-configs/ceph/fetch/ceph_cluster_uuid.conf
0e96e7f2-8175-44b3-ac1a-4f62de12ab9e
```

Step 6 Display the Ceph Cinder keyring content:

```
[root@management-server-cisco ~]# cat
/root/openstack-configs/ceph/fetch/0e96e7f2-8175-44b3-ac1a-4f62de12ab9e/etc/ceph/ceph.client.cinder.keyring
[client.cinder]
```

```
key = AQBAPYlXQCBEBEAARoXvmiwmlSMEyEoXKl/sQA==
```

Verify whether the keyring matches with the Nova libvirt keyring displayed in Step 3. Notice that in the above example the Cinder keyring is checked even though this procedure is for the Nova libvirt keyring. This occurs because the Nova services need access to the Cinder volumes and so authentication to Ceph uses the Cinder keyring.

What to do next

Do a final check to ensure that Ceph and Nova are connected by attaching a Nova volume using Horizon or the Nova CLI. After you attach the Nova volume, check the libvirt domain.

Verifying Nova Instance ID

From the management node, complete the following steps to verify the Nova instance ID of a guest VM having a cinder volume attached::

Step 1 Load the OpenStack authentication variables:

```
[root@management-server-cisco installer]# source ~/openstack-configs/openrc
```

Step 2 List the Nova instances:

```
[root@management-server-cisco images]# nova list
+-----+-----+-----+-----+
| ID                | Name                | Status | Task                |
+-----+-----+-----+-----+
```

```
| 77ea3918-793b-4fa7-9961-10fbdcl5c6e5 | cisco-vm | ACTIVE | -
+-----+-----+-----+-----+-----+-----+
```

Step 3 Show the Nova instance ID for one of the instances:

```
[root@management-server-cisco images]# nova show
77ea3918-793b-4fa7-9961-10fbdcl5c6e5 | grep instance_name
| OS-EXT-SRV-ATTR:instance_name | instance-00000003
```

The Nova instance ID in this example is instance-00000003. This ID will be used later with the virsh command. Nova instance IDs are actually the libvirt IDs of the libvirt domain associated with the Nova instance.

Step 4 Identify the compute node where the VM was deployed:

```
[root@management-server-cisco images]# nova show 77ea3918-793b-4fa7-9961-10fbdcl5c6e5 | grep
hypervisor
| OS-EXT-SRV-ATTR:hypervisor_hostname | compute_server-1
```

The compute node in this case is compute_server-1. You will connect to this compute node to call the virsh commands. Next, you get the volume ID from the libvirt domain in the Nova libvirt container.

Step 5 Launch a SSH session to the identified compute node, compute_server-1:

```
[root@management-server-cisco ~]# ssh root@compute_server-1
```

Step 6 Navigate to the Nova libvirt container:

```
[root@compute_server-1 ~]# libvirt
```

Step 7 Get the instance libvirt domain volume ID:

```
novalibvirt_4612 [root@compute_server-1 /]# virsh dumpxml instance-00000003 | grep rbd
<source protocol='rbd' name='volumes/volume-dd188a5d-f822-4769-8a57-c16694841a23'>
```

Step 8 Launch a SSH session to a controller node:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 9 Navigate to the Ceph Monitor container:

```
[root@compute_server-1 ~]# cephmon
```

Step 10 Verify volume ID matches the ID in Step 7:

```
cephmon_4612 [ceph@controller_server-1 ceph]
$ rbd list volumes | grep volume-dd188a5d-f822-4769-8a57-c16694841a23
volume-dd188a5d-f822-4769-8a57-c16694841a23
```

Displaying Docker Disk Space Usage

Docker supports multiple storage back ends such as Device Mapper, thin pool, overlay, and AUFS. Cisco VIM uses the devicemapper storage driver because it provides strong performance and thin provisioning. Device Mapper is a kernel-based framework that supports advanced volume management capability. Complete the following steps to display the disk space used by Docker containers.

Step 1 Launch a SSH session to a controller or compute node, for example:

```
[root@management-server-cisco ~]# ssh root@controller_server-1
```

Step 2 Enter the docker info command to display the disk space used by Docker containers:

```
[root@controller_server_1 ~]# docker info
Containers: 24
Images: 186
Storage Driver: devicemapper
 Pool Name: vg_var-docker--pool
 Pool Blocksize: 524.3 kB
 Backing Filesystem: xfs
 Data file:
 Metadata file:
 Data Space Used: 17.51 GB
 Data Space Total: 274.9 GB
 Data Space Available: 257.4 GB...
```

Reconfiguring SwiftStack Integration

Cisco VIM provides integration with SwiftStack, an object storage solution. The key aspect of the SwiftStack integration is to add a SwiftStack endpoint to an existing pod running on Cisco VIM through the reconfigure option. In this case the SwiftStack is installed and managed outside the Cisco VIM ahead of time, and the VIM orchestrator adds the relevant Keystone configuration details to access the SwiftStack endpoint (see the Cisco VIM install guide for more details of SwiftStack).

The following options support the SwiftStack reconfiguration:

- Enable SwiftStack integration if it is not present.
- Reconfigure the existing SwiftStack PAC endpoint to point to a different cluster (cluster_api_endpoint).
- Reconfigure the Reseller_prefix of the existing SwiftStack installation.
- Reconfigure the admin password (admin_password) of an existing SwiftStack Install.

Integrating SwiftStack over TLS

The automation supports SwiftStack integration over TLS. To enable TLS, the CA root certificate must be presented as part of the `/root/openstack-configs/haproxy-ca.crt` file. The protocol parameter within the SWIFTSTACK stanza must be set to https. As a pre-requisite, the SwiftStack cluster needs to be configured to enable HTTPS connections for the SwiftStack APIs with termination at the proxy servers.

The following section needs to be configured in the Setup_data.yaml file.

```
#####
# Optional Swift configuration section
#####
# SWIFTSTACK: # Identifies the objectstore provider by name
# cluster_api_endpoint: <IP address of PAC (proxy-account-container) endpoint>
# reseller_prefix: <Reseller_prefix as configured for Keystone Auth,AuthToken support in
Swiftstack E.g KEY_>
# admin_user: <admin user for swift to authenticate in keystone>
# admin_password: <swiftstack_admin_password>
# admin_tenant: <The service tenant corresponding to the Account-Container used by
Swiftstack
protocol: <http or https> # protocol that swiftstack is running on top
```



Note The operator should pay attention while updating the settings to ensure that SwiftStack over TLS are appropriately pre-configured in the customer-managed SwiftStack controller as specified in the Install guide.

To initiate the integration, copy the `setupdata` into a local directory by running the following command:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
```

Update the `setupdata` by running the following command:

```
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to include SwiftStack info)
```

Run the reconfiguration command as follows:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>
```

Cinder Volume Backup on SwiftStack

Cisco VIM enables cinder service to be configured to backup its block storage volumes to the SwiftStack object store. This feature is automatically configured if the `SWIFTSTACK` stanza is present in the `setup_data.yaml` file. The mechanism is to authenticate against SwiftStack during volume backups leverages. The same keystone SwiftStack endpoint is configured to manage objects. The default SwiftStack container that manages cinder volumes within the account (Keystone Tenant as specified by `admin_tenant`) is currently defaulted to `volumebackups`.

Reconfiguring Administrator Source Networks

To access the administrator services, Cisco VIM provides source IP based filtering of network requests on the management node. These services include SSH and Kibana dashboard access. When the services are configured all admin network requests made to the management node are dropped, except the white listed addresses in the configuration.

Reconfiguring administrator source network supports the following options:

- Set administrator source network list: Network addresses can be added or deleted from the configuration; the list is replaced in whole during a reconfigure operation.
- Remove administrator source network list: If the `admin_source_networks` option is removed, then the source address does not filter the incoming admin service requests.

The following section needs to be configured in the `Setup_data.yaml` file:

```
admin_source_networks: # optional, host based firewall to white list admin's source IP
- 10.0.0.0/8
- 172.16.0.0/12
```



Note The operator has to be careful while updating the source networks. If the list is misconfigured, operators may lock themselves out of access to the management node through SSH. If it is locked, an operator must log into the management node through the console port to repair the configuration.

To initiate the integration, copy the `setupdata` into a local directory by running the following command:

```
[root@mgmt1 ~]# cd /root/
[root@mgmt1 ~]# mkdir MyDir
[root@mgmt1 ~]# cd MyDir
[root@mgmt1 ~]# cp /root/openstack-configs/setup_data.yaml <my_setup_data.yaml>
```

Update the `setupdata` by running the following command:

```
[root@mgmt1 ~]# vi my_setup_data.yaml (update the setup_data to include SwiftStack info)
```

Run the reconfiguration command as follows:

```
[root@mgmt1 ~]# cd ~/installer-xxxx
[root@mgmt1 ~]# ciscovim reconfigure --setupfile ~/MyDir/<my_setup_data.yaml>
```

Password Reset for Cisco VIM Management Node

Run the following command to reset the Root Password of Cisco VIM management node **RHEL-7 / systemd**

1. Boot your system and wait until the **GRUB2** menu appears.
2. In the **boot loader** menu, highlight any entry and press **e**.
3. Find the line beginning with `linux`. At the end of this line, append the following:

```
init=/bin/sh
```

Or if you face any alarm, instead of **ro** change **rw** to **sysroot** as shown in the following example:

```
rw init=/sysroot/bin/sh
```

4. Press **Ctrl+X** to boot the system using the options you edited.

Once the system boots, you can see the shell prompt without having to enter any user name or password:

```
sh-4.2#
```

5. Load the installed SELinux policy by running the following command:

```
sh-4.2# /usr/sbin/load_policy -i
```

6. Execute the following command to remount your root partition:

```
sh4.2#
mount -o remount,rw /
```

7. Reset the root password by running the following command:

```
sh4.2# passwd root
```

When prompted, enter your new root password and click **Enter** key to confirm. Enter the password for the second time to make sure you typed it correctly and confirm with **Enter** again. If both the passwords match, a confirmation message appears.

8. Execute the following command to remount the root partition again, this time as read-only:

```
sh4.2#  
mount -o remount,ro /
```

9. Reboot the system. Now you can log in as the root user using the new password set up during this procedure.
To reboot the system, enter **exit** and **exit** again to leave the environment and reboot the system.

References: <https://access.redhat.com/solutions/918283>.



CHAPTER 6

Overview to Cisco VIM Unified Management

Cisco VIM Unified Management is an optional application, which acts as a single point of management for the Cisco VIM. Inclusive of your Cisco NFVI package, you can use Cisco VIM Unified Management to manage Cisco NFVI for day-0 and day-n and for multi-site and multi-pod management features.


- [Cisco VIM Unified Management Overview, on page 169](#)
- [Cisco VIM Unified Management Admin UI Overview, on page 171](#)
- [Cisco VIM Unified Management Pod UI Overview, on page 171](#)

Cisco VIM Unified Management Overview

Cisco VIM provides an Intuitive and easy way to deploy and manage the NFVI platform, reducing user-error and providing visualization deployment to manage multiple Cisco VIM Pods from a single portal. In Cisco VIM 2.2 and higher releases, a light-weight UI which is a dockerized application, supports multi-tenancy with local RBAC support and CiscoVIM Rest layer are integrated. The container-based UI platform manages multiple CiscoVIM pods from day-0, or above in the lifecycle of the cloud.


The following figure shows the architecture of the CiscoVIM UM's interaction with a Pod:

Figure 16: Cisco VIM UM's Interaction with a Pod



The architecture of the CiscoVIM UM is light-weight, hierarchical, and scalable. Each local site is autonomous with localized toolsets. Global Unified Management UI, provides ease of management with multisite and multi-pod capability for distributed NFV deployment at scale. This facility can be used through browsers such as IE, Firefox, Safari, and Chrome. Cisco VIM UM by itself, is designed to operate in HA. The platform is a modular, loosely coupled architecture, that provides the capability to manage multiple pods, with RBAC support as depicted in the following figure:

Figure 17: Cisco VIM UM Architecture



Cisco VIM UM can be installed in Standalone or non-HA mode: You can Install in a Standalone or non-HA mode (on the management node of the pod) or a standalone (BOM same as the management node) server. Migrating from one install mode to another can be done effectively as the UI interacts with each Pod through REST API and little RBAC information of the Admin and user is kept in the DB.

The UI has two types of views:

- UI Admin: UI Admin can add users as UI Admin or Pod Admin.
- Pod Admin: Pod Admin has the privilege only at the Pod level, unless Pod Admin is also a UI Admin.

Cisco VIM Unified Management Admin UI Overview

Admin UI is responsible for managing the UI and Pod admin, which includes adding and revoking user privileges. Also, the UI Admin can delete an existing Pod from the management pane.

Cisco VIM Unified Management Pod UI Overview

The Pod UI, is responsible for managing each Pod. VIM UM gives easy access to switch between multiple Pods. Through the Pod UI, a Pod Admin can manage users and their respective roles and responsibilities. Also, the Pod UI provides the user to execute day-0 (install) and day-n (Pod management, software update, and so on.) activities seamlessly. ELK, Horizon Web UI, and so on, are also cross-launched and visible for each Pod through the Pod UI.



CHAPTER 7

Managing Cisco VIM through Unified Management

This functionality brings in clear separation of roles. It does not store any pod related details obtained directly through Rest API from the pods locally, except for RBAC information.

- [UI Administrators Privileges and Responsibilities, on page 173](#)
- [Pod UI Privileges and Responsibilities, on page 174](#)
- [Adding Cisco VIM Pod, on page 174](#)
- [Deleting Pod from Cisco VIM Unified Management, on page 175](#)
- [Context Switching Within Unified Management, on page 176](#)
- [Dashboard, on page 176](#)

UI Administrators Privileges and Responsibilities

The Unified Management UI Admin has the following privileges and responsibilities:

1. Unified Management UI Admin(s) can only add Pod Admin. The Pod Admin can be added in two ways:
 - Local database
 - LDAP with registration type as mail, uid, cn or group.
2. Unified Management UI Admin can manage all the users in Unified Management from **Manage Pod Users**.
 - UI Admin can revoke permission of Users: If UI Admin wants to revoke a user from a Pod, click **Revoke permission** icon under Action column.
 - UI Admin can delete a User: If UI Admin wants to delete a user from the UM, Click **Delete** icon under Action column. If there is only one user associated with a Pod then UI Admin needs to delete the pod and then delete or revoke the user permission.
3. Unified Management UI Admin can manage Pod Admin(s) from **Manage Pod Admin**.
 - UI Admin can add a new Pod Admin in Unified Management.
 - UI Admin can revoke permission of a user or LDAP group from being a Pod Admin.
4. Unified Management UI Admin can manage Pods from Manage Pods.

- UI Admin can delete a Pod from Unified Management.
 - UI Admin can also update password for the REST incase there was a system update on the pod and REST password was changed in that process.
5. Unified Management UI Admin can manage other UI Admin(s) from **Manage UI Admin Users**.
- Unified Management UI Admin can add another UI Admin.
 - Unified Management UI Admin can revoke permission of the user from being an UI Admin.



Note If there is only one UI Admin for Unified Management, the revoke permission icon is disabled for the user.

Pod UI Privileges and Responsibilities

As Cisco VIM is Rest API based, you can manage a pod through CLI, Rest API or UI. You can always bring in a partial or fully functional Pod and register with VIM UM. UM queries the pod status through Rest API and reflect the same.



Note We recommend the admin to choose only one path to manage the pod.

Adding Cisco VIM Pod

Before you begin

Complete the following pre-requisites to add a Cisco VIM Pod:

- Bootstrap of VIM Unified Management is complete and successful as per the install guide.
- At minimum, a UI and Pod Admin exists as per the install guide.

Step 1 Navigate to https://br_api:9000

Step 2 Click **Register Management Node** link.

- Enter the Endpoint IP which is the **br_api** of your Pod.

Note Run time validation to check if the Endpoint IP is already registered to Unified Management.

- Give a name or tag for the pod you are registering.
- Enter the REST API password for the Pod.
 - You can locate the REST API password on the Pod you are registering.
 - The path to locate REST API password is : `/opt/cisco/ui_config.json`.

- A brief description about management node. Description field is optional and can be left blank.
- Enter the Email ID of the Pod Admin.
 - Run time validation to check if the Email ID is Pod admin or not.
 - If False, the Unified Management gives an error that the User is not registered as Pod Admin.
 - If True, the User Name is auto-populated and the **Register** button is enabled.

Step 3 Click **Browse** to upload restapi server CA Certificate. This is enabled once the Pod Admin validation is successful.

- Navigate to `/var/www/mercury/mercury-ca.crt` of the management node.
- Download the Certificate to the local machine and upload the certificate using Unified Management.

Validation check for file size and extension is done as a part of upload and in case of failure the Certificate is deleted and you need to upload the valid certificate again.

If the Certificate is uploaded successfully then **Register** button is enabled. To do a management node health check click **Register**.

- If the REST API service is down on the management node then a failure message will be displayed as : Installer REST API service not available. The certificate will not be deleted.
- If the Certificate is invalid and there is a SSL connection problem with the management node then certificate is deleted and message is displayed to upload the certificate again.
- If the Certificate is valid user is redirected to the login page with a message- management node registered successfully.

Step 4 Click **Register** to redirect the user to the landing or login page. Pod Admin receives the notification mail that the management node is registered successfully.

Deleting Pod from Cisco VIM Unified Management

When you delete a Pod from Cisco VIM UM, you are not deleting the Pod from your OpenStack deployment.

Before you begin

Following the steps to delete a Cisco VIM Pod:

- Bootstrap of VIM Unified Management is complete and successful as per the install guide.
- At least one UI and Pod Admin exists as per the install guide.
- The UM manages the targeted Pod.

Step 1 Log in as the **UM UI Admin**.

Step 2 In the navigation pane, click **Manage Pods**.

Step 3 Choose the pod that you want to delete in the Action column and click **Delete**.

Step 4 Click **Proceed**, to confirm the deletion.

Context Switching Within Unified Management


Cisco VIM UM has permissions to switch between two or more pods for a particular node. The user can be a admin for one or more pods, and a normal user for some other pod, simultaneously. Ability to access multiple pods, provides the user to maintain context and yet scale from a pod management point of view.

There are two ways a user can switch to another pod.

- **Context Switching Icon:** Context Switching Icon is situated on the top right corner and is the third icon from the right tool tip of the UI. Click **Context Switching** Icon to view all the pods that you can access. Pod with a red dot indicates that the REST Password that is entered during registration of the Management node does not match with the current REST Password for that of particular node. In such a situation the Pod admin or User has to reach out to UI admin to update the password for that Node. UI admin updates the password from Manage Pods in Unified Management UI admin Portal.
- **Switch Between Management Nodes:** Switch Between Management Nodes is available in the Dashboard. The user can see all the pods in the table and can navigate to any Pod using a single click. If mouse pointer changes from hand or cursor to a red dot sign it indicates that the REST Password entered during registration of Management node does not match with the current REST Password for that particular node.

Dashboard

After selecting a Pod from landing page, you will be redirected to the **Dashboard** of that particular Pod.



Blueprint Name

Blueprint section provides the name of the Blueprint, the health status of the blueprint and the various installation stages with the status. The different status is Success, Failed or Not Run.

Click **Next and Previous**, you can navigate between various installation stages.

Deployed Cloud Status

This section highlights the cloud status on the Pod.

- Active (Green): If the cloud is deployed without any failures.
- Failed (Red): If the cloud deployment fails.
- Not Available (Gray): If the cloud is not deployed on the Pod.

Deployed Blueprint Details

In this section you get information about deployed blueprint which includes Deployment Status, Operation start time, Operation update time, and a link to the log of last operation. In case of the failure of cloud installation, the name with keyword regarding component failure is visible as Deployment Status.

Pod Operation Details

The Pod operation details table provides information regarding the current and last operation which includes Current operation details, Pod operation status and information about the operation start time and update time. Refresh icon facilitates the user to fetch latest operation status from the Pod.



CHAPTER 8

Managing Blueprints

The following topics tell you how to manage Cisco NFVI Blueprints.

- [Blueprints](#), on page 179
- [Creating a Blueprint Using Upload Functionality](#), on page 180
- [Managing Post Install Features](#), on page 279

Blueprints

Blueprints contain the configuration metadata required to deploy an OpenStack system through a Cisco VIM pod in Cisco VIM Unified Management. You can create a blueprint in Cisco UM or you can upload a yaml file that contains the metadata for a blueprint. You can also create a blueprint from an existing OpenStack system that you are configuring as a Cisco VIM pod.

The configuration in the blueprint is specific to the type of Cisco UCS server that is in the OpenStack system. A blueprint for a C-Series server-based OpenStack system cannot be used to configure a B-Series server-based OpenStack system. Cisco UM displays an error if the blueprint does not match the configuration of the OpenStack system.

The blueprint enables you to quickly change the configuration of an OpenStack system. While only one blueprint can be active, you can create or upload multiple blueprints for a Cisco VIM pod. If you change the active blueprint for a pod, you have to update the configuration of the OpenStack system to match the new blueprint.



Note You can modify and validate an existing blueprint, or delete a blueprint. However, you cannot modify any of the configuration metadata in the active blueprint for a Cisco VIM pod.

Blueprint Activation

A blueprint becomes active when you use it in a successful installation for a Cisco VIM pod. Other blueprints that you created or uploaded to that pod are in nonactive state.

Uploading or creating a blueprint does not activate that blueprint for the pod. Install a blueprint through the **Cisco VIM Suite** wizard. If the installation is successful, the selected blueprint becomes active.



Note If you want to activate a new blueprint in an existing pod, you have to delete certain accounts and the credential policies for that pod before you activate the blueprint. See [Activating a Blueprint in an Existing Pod with OpenStack Installed, on page 181](#).

Viewing Blueprint Details

To view blueprint details:

-
- Step 1** Log in to Cisco VIM Unified Management as pod user.
 - Step 2** Choose the Cisco VIM pod with the blueprint that you want to view.
 - Step 3** Click **Menu** at the top left corner to expand the navigation pane.
 - Step 4** Choose **Pre-Install > Blueprint Management**.
 - Step 5** Choose a blueprint from the list.
 - Step 6** Click **Preview and Download YAML**.
-

Creating a Blueprint Using Upload Functionality

Before you begin

- You must have a YAML file (B series or C Series) on your system.
- Only one blueprint can be uploaded at a time. To create a blueprint off-line, refer to the `setup_data.yaml.B_Series_EXAMPLE` or `setup_data.yaml.C_Series_EXAMPLE`.
- The respective keys in the sample YAML have to match or the corresponding pane does not get populated during the upload.

-
- Step 1** Log in to **Cisco VIM UM**.
 - Step 2** In the navigation pane, expand the **Pre-Install** section and click **Blueprint** setup.
 - Step 3** Click the **Browse** in the **Blueprint Initial Setup**.
 - Step 4** Click **Select**.
 - Step 5** Click **Load** in the **Unified Management UI Application**.
All the fields present in the YAML file is uploaded to the respective fields in the UI.
 - Step 6** Provide a **Name for the Blueprint**.
While saving the blueprint name has to be unique.
 - Step 7** Click **Offline Validation**.

- If all the mandatory fields in the UI are populated, then Offline Validation of the Blueprint commences, or else a pop up message indicating the section of Blueprint creation that has missing information error shows up.

Step 8 On Offline Blueprint Validation being successful, **Save Blueprint** and **Cancel** is enabled.

Note If the Blueprint Validation Fails, only the **Cancel** button is enabled.

Activating a Blueprint in an Existing Pod with OpenStack Installed

Before you begin

You must have a POD which has an active Installation of OpenStack. If the OpenStack installation is in Failed State, then UM UI will not be able to fetch the Blueprint.

Step 1 Go to the **Landing page** of the UM Log in.

Step 2 Click **Register Management Node**.

Step 3 Enter the following details:

- Management Node IP Address.
- Management Node Name (Any friendly Name).
- REST API Password (/opt/cisco/ui_config.json).
- Description about the Management Node.
- POD Admin's Email ID.

A notification email is sent to the email id entered during registration.

Step 4 Log in using the same email id and password.

Step 5 In the navigation pane, click **Pre-Install > Blueprint Management**.

Choose the **NEWSETUPDATA** from the **Blueprint Management** pane.

This is the same setup data which was used by ciscovimclient, to run the installation on the Management Node.

Blueprint Management



Note You must have at least one blueprint (In any state Active or In-Active or In-progress), in the Blueprint Management Pane.

The screenshot shows the Cisco VIM Unified Management interface. The top navigation bar includes the Cisco logo, 'VIM Unified Management', the user's name 'Calsoft', IP address '10.30.116.244', role 'Full-Pod-Access', and user ID 'rohshar'. A notification bar indicates 'Press F11 to exit full screen'. The left sidebar contains navigation options: Dashboard, Pre-Install, Blueprint Setup (with sub-option 'Blueprint Management' selected), Post-Install, View Topology, and Pod User Administration. The main content area is titled 'Blueprints Management' and features a table with columns for 'Blueprint Title', 'Modified Date', 'Status', and 'Action'. The table lists four blueprints: 'Test' (Invalid), '5555' (Invalid), 'NEWSETUPDATA' (Deployed), and '56646' (Invalid). Each row has an 'Action' column with icons for edit, delete, and download. A search bar and pagination controls are also visible.

Blueprint Title	Modified Date	Status	Action
Test	4/3/2018, 2:55:18 PM	Invalid	[Edit] [Delete] [Download]
5555	4/2/2018, 9:27:07 PM	Invalid	[Edit] [Delete] [Download]
NEWSETUPDATA	4/3/2018, 5:15:25 PM	Deployed	[Edit] [Delete] [Download]
56646	4/2/2018, 9:29:00 PM	Invalid	[Edit] [Delete] [Download]

Blueprint Management grid contains the list of all the blueprints that are saved. You can save the blueprint even if it is failed in the Blueprint Setup. However, you will not be allowed to deploy those Blueprints.

Blueprint Management table provides the following information:

- Blueprint Name
- Modified Date
- Edit, Remove, and Download Blueprint
- Search Blueprint

Blueprint Name: It shows the name of the Blueprint. You cannot edit this field. It shows the name of the blueprint that is saved after Offline Validation.



Note No two blueprints can have the same Blueprint name.

Modified Date: This shows when blueprint was last modified.

Blueprint Status: There are 6 total status for the Blueprint.


- Valid: Blueprint that is saved after offline validation success.
- Invalid: Blueprint that is saved after Offline Validation failure.
- Inprogress: Blueprint that is saved without running Offline Validation.
- Deployed: Blueprint that is used to bring up cloud without failures.
- Installing: Blueprint that is used to initiate the cloud deployment.

- Failed: Blueprint that is used to deploy the cloud which eventually failed.

With every blueprint record, there are some operations associated that you can perform by using the buttons – Topology, Install, and Remove.

Topology

Topology allows you to view graphical representation of the control, compute, and storage node that is associated with the various network segments.



Install Button

Click **Install**, a confirmation message is generated requesting to initiate the deployment with the stages you want to run. By default all stages are selected but you can also do an incremented install. In case of Incremented Install, you have to choose stages in the order. For Example: If you choose Validation Stage then the 2nd stage Management Node Orchestration is enabled. You cannot skip stages and run a deployment. Once you click **Proceed**, the Cloud Deployment is initiated and the progress can be viewed from the Dashboard.

Remove Button

Choose the blueprint and click **Remove** to remove the blueprint. A confirmation message appears. If you click **Proceed**, the blueprint removal operation is initiated.

Edit, Remove, and Download Blueprint

You can edit or delete a Blueprint which is not in Deployed State. If you want to take a backup of the Blueprint locally, click *Download* icon which generates the preview to download the Blueprint.

Following are the ways to deploy a Blueprint:

- If there is no Blueprint in Deployed state, then you can choose any Valid Blueprint from the list.
- If there is a Blueprint in a Failed state, you can choose another Valid Blueprint but Unified Management asks you to remove the previous deployment before proceeding.
- If there is a Blueprint in Deployed state, you can choose another Valid Blueprint but Unified Management asks you to remove the previous deployment before proceeding.

The deployment of Blueprint occurs stepwise and if any one step fails for some reason, a **Play** button is displayed on that particular step. You can click a **Play** button and begin the installation for that particular state.



Note There is always one blueprint in Deployed state. You cannot deploy multiple blueprints in the cloud.

Search Blueprint: Search box is displayed on top-right of the table which facilitates you to lookup for Blueprint by their name or status. Navigate to **Topology** and choose a Blueprint which redirects you to the default blueprint, the one which is selected in the Blueprint Management pane.




Note During the various operations across the application the cloud icon in the center of the header changes its color which is based on the following table.

Table 16:


POD Operation	Status	Icon or Color
Management Node Registered, No Active Deployment	Pending	Gray
Cloud Up And Running, No Failure	Active	Green
Cloud Installation/ Any Operation In Progress	In-Progress	Blue
Cloudpulse Failed	Critical Warnings	Red
Pod Operation Failed	Warning	Amber
Software Update (Auto) Rollback Failed	Critical Warnings	Red
Uncommitted Software Update	Warning	Amber
Reconfigure Openstack Password	Critical Warning	Red
Reconfigure CIMC Password	Warning	Amber
Reconfigure Optional Features/ OS	Critical Warning	Red
Power Management Operation Fails	Warning	Amber
Management Not-Reachable	Not-Reachable	Red


Creating a Blueprint for B-Series Server Platform

Procedure


	Command or Action	Purpose						
Step 1	In the navigation pane, choose Pre-Install > Blueprint Setup .							
Step 2	To create a B Series Blueprint :	<p>1. On the Blueprint Initial Setup pane of the Cisco VIM Unified Management, complete the following fields:</p>  <table border="1" data-bbox="966 1344 1526 1774"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Blueprint Name field</td> <td>Enter blueprint configuration name.</td> </tr> <tr> <td>Platform Type drop-down list</td> <td>Choose one of the following platform types: <ul style="list-style-type: none"> • B-Series (By default) choose B series for this section. • C-Series </td> </tr> </tbody> </table>	Name	Description	Blueprint Name field	Enter blueprint configuration name.	Platform Type drop-down list	Choose one of the following platform types: <ul style="list-style-type: none"> • B-Series (By default) choose B series for this section. • C-Series
Name	Description							
Blueprint Name field	Enter blueprint configuration name.							
Platform Type drop-down list	Choose one of the following platform types: <ul style="list-style-type: none"> • B-Series (By default) choose B series for this section. • C-Series 							

	Command or Action	Purpose	
		Name	Description
		Tenant Network drop-down list	Choose one of the following tenant network types: <ul style="list-style-type: none"> • Linuxbridge/VXLAN • OVS/VLAN
		Pod Type drop-down list	Choose one of the following pod types: <ul style="list-style-type: none"> • Fullon(By Default)
		Ceph Mode drop-down list	Choose one of the following Ceph types: <ul style="list-style-type: none"> • Dedicated • Central (By Default) - Not supported in Production
		Optional Features and Services Checkbox	Swiftstack, LDAP, Syslog Export Settings, Install Mode, ToR Switch Information, TLS, NFVMON, Pod Name, VMTP, NFV Bench, Auto-backup, Heat, Keystone v3, Enable Esc Priv. If any one is selected, the corresponding section is visible in various Blueprint sections. By default all features are disabled except Auto-backup.

	Command or Action	Purpose												
		<table border="1" data-bbox="966 273 1526 787"> <thead> <tr> <th data-bbox="966 273 1242 325">Name</th> <th data-bbox="1242 273 1526 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 325 1242 787">Import Existing YAML file</td> <td data-bbox="1242 325 1526 787"> Click Browse button to import the existing yaml file. If you have an existing B Series YAML file you can use this feature to upload the file. Unified Management automatically fill in the fields and if any mandatory field is missed then it gets highlighted in the respective section. </td> </tr> </tbody> </table> <p data-bbox="901 808 1526 913">2. Click Physical Setup to navigate to the Registry Setup configuration page. Fill in the following details for Registry Setup:</p>  <table border="1" data-bbox="966 1333 1526 1648"> <thead> <tr> <th data-bbox="966 1333 1242 1386">Name</th> <th data-bbox="1242 1333 1526 1386">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 1386 1242 1470">Registry User Name text field</td> <td data-bbox="1242 1386 1526 1470">Enter the User-Name for Registry (Mandatory).</td> </tr> <tr> <td data-bbox="966 1470 1242 1554">Registry Password text field</td> <td data-bbox="1242 1470 1526 1554">Enter the Password for Registry (Mandatory).</td> </tr> <tr> <td data-bbox="966 1554 1242 1648">Registry Email text field</td> <td data-bbox="1242 1554 1526 1648">Enter the Email ID for Registry (Mandatory).</td> </tr> </tbody> </table> <p data-bbox="966 1669 1526 1732">Once all mandatory fields are filled the Validation Check Registry Pane shows a Green Tick.</p> <p data-bbox="901 1753 1526 1816">3. Click UCSM Common Tab and complete the following fields:</p>	Name	Description	Import Existing YAML file	Click Browse button to import the existing yaml file. If you have an existing B Series YAML file you can use this feature to upload the file. Unified Management automatically fill in the fields and if any mandatory field is missed then it gets highlighted in the respective section.	Name	Description	Registry User Name text field	Enter the User-Name for Registry (Mandatory).	Registry Password text field	Enter the Password for Registry (Mandatory).	Registry Email text field	Enter the Email ID for Registry (Mandatory).
Name	Description													
Import Existing YAML file	Click Browse button to import the existing yaml file. If you have an existing B Series YAML file you can use this feature to upload the file. Unified Management automatically fill in the fields and if any mandatory field is missed then it gets highlighted in the respective section.													
Name	Description													
Registry User Name text field	Enter the User-Name for Registry (Mandatory).													
Registry Password text field	Enter the Password for Registry (Mandatory).													
Registry Email text field	Enter the Email ID for Registry (Mandatory).													




	Command or Action	Purpose												
		 <table border="1" data-bbox="927 1014 1487 1684"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>User name disabled field</td> <td>By default the value is Admin.</td> </tr> <tr> <td>Password text field</td> <td>Enter Password for UCSM Common (Mandatory).</td> </tr> <tr> <td>UCSM IP text field</td> <td>Enter IP Address for UCSM Common (Mandatory).</td> </tr> <tr> <td>Resource Prefix text field</td> <td>Enter the resource prefix(Mandatory).</td> </tr> <tr> <td>QOS Policy Type drop-down</td> <td>Choose one of the following types: <ul style="list-style-type: none"> NFVI (Default) Media </td> </tr> </tbody> </table>	Name	Description	User name disabled field	By default the value is Admin.	Password text field	Enter Password for UCSM Common (Mandatory).	UCSM IP text field	Enter IP Address for UCSM Common (Mandatory).	Resource Prefix text field	Enter the resource prefix(Mandatory).	QOS Policy Type drop-down	Choose one of the following types: <ul style="list-style-type: none"> NFVI (Default) Media
Name	Description													
User name disabled field	By default the value is Admin.													
Password text field	Enter Password for UCSM Common (Mandatory).													
UCSM IP text field	Enter IP Address for UCSM Common (Mandatory).													
Resource Prefix text field	Enter the resource prefix(Mandatory).													
QOS Policy Type drop-down	Choose one of the following types: <ul style="list-style-type: none"> NFVI (Default) Media 													

	Command or Action	Purpose			
		<table border="1"> <thead> <tr> <th data-bbox="893 273 1242 325">Name</th> <th data-bbox="1242 273 1534 325">Description</th> </tr> </thead> </table>	Name	Description	
Name	Description				
		<table border="1"> <tbody> <tr> <td data-bbox="893 325 1242 661"> Max VF Count text field </td> <td data-bbox="1242 325 1534 661"> Select the Max VF Count. <1-54> Maximum VF count 54, default is 20. If VF performance is enabled we recommend you to keep MAX_VF_COUNT to 20 else may fail on some VICs like 1240. </td> </tr> </tbody> </table>	Max VF Count text field	Select the Max VF Count. <1-54> Maximum VF count 54, default is 20. If VF performance is enabled we recommend you to keep MAX_VF_COUNT to 20 else may fail on some VICs like 1240.	
Max VF Count text field	Select the Max VF Count. <1-54> Maximum VF count 54, default is 20. If VF performance is enabled we recommend you to keep MAX_VF_COUNT to 20 else may fail on some VICs like 1240.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 661 1242 787"> Enable VF Performance optional checkbox </td> <td data-bbox="1242 661 1534 787"> Default is false. Set to true to apply adaptor policy at VF level. </td> </tr> </tbody> </table>	Enable VF Performance optional checkbox	Default is false. Set to true to apply adaptor policy at VF level.	
Enable VF Performance optional checkbox	Default is false. Set to true to apply adaptor policy at VF level.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 787 1242 871"> Enable Prov FI PIN optional checkbox </td> <td data-bbox="1242 787 1534 871"> Default is false. </td> </tr> </tbody> </table>	Enable Prov FI PIN optional checkbox	Default is false.	
Enable Prov FI PIN optional checkbox	Default is false.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 871 1242 1092"> MRAID-CARD optional checkbox </td> <td data-bbox="1242 871 1534 1092"> Enables JBOD mode to be set on disks. Applicable only if you have RAID controller configured on Storage C240 Rack servers. </td> </tr> </tbody> </table>	MRAID-CARD optional checkbox	Enables JBOD mode to be set on disks. Applicable only if you have RAID controller configured on Storage C240 Rack servers.	
MRAID-CARD optional checkbox	Enables JBOD mode to be set on disks. Applicable only if you have RAID controller configured on Storage C240 Rack servers.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 1092 1242 1207"> Enable UCSM Plugin optional checkbox </td> <td data-bbox="1242 1092 1534 1207"> Visible when Tenant Network type is OVS/VLAN. </td> </tr> </tbody> </table>	Enable UCSM Plugin optional checkbox	Visible when Tenant Network type is OVS/VLAN.	
Enable UCSM Plugin optional checkbox	Visible when Tenant Network type is OVS/VLAN.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 1207 1242 1396"> Enable QoS Policy optional checkbox </td> <td data-bbox="1242 1207 1534 1396"> Visible only when UCSM Plugin is enabled. If UCSM Plugin is disabled then this option is set to False. </td> </tr> </tbody> </table>	Enable QoS Policy optional checkbox	Visible only when UCSM Plugin is enabled. If UCSM Plugin is disabled then this option is set to False.	
Enable QoS Policy optional checkbox	Visible only when UCSM Plugin is enabled. If UCSM Plugin is disabled then this option is set to False.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 1396 1242 1522"> Enable QOS for Port Profile optional checkbox </td> <td data-bbox="1242 1396 1534 1522"> Visible only when UCSM Plugin is enabled. </td> </tr> </tbody> </table>	Enable QOS for Port Profile optional checkbox	Visible only when UCSM Plugin is enabled.	
Enable QOS for Port Profile optional checkbox	Visible only when UCSM Plugin is enabled.				
		<table border="1"> <tbody> <tr> <td data-bbox="893 1522 1242 1816"> SRIOV Multi VLAN Trunk optional grid </td> <td data-bbox="1242 1522 1534 1816"> Visible when UCSM Plugin is enabled. Enter the values for network and vlans ranges. Grid can handle all CRUD operations such as Add, Delete, Edit and, Multiple Delete. </td> </tr> </tbody> </table>	SRIOV Multi VLAN Trunk optional grid	Visible when UCSM Plugin is enabled. Enter the values for network and vlans ranges. Grid can handle all CRUD operations such as Add, Delete, Edit and, Multiple Delete.	
SRIOV Multi VLAN Trunk optional grid	Visible when UCSM Plugin is enabled. Enter the values for network and vlans ranges. Grid can handle all CRUD operations such as Add, Delete, Edit and, Multiple Delete.				

	Command or Action	Purpose										
		<p>4. Click Networking to advance to the networking section of the Blueprint:</p>  <table border="1" data-bbox="922 1241 1489 1774"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Domain Name field</td> <td>Enter the domain name (Mandatory).</td> </tr> <tr> <td>HTTP Proxy Server field</td> <td>If your configuration uses an HTTP proxy server, enter the IP address of the server.</td> </tr> <tr> <td>HTTPS Proxy Server field</td> <td>If your configuration uses an HTTPS proxy server, enter the IP address of the server.</td> </tr> <tr> <td>IP Tables on Management Pods</td> <td>Specifies the list of IP Address with Mask.</td> </tr> </tbody> </table>	Name	Description	Domain Name field	Enter the domain name (Mandatory) .	HTTP Proxy Server field	If your configuration uses an HTTP proxy server, enter the IP address of the server.	HTTPS Proxy Server field	If your configuration uses an HTTPS proxy server, enter the IP address of the server.	IP Tables on Management Pods	Specifies the list of IP Address with Mask.
Name	Description											
Domain Name field	Enter the domain name (Mandatory) .											
HTTP Proxy Server field	If your configuration uses an HTTP proxy server, enter the IP address of the server.											
HTTPS Proxy Server field	If your configuration uses an HTTPS proxy server, enter the IP address of the server.											
IP Tables on Management Pods	Specifies the list of IP Address with Mask.											

	Command or Action	Purpose	
		Name	Description
		NTP Server	Enter a maximum of four and minimum of one IPv4 and /or IPv6 addresses in the table.
		Domain Name Server	Enter a maximum of three and minimum of one IPv4 and/or IPv6 addresses.


	Command or Action	Purpose	
		Name	Description
		Network table	

	Command or Action	Purpose								
		<table border="1"> <thead> <tr> <th data-bbox="885 273 1242 325">Name</th> <th data-bbox="1242 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 325 1242 1852"></td> <td data-bbox="1242 325 1534 1852"> <p>Network table is pre-populated with segments. To add Networks you can either clear all the table using Delete All or click Edit icon for each segment and fill in the details.</p> <p>You can add, edit, or delete network information in the table:</p>  <ul style="list-style-type: none"> • Click + to enter new entries (networks) to the table. • Specify the following fields in the Edit Entry to Networks dialog box. <table border="1"> <thead> <tr> <th data-bbox="1258 1585 1388 1638">Name</th> <th data-bbox="1388 1585 1534 1638">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1258 1638 1388 1852">VLAN field</td> <td data-bbox="1388 1638 1534 1852">Enter the VLAN ID. For Segment - Provider, the VLAN</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>Network table is pre-populated with segments. To add Networks you can either clear all the table using Delete All or click Edit icon for each segment and fill in the details.</p> <p>You can add, edit, or delete network information in the table:</p>  <ul style="list-style-type: none"> • Click + to enter new entries (networks) to the table. • Specify the following fields in the Edit Entry to Networks dialog box. <table border="1"> <thead> <tr> <th data-bbox="1258 1585 1388 1638">Name</th> <th data-bbox="1388 1585 1534 1638">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1258 1638 1388 1852">VLAN field</td> <td data-bbox="1388 1638 1534 1852">Enter the VLAN ID. For Segment - Provider, the VLAN</td> </tr> </tbody> </table>	Name	Description	VLAN field	Enter the VLAN ID. For Segment - Provider, the VLAN
Name	Description									
	<p>Network table is pre-populated with segments. To add Networks you can either clear all the table using Delete All or click Edit icon for each segment and fill in the details.</p> <p>You can add, edit, or delete network information in the table:</p>  <ul style="list-style-type: none"> • Click + to enter new entries (networks) to the table. • Specify the following fields in the Edit Entry to Networks dialog box. <table border="1"> <thead> <tr> <th data-bbox="1258 1585 1388 1638">Name</th> <th data-bbox="1388 1585 1534 1638">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1258 1638 1388 1852">VLAN field</td> <td data-bbox="1388 1638 1534 1852">Enter the VLAN ID. For Segment - Provider, the VLAN</td> </tr> </tbody> </table>	Name	Description	VLAN field	Enter the VLAN ID. For Segment - Provider, the VLAN					
Name	Description									
VLAN field	Enter the VLAN ID. For Segment - Provider, the VLAN									

	Command or Action	Purpose																				
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1211 327">Name</th> <th colspan="2" data-bbox="1211 275 1487 327">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 327 1211 489"></td> <td data-bbox="1211 327 1352 489"> <table border="1"> <thead> <tr> <th data-bbox="1211 327 1352 373">Name</th> <th data-bbox="1352 327 1487 373">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1211 373 1352 489"></td> <td data-bbox="1352 373 1487 489">ID value is always <i>none</i>.</td> </tr> </tbody> </table> </td> <td data-bbox="1352 327 1487 489"></td> </tr> <tr> <td data-bbox="854 489 1211 1524"></td> <td data-bbox="1211 489 1352 1524"> Segment drop-down list </td> <td data-bbox="1352 489 1487 1524"> You can select any one segment from the drop-down list. <ul style="list-style-type: none"> • API • Management • Tenant • CIMC • Storage • External • Provider (optional) <p>Note Some segments do not need some of the values listed in the preceding points.</p> </td> </tr> <tr> <td data-bbox="854 1524 1211 1675"></td> <td data-bbox="1211 1524 1352 1675"> Subnet field </td> <td data-bbox="1352 1524 1487 1675"> Enter the IPv4 address for the subnet. </td> </tr> <tr> <td data-bbox="854 1675 1211 1793"></td> <td data-bbox="1211 1675 1352 1793"> IPv6 Subnet field </td> <td data-bbox="1352 1675 1487 1793"></td> </tr> </tbody> </table>	Name	Description			<table border="1"> <thead> <tr> <th data-bbox="1211 327 1352 373">Name</th> <th data-bbox="1352 327 1487 373">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1211 373 1352 489"></td> <td data-bbox="1352 373 1487 489">ID value is always <i>none</i>.</td> </tr> </tbody> </table>	Name	Description		ID value is always <i>none</i> .			Segment drop-down list	You can select any one segment from the drop-down list. <ul style="list-style-type: none"> • API • Management • Tenant • CIMC • Storage • External • Provider (optional) <p>Note Some segments do not need some of the values listed in the preceding points.</p>		Subnet field	Enter the IPv4 address for the subnet.		IPv6 Subnet field		
Name	Description																					
	<table border="1"> <thead> <tr> <th data-bbox="1211 327 1352 373">Name</th> <th data-bbox="1352 327 1487 373">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1211 373 1352 489"></td> <td data-bbox="1352 373 1487 489">ID value is always <i>none</i>.</td> </tr> </tbody> </table>	Name	Description		ID value is always <i>none</i> .																	
Name	Description																					
	ID value is always <i>none</i> .																					
	Segment drop-down list	You can select any one segment from the drop-down list. <ul style="list-style-type: none"> • API • Management • Tenant • CIMC • Storage • External • Provider (optional) <p>Note Some segments do not need some of the values listed in the preceding points.</p>																				
	Subnet field	Enter the IPv4 address for the subnet.																				
	IPv6 Subnet field																					

	Command or Action	Purpose		
		Name	Description	
			Name	Description
				Enter IPv6 address. This field is available only for Management provision and API.
			Gateway field	Enter the IPv4 address for the Gateway.
			IPv6 Gateway field	Enter IPv6 gateway. This field is available only for Management provision and API network.
			Pool field	Enter the pool information in the following format. For example: 10.30.1.1 or 10.30.1.1 to 10.30.1.12
			IPv6 Pool field	

	Command or Action	Purpose												
		<table border="1"> <thead> <tr> <th data-bbox="927 275 1208 327">Name</th> <th colspan="2" data-bbox="1208 275 1485 327">Description</th> </tr> <tr> <td data-bbox="927 327 1208 884"></td> <th data-bbox="1208 327 1352 380">Name</th> <th data-bbox="1352 327 1485 380">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 380 1208 884"></td> <td data-bbox="1208 380 1352 821"></td> <td data-bbox="1352 380 1485 821"> Enter the pool information in the following format. For example: 15C11025210 This field is only available for the Mgmt Provision </td> </tr> <tr> <td colspan="3" data-bbox="1208 821 1485 884">Click Save.</td> </tr> </tbody> </table> <p data-bbox="854 898 1494 1033">5. On the Servers and Roles page of the Cisco VIM Suite wizard, you see a pre-populated table filled with Roles: Control, Compute and Block Storage (Only if CEPH Dedicated is selected in Blueprint Initial Setup.</p>	Name	Description			Name	Description			Enter the pool information in the following format. For example: 15C11025210 This field is only available for the Mgmt Provision	Click Save .		
Name	Description													
	Name	Description												
		Enter the pool information in the following format. For example: 15C11025210 This field is only available for the Mgmt Provision												
Click Save .														




	Command or Action	Purpose						
		 <table border="1" data-bbox="966 1197 1526 1459"> <thead> <tr> <th data-bbox="966 1197 1242 1249">Name</th> <th data-bbox="1242 1197 1526 1249">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 1249 1242 1333">Server User Name field</td> <td data-bbox="1242 1249 1526 1333">Enter the username of the server.</td> </tr> <tr> <td data-bbox="966 1333 1242 1459">Disable Hyperthreading</td> <td data-bbox="1242 1333 1526 1459">Default value is false. You can set it as true or false.</td> </tr> </tbody> </table>	Name	Description	Server User Name field	Enter the username of the server.	Disable Hyperthreading	Default value is false. You can set it as true or false.
Name	Description							
Server User Name field	Enter the username of the server.							
Disable Hyperthreading	Default value is false. You can set it as true or false.							

	Command or Action	Purpose	
		Name	Description
		Cobbler	


	Command or Action	Purpose																	
		<table border="1"> <thead> <tr> <th data-bbox="885 273 1250 325">Name</th> <th data-bbox="1250 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 325 1250 1860"></td> <td data-bbox="1250 325 1534 409"> Enter the Cobbler details in the following fields: </td> </tr> <tr> <td data-bbox="885 409 1250 462"> <table border="1"> <thead> <tr> <th data-bbox="885 409 1250 462">Name</th> <th data-bbox="1250 409 1534 462">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 462 1250 955"> Cobbler Timeout field </td> <td data-bbox="1250 462 1534 955"> The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120. </td> </tr> <tr> <td data-bbox="885 955 1250 1102"> Block Storage Kickstart field </td> <td data-bbox="1250 955 1534 1102"> Kickstart file for Storage Node. </td> </tr> <tr> <td data-bbox="885 1102 1250 1606"> Admin Password Hash field </td> <td data-bbox="1250 1102 1534 1606"> Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters. </td> </tr> <tr> <td data-bbox="885 1606 1250 1816"> Cobbler Username field </td> <td data-bbox="1250 1606 1534 1816"> Enter the cobbler username to access the cobbler server. </td> </tr> <tr> <td data-bbox="885 1816 1250 1860"> Control </td> <td data-bbox="1250 1816 1534 1860"> Kickstart </td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		Enter the Cobbler details in the following fields:	<table border="1"> <thead> <tr> <th data-bbox="885 409 1250 462">Name</th> <th data-bbox="1250 409 1534 462">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 462 1250 955"> Cobbler Timeout field </td> <td data-bbox="1250 462 1534 955"> The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120. </td> </tr> <tr> <td data-bbox="885 955 1250 1102"> Block Storage Kickstart field </td> <td data-bbox="1250 955 1534 1102"> Kickstart file for Storage Node. </td> </tr> <tr> <td data-bbox="885 1102 1250 1606"> Admin Password Hash field </td> <td data-bbox="1250 1102 1534 1606"> Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters. </td> </tr> <tr> <td data-bbox="885 1606 1250 1816"> Cobbler Username field </td> <td data-bbox="1250 1606 1534 1816"> Enter the cobbler username to access the cobbler server. </td> </tr> <tr> <td data-bbox="885 1816 1250 1860"> Control </td> <td data-bbox="1250 1816 1534 1860"> Kickstart </td> </tr> </tbody> </table>	Name	Description	Cobbler Timeout field	The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120.	Block Storage Kickstart field	Kickstart file for Storage Node.	Admin Password Hash field	Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters.	Cobbler Username field	Enter the cobbler username to access the cobbler server.	Control	Kickstart
Name	Description																		
	Enter the Cobbler details in the following fields:																		
<table border="1"> <thead> <tr> <th data-bbox="885 409 1250 462">Name</th> <th data-bbox="1250 409 1534 462">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 462 1250 955"> Cobbler Timeout field </td> <td data-bbox="1250 462 1534 955"> The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120. </td> </tr> <tr> <td data-bbox="885 955 1250 1102"> Block Storage Kickstart field </td> <td data-bbox="1250 955 1534 1102"> Kickstart file for Storage Node. </td> </tr> <tr> <td data-bbox="885 1102 1250 1606"> Admin Password Hash field </td> <td data-bbox="1250 1102 1534 1606"> Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters. </td> </tr> <tr> <td data-bbox="885 1606 1250 1816"> Cobbler Username field </td> <td data-bbox="1250 1606 1534 1816"> Enter the cobbler username to access the cobbler server. </td> </tr> <tr> <td data-bbox="885 1816 1250 1860"> Control </td> <td data-bbox="1250 1816 1534 1860"> Kickstart </td> </tr> </tbody> </table>	Name	Description	Cobbler Timeout field	The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120.	Block Storage Kickstart field	Kickstart file for Storage Node.	Admin Password Hash field	Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters.	Cobbler Username field	Enter the cobbler username to access the cobbler server.	Control	Kickstart							
Name	Description																		
Cobbler Timeout field	The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120.																		
Block Storage Kickstart field	Kickstart file for Storage Node.																		
Admin Password Hash field	Enter the Admin Password. Password must be alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters.																		
Cobbler Username field	Enter the cobbler username to access the cobbler server.																		
Control	Kickstart																		

	Command or Action	Purpose															
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1208 329">Name</th> <th colspan="2" data-bbox="1208 275 1494 329">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 329 1208 497"></td> <td data-bbox="1208 329 1352 384"> <table border="1"> <thead> <tr> <th data-bbox="1208 329 1352 384">Name</th> <th data-bbox="1352 329 1494 384">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1208 384 1352 497">Kickstart field</td> <td data-bbox="1352 384 1494 497">file for Control Node.</td> </tr> <tr> <td data-bbox="1208 497 1352 651">Compute Kickstart field</td> <td data-bbox="1352 497 1494 651">Kickstart file for Compute Node.</td> </tr> <tr> <td data-bbox="1208 651 1352 850">Cobbler Admin Username field</td> <td data-bbox="1352 651 1494 850">Enter the admin username of the Cobbler.</td> </tr> </tbody> </table> </td> <td data-bbox="1352 384 1494 497"></td> </tr> </tbody> </table>	Name	Description			<table border="1"> <thead> <tr> <th data-bbox="1208 329 1352 384">Name</th> <th data-bbox="1352 329 1494 384">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1208 384 1352 497">Kickstart field</td> <td data-bbox="1352 384 1494 497">file for Control Node.</td> </tr> <tr> <td data-bbox="1208 497 1352 651">Compute Kickstart field</td> <td data-bbox="1352 497 1494 651">Kickstart file for Compute Node.</td> </tr> <tr> <td data-bbox="1208 651 1352 850">Cobbler Admin Username field</td> <td data-bbox="1352 651 1494 850">Enter the admin username of the Cobbler.</td> </tr> </tbody> </table>	Name	Description	Kickstart field	file for Control Node.	Compute Kickstart field	Kickstart file for Compute Node.	Cobbler Admin Username field	Enter the admin username of the Cobbler.		
Name	Description																
	<table border="1"> <thead> <tr> <th data-bbox="1208 329 1352 384">Name</th> <th data-bbox="1352 329 1494 384">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1208 384 1352 497">Kickstart field</td> <td data-bbox="1352 384 1494 497">file for Control Node.</td> </tr> <tr> <td data-bbox="1208 497 1352 651">Compute Kickstart field</td> <td data-bbox="1352 497 1494 651">Kickstart file for Compute Node.</td> </tr> <tr> <td data-bbox="1208 651 1352 850">Cobbler Admin Username field</td> <td data-bbox="1352 651 1494 850">Enter the admin username of the Cobbler.</td> </tr> </tbody> </table>	Name	Description	Kickstart field	file for Control Node.	Compute Kickstart field	Kickstart file for Compute Node.	Cobbler Admin Username field	Enter the admin username of the Cobbler.								
Name	Description																
Kickstart field	file for Control Node.																
Compute Kickstart field	Kickstart file for Compute Node.																
Cobbler Admin Username field	Enter the admin username of the Cobbler.																

	Command or Action	Purpose	
		Name	Description
		Add Entry to Servers and Roles	

	Command or Action	Purpose														
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1208 323">Name</th> <th data-bbox="1208 275 1494 323">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 323 1208 1869"></td> <td data-bbox="1208 323 1494 1869"> <p>Click Edit or + to add a new server and role to the table.</p> <p>Server And Roles</p>  <table border="1"> <tbody> <tr> <td data-bbox="1208 1276 1354 1402">Server Name</td> <td data-bbox="1354 1276 1494 1402">Enter a server name.</td> </tr> <tr> <td data-bbox="1208 1402 1354 1621">Server Type drop-down list</td> <td data-bbox="1354 1402 1494 1621">Choose Blade or Rack from the drop-down list.</td> </tr> <tr> <td data-bbox="1208 1621 1354 1738">Rack ID</td> <td data-bbox="1354 1621 1494 1738">The Rack ID for the server.</td> </tr> <tr> <td data-bbox="1208 1738 1354 1831">Chassis ID</td> <td data-bbox="1354 1738 1494 1831">Enter a Chassis ID.</td> </tr> <tr> <td data-bbox="1208 1831 1354 1869">If Rack is</td> <td data-bbox="1354 1831 1494 1869">Enter a</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>Click Edit or + to add a new server and role to the table.</p> <p>Server And Roles</p>  <table border="1"> <tbody> <tr> <td data-bbox="1208 1276 1354 1402">Server Name</td> <td data-bbox="1354 1276 1494 1402">Enter a server name.</td> </tr> <tr> <td data-bbox="1208 1402 1354 1621">Server Type drop-down list</td> <td data-bbox="1354 1402 1494 1621">Choose Blade or Rack from the drop-down list.</td> </tr> <tr> <td data-bbox="1208 1621 1354 1738">Rack ID</td> <td data-bbox="1354 1621 1494 1738">The Rack ID for the server.</td> </tr> <tr> <td data-bbox="1208 1738 1354 1831">Chassis ID</td> <td data-bbox="1354 1738 1494 1831">Enter a Chassis ID.</td> </tr> <tr> <td data-bbox="1208 1831 1354 1869">If Rack is</td> <td data-bbox="1354 1831 1494 1869">Enter a</td> </tr> </tbody> </table>	Server Name	Enter a server name.	Server Type drop-down list	Choose Blade or Rack from the drop-down list.	Rack ID	The Rack ID for the server.	Chassis ID	Enter a Chassis ID.	If Rack is	Enter a
Name	Description															
	<p>Click Edit or + to add a new server and role to the table.</p> <p>Server And Roles</p>  <table border="1"> <tbody> <tr> <td data-bbox="1208 1276 1354 1402">Server Name</td> <td data-bbox="1354 1276 1494 1402">Enter a server name.</td> </tr> <tr> <td data-bbox="1208 1402 1354 1621">Server Type drop-down list</td> <td data-bbox="1354 1402 1494 1621">Choose Blade or Rack from the drop-down list.</td> </tr> <tr> <td data-bbox="1208 1621 1354 1738">Rack ID</td> <td data-bbox="1354 1621 1494 1738">The Rack ID for the server.</td> </tr> <tr> <td data-bbox="1208 1738 1354 1831">Chassis ID</td> <td data-bbox="1354 1738 1494 1831">Enter a Chassis ID.</td> </tr> <tr> <td data-bbox="1208 1831 1354 1869">If Rack is</td> <td data-bbox="1354 1831 1494 1869">Enter a</td> </tr> </tbody> </table>	Server Name	Enter a server name.	Server Type drop-down list	Choose Blade or Rack from the drop-down list.	Rack ID	The Rack ID for the server.	Chassis ID	Enter a Chassis ID.	If Rack is	Enter a					
Server Name	Enter a server name.															
Server Type drop-down list	Choose Blade or Rack from the drop-down list.															
Rack ID	The Rack ID for the server.															
Chassis ID	Enter a Chassis ID.															
If Rack is	Enter a															


	Command or Action	Purpose															
		<table border="1"> <thead> <tr> <th data-bbox="889 273 1247 325">Name</th> <th data-bbox="1247 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="889 325 1247 472"></td> <td data-bbox="1247 325 1534 472"> chosen, the Rack Unit ID field is displayed. Rack Unit ID. </td> </tr> <tr> <td data-bbox="889 472 1247 651"></td> <td data-bbox="1247 472 1534 651"> If Blade is chosen, the Blade ID field is displayed. Enter a Blade ID. </td> </tr> <tr> <td data-bbox="889 651 1247 1060"></td> <td data-bbox="1247 651 1534 1060"> Select the Role from the drop-down list. If Server type is Blade then select Control and Compute. If server is Rack then select Block Storage. </td> </tr> <tr> <td data-bbox="889 1060 1247 1501"></td> <td data-bbox="1247 1060 1534 1501"> Management IP It is an optional field but if provided for one server then it is mandatory to provide details for other Servers as well. </td> </tr> <tr> <td data-bbox="889 1501 1247 1648"></td> <td data-bbox="1247 1501 1534 1648"> Management IPv6 Enter the Management IPv6 Address. </td> </tr> <tr> <td data-bbox="889 1648 1247 1717"></td> <td data-bbox="1247 1648 1534 1717"> Click Save. </td> </tr> </tbody> </table>	Name	Description		chosen, the Rack Unit ID field is displayed. Rack Unit ID.		If Blade is chosen, the Blade ID field is displayed. Enter a Blade ID.		Select the Role from the drop-down list. If Server type is Blade then select Control and Compute . If server is Rack then select Block Storage .		Management IP It is an optional field but if provided for one server then it is mandatory to provide details for other Servers as well.		Management IPv6 Enter the Management IPv6 Address.		Click Save .	<p>6. Click ToR Switch checkbox in Blueprint Initial Setup to enable the TOR SWITCH configuration page. It is an Optional section in Blueprint Setup,</p>
Name	Description																
	chosen, the Rack Unit ID field is displayed. Rack Unit ID.																
	If Blade is chosen, the Blade ID field is displayed. Enter a Blade ID.																
	Select the Role from the drop-down list. If Server type is Blade then select Control and Compute . If server is Rack then select Block Storage .																
	Management IP It is an optional field but if provided for one server then it is mandatory to provide details for other Servers as well.																
	Management IPv6 Enter the Management IPv6 Address.																
	Click Save .																




	Command or Action	Purpose				
		<p>but when all the fields are filled it is a part of the Blueprint.</p>  <table border="1" data-bbox="922 1060 1489 1232"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Configure ToR optional checkbox.</td> <td>Enabling this checkbox, changes the configure ToR section from false to true.</td> </tr> </tbody> </table>	Name	Description	Configure ToR optional checkbox.	Enabling this checkbox, changes the configure ToR section from false to true.
Name	Description					
Configure ToR optional checkbox.	Enabling this checkbox, changes the configure ToR section from false to true.					

	Command or Action	Purpose	
		Name	Description
		ToR Switch Information mandatory table.	




	Command or Action	Purpose														
		<table border="1"> <thead> <tr> <th data-bbox="927 275 1187 323">Name</th> <th data-bbox="1187 275 1485 323">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 323 1187 1858"></td> <td data-bbox="1187 323 1485 1858"> <p>Click (+) to add information for ToR Switch.</p> <p>Switch Details</p> <p>Hostname * Enter Switch Hostname</p> <p>Username * Enter Switch Username</p> <p>Password * Enter Password</p> <p>SSH-IP * Enter IP Address</p> <p>SSN Num Enter SSN Num</p> <p>VPC Peer Keepalive Enter IP Address</p> <p>VPC Domain Enter VPC Domain</p> <p>VPC Peer Port Info Enter VPC Port</p> <p>VPC Peer VLAN Info Enter VPC VLAN Info</p> <p>BR Management Port Info Enter BR Port Info</p> <p>BR Management PO Info Enter BR PO Info</p> <p>Save Cancel</p> <table border="1"> <thead> <tr> <th data-bbox="1195 1478 1341 1528">Name</th> <th data-bbox="1341 1478 1485 1528">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1195 1528 1341 1623">Hostname</td> <td data-bbox="1341 1528 1485 1623">ToR switch hostname.</td> </tr> <tr> <td data-bbox="1195 1623 1341 1717">Username</td> <td data-bbox="1341 1623 1485 1717">ToR switch username.</td> </tr> <tr> <td data-bbox="1195 1717 1341 1812">Password</td> <td data-bbox="1341 1717 1485 1812">ToR switch password.</td> </tr> <tr> <td data-bbox="1195 1812 1341 1858">SSH IP</td> <td data-bbox="1341 1812 1485 1858">ToR switch</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>Click (+) to add information for ToR Switch.</p> <p>Switch Details</p> <p>Hostname * Enter Switch Hostname</p> <p>Username * Enter Switch Username</p> <p>Password * Enter Password</p> <p>SSH-IP * Enter IP Address</p> <p>SSN Num Enter SSN Num</p> <p>VPC Peer Keepalive Enter IP Address</p> <p>VPC Domain Enter VPC Domain</p> <p>VPC Peer Port Info Enter VPC Port</p> <p>VPC Peer VLAN Info Enter VPC VLAN Info</p> <p>BR Management Port Info Enter BR Port Info</p> <p>BR Management PO Info Enter BR PO Info</p> <p>Save Cancel</p> <table border="1"> <thead> <tr> <th data-bbox="1195 1478 1341 1528">Name</th> <th data-bbox="1341 1478 1485 1528">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1195 1528 1341 1623">Hostname</td> <td data-bbox="1341 1528 1485 1623">ToR switch hostname.</td> </tr> <tr> <td data-bbox="1195 1623 1341 1717">Username</td> <td data-bbox="1341 1623 1485 1717">ToR switch username.</td> </tr> <tr> <td data-bbox="1195 1717 1341 1812">Password</td> <td data-bbox="1341 1717 1485 1812">ToR switch password.</td> </tr> <tr> <td data-bbox="1195 1812 1341 1858">SSH IP</td> <td data-bbox="1341 1812 1485 1858">ToR switch</td> </tr> </tbody> </table>	Name	Description	Hostname	ToR switch hostname.	Username	ToR switch username.	Password	ToR switch password.	SSH IP	ToR switch
Name	Description															
	<p>Click (+) to add information for ToR Switch.</p> <p>Switch Details</p> <p>Hostname * Enter Switch Hostname</p> <p>Username * Enter Switch Username</p> <p>Password * Enter Password</p> <p>SSH-IP * Enter IP Address</p> <p>SSN Num Enter SSN Num</p> <p>VPC Peer Keepalive Enter IP Address</p> <p>VPC Domain Enter VPC Domain</p> <p>VPC Peer Port Info Enter VPC Port</p> <p>VPC Peer VLAN Info Enter VPC VLAN Info</p> <p>BR Management Port Info Enter BR Port Info</p> <p>BR Management PO Info Enter BR PO Info</p> <p>Save Cancel</p> <table border="1"> <thead> <tr> <th data-bbox="1195 1478 1341 1528">Name</th> <th data-bbox="1341 1478 1485 1528">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="1195 1528 1341 1623">Hostname</td> <td data-bbox="1341 1528 1485 1623">ToR switch hostname.</td> </tr> <tr> <td data-bbox="1195 1623 1341 1717">Username</td> <td data-bbox="1341 1623 1485 1717">ToR switch username.</td> </tr> <tr> <td data-bbox="1195 1717 1341 1812">Password</td> <td data-bbox="1341 1717 1485 1812">ToR switch password.</td> </tr> <tr> <td data-bbox="1195 1812 1341 1858">SSH IP</td> <td data-bbox="1341 1812 1485 1858">ToR switch</td> </tr> </tbody> </table>	Name	Description	Hostname	ToR switch hostname.	Username	ToR switch username.	Password	ToR switch password.	SSH IP	ToR switch					
Name	Description															
Hostname	ToR switch hostname.															
Username	ToR switch username.															
Password	ToR switch password.															
SSH IP	ToR switch															

	Command or Action	Purpose																																		
		<table border="1"> <thead> <tr> <th data-bbox="889 275 1224 323">Name</th> <th colspan="2" data-bbox="1224 275 1534 323">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="889 323 1224 407"></td> <td data-bbox="1224 323 1377 407"></td> <td data-bbox="1377 323 1534 407">SSH IP Address.</td> </tr> <tr> <td data-bbox="889 407 1224 491"></td> <td data-bbox="1224 407 1377 491">SSN Num</td> <td data-bbox="1377 407 1534 491">ToR switch ssn num.</td> </tr> <tr> <td data-bbox="889 491 1224 711"></td> <td data-bbox="1224 491 1377 711">VPC Peer Keepalive</td> <td data-bbox="1377 491 1534 711">Peer Management IP. You do not define if there is no peer.</td> </tr> <tr> <td data-bbox="889 711 1224 869"></td> <td data-bbox="1224 711 1377 869">VPC Domain</td> <td data-bbox="1377 711 1534 869">Do not define if peer is absent.</td> </tr> <tr> <td data-bbox="889 869 1224 984"></td> <td data-bbox="1224 869 1377 984">VPC Peer Port Info</td> <td data-bbox="1377 869 1534 984">Interface for vpc peer ports.</td> </tr> <tr> <td data-bbox="889 984 1224 1163"></td> <td data-bbox="1224 984 1377 1163">BR Management Port Info</td> <td data-bbox="1377 984 1534 1163">Management interface of the management node.</td> </tr> <tr> <td data-bbox="889 1163 1224 1415"></td> <td data-bbox="1224 1163 1377 1415">BR Management PO Info</td> <td data-bbox="1377 1163 1534 1415">Port channel number for management interface of the management node.</td> </tr> <tr> <td data-bbox="889 1415 1224 1480"></td> <td colspan="2" data-bbox="1224 1415 1534 1480">ClickSave.</td> </tr> </tbody> </table>	Name	Description				SSH IP Address.		SSN Num	ToR switch ssn num.		VPC Peer Keepalive	Peer Management IP. You do not define if there is no peer.		VPC Domain	Do not define if peer is absent.		VPC Peer Port Info	Interface for vpc peer ports.		BR Management Port Info	Management interface of the management node.		BR Management PO Info	Port channel number for management interface of the management node.		ClickSave.		<table border="1"> <tbody> <tr> <td data-bbox="1224 1480 1377 1633">On clicking save button, Add ToR Info Connected to Fabric field is visible.</td> <td data-bbox="1377 1480 1534 1633">Port Channel field.</td> <td data-bbox="1534 1480 1624 1633">Enter the Port Channel input.</td> </tr> <tr> <td data-bbox="1224 1633 1377 1753"></td> <td data-bbox="1377 1633 1534 1753">Switch Name field.</td> <td data-bbox="1534 1633 1624 1753">Enter the name of the Switch.</td> </tr> </tbody> </table>	On clicking save button, Add ToR Info Connected to Fabric field is visible.	Port Channel field.	Enter the Port Channel input.		Switch Name field.	Enter the name of the Switch.
Name	Description																																			
		SSH IP Address.																																		
	SSN Num	ToR switch ssn num.																																		
	VPC Peer Keepalive	Peer Management IP. You do not define if there is no peer.																																		
	VPC Domain	Do not define if peer is absent.																																		
	VPC Peer Port Info	Interface for vpc peer ports.																																		
	BR Management Port Info	Management interface of the management node.																																		
	BR Management PO Info	Port channel number for management interface of the management node.																																		
	ClickSave.																																			
On clicking save button, Add ToR Info Connected to Fabric field is visible.	Port Channel field.	Enter the Port Channel input.																																		
	Switch Name field.	Enter the name of the Switch.																																		
		<p>7. Click NFVI Monitoring checkbox in Blueprint Initial Setup to enable the NFVI Monitoring configuration tab.</p>																																		




	Command or Action	Purpose																
		 <table border="1" data-bbox="925 913 1489 1589"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Admin IP</td> <td>IP Address of Control Center VM</td> </tr> <tr> <td>Management VIP</td> <td>VIP for ceilometer/dispatcher to use, must be unique across VIM Pod</td> </tr> <tr> <td>Host Name</td> <td>Hostname of Collector VM</td> </tr> <tr> <td>Password</td> <td>Password of Collector VM</td> </tr> <tr> <td>CCUSER Password</td> <td>Password of CCUSER</td> </tr> <tr> <td>Admin IP</td> <td>SSH IP of Collector VM</td> </tr> <tr> <td>Management IP</td> <td>Management IP of Collector VM</td> </tr> </tbody> </table>	Name	Description	Admin IP	IP Address of Control Center VM	Management VIP	VIP for ceilometer/dispatcher to use, must be unique across VIM Pod	Host Name	Hostname of Collector VM	Password	Password of Collector VM	CCUSER Password	Password of CCUSER	Admin IP	SSH IP of Collector VM	Management IP	Management IP of Collector VM
Name	Description																	
Admin IP	IP Address of Control Center VM																	
Management VIP	VIP for ceilometer/dispatcher to use, must be unique across VIM Pod																	
Host Name	Hostname of Collector VM																	
Password	Password of Collector VM																	
CCUSER Password	Password of CCUSER																	
Admin IP	SSH IP of Collector VM																	
Management IP	Management IP of Collector VM																	

	Command or Action	Purpose										
		<table border="1"> <thead> <tr> <th data-bbox="966 273 1242 325">Name</th> <th data-bbox="1242 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 325 1242 1480"> Collector ToR Connections </td> <td data-bbox="1242 325 1534 1480"> <ol style="list-style-type: none"> Click on (+) icon to Add Collector ToR Connections. Select the ToR switches from list to add the information. It is optional and available for ToR type NCS-5500 For now, it supports adding only one Collector ToR Connection <p>Add Collector Tor Connections</p>  <table border="1"> <tr> <td>Port Channel</td> <td>Enter port channel.</td> </tr> <tr> <td>Switch - test-to</td> <td>Enter port number, E.g:eth1/15.</td> </tr> </table> <p>Click Save</p> </td> </tr> <tr> <td data-bbox="966 1480 1242 1564"> Rabbit MQ User Name </td> <td data-bbox="1242 1480 1534 1564"> Enter Rabbit MQ username. </td> </tr> </tbody> </table> <p>8. Click OpenStack Setup tab to advance to the OpenStack Setup Configuration page. On the OpenStack Setup page of the Cisco VIM Unified Management wizard, complete the following fields:</p>	Name	Description	Collector ToR Connections	<ol style="list-style-type: none"> Click on (+) icon to Add Collector ToR Connections. Select the ToR switches from list to add the information. It is optional and available for ToR type NCS-5500 For now, it supports adding only one Collector ToR Connection <p>Add Collector Tor Connections</p>  <table border="1"> <tr> <td>Port Channel</td> <td>Enter port channel.</td> </tr> <tr> <td>Switch - test-to</td> <td>Enter port number, E.g:eth1/15.</td> </tr> </table> <p>Click Save</p>	Port Channel	Enter port channel.	Switch - test-to	Enter port number, E.g:eth1/15.	Rabbit MQ User Name	Enter Rabbit MQ username.
Name	Description											
Collector ToR Connections	<ol style="list-style-type: none"> Click on (+) icon to Add Collector ToR Connections. Select the ToR switches from list to add the information. It is optional and available for ToR type NCS-5500 For now, it supports adding only one Collector ToR Connection <p>Add Collector Tor Connections</p>  <table border="1"> <tr> <td>Port Channel</td> <td>Enter port channel.</td> </tr> <tr> <td>Switch - test-to</td> <td>Enter port number, E.g:eth1/15.</td> </tr> </table> <p>Click Save</p>	Port Channel	Enter port channel.	Switch - test-to	Enter port number, E.g:eth1/15.							
Port Channel	Enter port channel.											
Switch - test-to	Enter port number, E.g:eth1/15.											
Rabbit MQ User Name	Enter Rabbit MQ username.											

	Command or Action	Purpose														
		<table border="1"> <thead> <tr> <th data-bbox="927 275 1187 329">Name</th> <th data-bbox="1187 275 1492 329">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 329 1187 884"> HA Proxy </td> <td data-bbox="1187 329 1492 884"> Fill in the following details:  </td> </tr> <tr> <td data-bbox="1187 884 1344 1064"> External VIP Address field </td> <td data-bbox="1344 884 1492 1064"> Enter the IP address of the External VIP. </td> </tr> <tr> <td data-bbox="1187 1064 1344 1247"> External VIP Address IPv6 field </td> <td data-bbox="1344 1064 1492 1247"> Enter the IPv6 address of the External VIP. </td> </tr> <tr> <td data-bbox="1187 1247 1344 1367"> Virtual Router ID field </td> <td data-bbox="1344 1247 1492 1367"> Enter the Router ID for the HA. </td> </tr> <tr> <td data-bbox="1187 1367 1344 1549"> Internal VIP Address IPv6 field </td> <td data-bbox="1344 1367 1492 1549"> Enter the IPv6 address of the Internal IP. </td> </tr> <tr> <td data-bbox="1187 1549 1344 1717"> Internal VIP Address field </td> <td data-bbox="1344 1549 1492 1717"> Enter the IP address of the Internal VIP. </td> </tr> </tbody> </table>	Name	Description	HA Proxy	Fill in the following details: 	External VIP Address field	Enter the IP address of the External VIP.	External VIP Address IPv6 field	Enter the IPv6 address of the External VIP.	Virtual Router ID field	Enter the Router ID for the HA.	Internal VIP Address IPv6 field	Enter the IPv6 address of the Internal IP.	Internal VIP Address field	Enter the IP address of the Internal VIP.
Name	Description															
HA Proxy	Fill in the following details: 															
External VIP Address field	Enter the IP address of the External VIP.															
External VIP Address IPv6 field	Enter the IPv6 address of the External VIP.															
Virtual Router ID field	Enter the Router ID for the HA.															
Internal VIP Address IPv6 field	Enter the IPv6 address of the Internal IP.															
Internal VIP Address field	Enter the IP address of the Internal VIP.															

	Command or Action	Purpose								
		<table border="1"> <thead> <tr> <th data-bbox="889 273 1226 331">Name</th> <th data-bbox="1226 273 1534 331">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="889 331 1226 1218">Keystone</td> <td data-bbox="1226 331 1534 1218"> <p>The following are the Pre-populated field values. This option is always set to be true.</p>  <table border="1" data-bbox="1234 976 1526 1207"> <tbody> <tr> <td data-bbox="1234 976 1380 1081">Admin Username field</td> <td data-bbox="1380 976 1526 1081">admin</td> </tr> <tr> <td data-bbox="1234 1081 1380 1207">Admin Tenant Name field</td> <td data-bbox="1380 1081 1526 1207">admin</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description	Keystone	<p>The following are the Pre-populated field values. This option is always set to be true.</p>  <table border="1" data-bbox="1234 976 1526 1207"> <tbody> <tr> <td data-bbox="1234 976 1380 1081">Admin Username field</td> <td data-bbox="1380 976 1526 1081">admin</td> </tr> <tr> <td data-bbox="1234 1081 1380 1207">Admin Tenant Name field</td> <td data-bbox="1380 1081 1526 1207">admin</td> </tr> </tbody> </table>	Admin Username field	admin	Admin Tenant Name field	admin
Name	Description									
Keystone	<p>The following are the Pre-populated field values. This option is always set to be true.</p>  <table border="1" data-bbox="1234 976 1526 1207"> <tbody> <tr> <td data-bbox="1234 976 1380 1081">Admin Username field</td> <td data-bbox="1380 976 1526 1081">admin</td> </tr> <tr> <td data-bbox="1234 1081 1380 1207">Admin Tenant Name field</td> <td data-bbox="1380 1081 1526 1207">admin</td> </tr> </tbody> </table>	Admin Username field	admin	Admin Tenant Name field	admin					
Admin Username field	admin									
Admin Tenant Name field	admin									

	Command or Action	Purpose	
		Name	Description
		LDAP (Only if Keystonev3 is enabled) Note This option is only available with Keystone v3	

	Command or Action	Purpose														
		<table border="1"> <thead> <tr> <th data-bbox="885 273 1226 325">Name</th> <th data-bbox="1226 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 325 1226 1837"></td> <td data-bbox="1226 325 1534 1837"> <p>This is available only when Keystone v3 and LDAP both are enabled under <i>Optional Features and Services</i> in Blueprint Initial Setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1226 1218 1372 1333">Domain Name field</td> <td data-bbox="1372 1218 1534 1333">Enter the Domain name.</td> </tr> <tr> <td data-bbox="1226 1333 1372 1459">Object Class for Users field</td> <td data-bbox="1372 1333 1534 1459">Enter a string as input.</td> </tr> <tr> <td data-bbox="1226 1459 1372 1585">Object Class for Groups field</td> <td data-bbox="1372 1459 1534 1585">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1585 1372 1732">Domain Name Tree for Users field</td> <td data-bbox="1372 1585 1534 1732">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1732 1372 1837">Domain Name Tree for Groups</td> <td data-bbox="1372 1732 1534 1837">Enter a string.</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>This is available only when Keystone v3 and LDAP both are enabled under <i>Optional Features and Services</i> in Blueprint Initial Setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1226 1218 1372 1333">Domain Name field</td> <td data-bbox="1372 1218 1534 1333">Enter the Domain name.</td> </tr> <tr> <td data-bbox="1226 1333 1372 1459">Object Class for Users field</td> <td data-bbox="1372 1333 1534 1459">Enter a string as input.</td> </tr> <tr> <td data-bbox="1226 1459 1372 1585">Object Class for Groups field</td> <td data-bbox="1372 1459 1534 1585">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1585 1372 1732">Domain Name Tree for Users field</td> <td data-bbox="1372 1585 1534 1732">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1732 1372 1837">Domain Name Tree for Groups</td> <td data-bbox="1372 1732 1534 1837">Enter a string.</td> </tr> </tbody> </table>	Domain Name field	Enter the Domain name.	Object Class for Users field	Enter a string as input.	Object Class for Groups field	Enter a string.	Domain Name Tree for Users field	Enter a string.	Domain Name Tree for Groups	Enter a string.
Name	Description															
	<p>This is available only when Keystone v3 and LDAP both are enabled under <i>Optional Features and Services</i> in Blueprint Initial Setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1226 1218 1372 1333">Domain Name field</td> <td data-bbox="1372 1218 1534 1333">Enter the Domain name.</td> </tr> <tr> <td data-bbox="1226 1333 1372 1459">Object Class for Users field</td> <td data-bbox="1372 1333 1534 1459">Enter a string as input.</td> </tr> <tr> <td data-bbox="1226 1459 1372 1585">Object Class for Groups field</td> <td data-bbox="1372 1459 1534 1585">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1585 1372 1732">Domain Name Tree for Users field</td> <td data-bbox="1372 1585 1534 1732">Enter a string.</td> </tr> <tr> <td data-bbox="1226 1732 1372 1837">Domain Name Tree for Groups</td> <td data-bbox="1372 1732 1534 1837">Enter a string.</td> </tr> </tbody> </table>	Domain Name field	Enter the Domain name.	Object Class for Users field	Enter a string as input.	Object Class for Groups field	Enter a string.	Domain Name Tree for Users field	Enter a string.	Domain Name Tree for Groups	Enter a string.					
Domain Name field	Enter the Domain name.															
Object Class for Users field	Enter a string as input.															
Object Class for Groups field	Enter a string.															
Domain Name Tree for Users field	Enter a string.															
Domain Name Tree for Groups	Enter a string.															

	Command or Action	Purpose	
		Name	Description
		field	
		Suffix for Domain Name field	Enter a string.
		URL field	Enter a URL with ending port number.
		Domain Name of bind user field	Enter a string.
		Password field	Enter Password as string format.
		User Filter field	Enter filter name as string.
		User ID Attribute field	Enter a string.
		User Name Attribute field	Enter a string.
		User Mail Attribute field	Enter a string.
		Group Name Attribute field	Enter a string.

	Command or Action	Purpose	
		Name	Description
		Neutron	



	Command or Action	Purpose										
		<table border="1"> <thead> <tr> <th data-bbox="927 275 1192 329">Name</th> <th data-bbox="1192 275 1492 329">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 329 1192 1003"></td> <td data-bbox="1192 329 1492 1003"> <p>Neutron fields change on the basis of <i>Tenant Network Type</i> selection from Blueprint Initial Setup. Following are the options available for Neutron for OVS/VLAN:</p>  </td> </tr> <tr> <td data-bbox="1192 1003 1341 1350">Tenant Network Type field</td> <td data-bbox="1341 1003 1492 1350">It is Auto-filled based on the <i>Tenant Network Type</i> selected in the Blueprint Initial Setup page.</td> </tr> <tr> <td data-bbox="1192 1350 1341 1696">Mechanism Drivers field</td> <td data-bbox="1341 1350 1492 1696">It is Auto-filled based on the <i>Tenant Network Type</i> selected in Blueprint Initial Setup page.</td> </tr> <tr> <td data-bbox="1192 1696 1341 1862">NFV Hosts field</td> <td data-bbox="1341 1696 1492 1862">It is Auto-filled with the Compute you added</td> </tr> </tbody> </table>	Name	Description		<p>Neutron fields change on the basis of <i>Tenant Network Type</i> selection from Blueprint Initial Setup. Following are the options available for Neutron for OVS/VLAN:</p> 	Tenant Network Type field	It is Auto-filled based on the <i>Tenant Network Type</i> selected in the Blueprint Initial Setup page.	Mechanism Drivers field	It is Auto-filled based on the <i>Tenant Network Type</i> selected in Blueprint Initial Setup page.	NFV Hosts field	It is Auto-filled with the Compute you added
Name	Description											
	<p>Neutron fields change on the basis of <i>Tenant Network Type</i> selection from Blueprint Initial Setup. Following are the options available for Neutron for OVS/VLAN:</p> 											
Tenant Network Type field	It is Auto-filled based on the <i>Tenant Network Type</i> selected in the Blueprint Initial Setup page.											
Mechanism Drivers field	It is Auto-filled based on the <i>Tenant Network Type</i> selected in Blueprint Initial Setup page.											
NFV Hosts field	It is Auto-filled with the Compute you added											





	Command or Action	Purpose	
		Name	Description
			<p>in Server and Roles.</p> <p>If you select All in this section NFV_HOSTS: ALL is added to the Blueprint or you can select one particular compute. For Example: NFV_HOSTS: compute-svr-1, compute-svr-2</p>
		<p>Tenant VLAN Ranges field</p>	<p>List of ranges separated by comma form start:end.</p>
		<p>Provider VLAN Ranges field</p>	<p>List of ranges separated by comma form start:end.</p>
		<p>VM High Page Size (available for NFV_HOSTS option) field</p>	<p>2M or 1G</p>
		<p>Enable Jumbo Frames field</p>	<p>Enable the checkbox.</p>

	Command or Action	Purpose	
		Name	Description
			For Tenant Network Type, Linux Bridge everything remains the same but Tenant VLAN Ranges is removed.

	Command or Action	Purpose	
		Name	Description
		CEPH	




	Command or Action	Purpose																		
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1190 331">Name</th> <th data-bbox="1190 275 1492 331">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 331 1190 1839"></td> <td data-bbox="1190 331 1492 1839"> <p>1. 1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1247 898 1341 1010">CEPH Mode</td> <td data-bbox="1341 898 1492 1010">By default Ceph Mode is Central.</td> </tr> <tr> <td data-bbox="1247 1010 1341 1094">Cluster ID</td> <td data-bbox="1341 1010 1492 1094">Enter the Cluster ID.</td> </tr> <tr> <td data-bbox="1247 1094 1341 1241">Monitor Host</td> <td data-bbox="1341 1094 1492 1241">Enter the Monitor Host for CEPH</td> </tr> <tr> <td data-bbox="1247 1241 1341 1381">Monitor Members</td> <td data-bbox="1341 1241 1492 1381">Enter the Monitor Members for CEPH</td> </tr> <tr> <td data-bbox="1247 1381 1341 1528">Secret UUID</td> <td data-bbox="1341 1381 1492 1528">Enter the Secret UUID for CEPH</td> </tr> <tr> <td data-bbox="1247 1528 1341 1766">NOVA Boot from</td> <td data-bbox="1341 1528 1492 1766">You can choose CEPH or local from the drop-down list.</td> </tr> <tr> <td data-bbox="1247 1766 1341 1839">NOVA RBD</td> <td data-bbox="1341 1766 1492 1839">Enter the NOVA</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>1. 1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1247 898 1341 1010">CEPH Mode</td> <td data-bbox="1341 898 1492 1010">By default Ceph Mode is Central.</td> </tr> <tr> <td data-bbox="1247 1010 1341 1094">Cluster ID</td> <td data-bbox="1341 1010 1492 1094">Enter the Cluster ID.</td> </tr> <tr> <td data-bbox="1247 1094 1341 1241">Monitor Host</td> <td data-bbox="1341 1094 1492 1241">Enter the Monitor Host for CEPH</td> </tr> <tr> <td data-bbox="1247 1241 1341 1381">Monitor Members</td> <td data-bbox="1341 1241 1492 1381">Enter the Monitor Members for CEPH</td> </tr> <tr> <td data-bbox="1247 1381 1341 1528">Secret UUID</td> <td data-bbox="1341 1381 1492 1528">Enter the Secret UUID for CEPH</td> </tr> <tr> <td data-bbox="1247 1528 1341 1766">NOVA Boot from</td> <td data-bbox="1341 1528 1492 1766">You can choose CEPH or local from the drop-down list.</td> </tr> <tr> <td data-bbox="1247 1766 1341 1839">NOVA RBD</td> <td data-bbox="1341 1766 1492 1839">Enter the NOVA</td> </tr> </tbody> </table>	CEPH Mode	By default Ceph Mode is Central.	Cluster ID	Enter the Cluster ID.	Monitor Host	Enter the Monitor Host for CEPH	Monitor Members	Enter the Monitor Members for CEPH	Secret UUID	Enter the Secret UUID for CEPH	NOVA Boot from	You can choose CEPH or local from the drop-down list.	NOVA RBD	Enter the NOVA
Name	Description																			
	<p>1. 1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p>  <table border="1"> <tbody> <tr> <td data-bbox="1247 898 1341 1010">CEPH Mode</td> <td data-bbox="1341 898 1492 1010">By default Ceph Mode is Central.</td> </tr> <tr> <td data-bbox="1247 1010 1341 1094">Cluster ID</td> <td data-bbox="1341 1010 1492 1094">Enter the Cluster ID.</td> </tr> <tr> <td data-bbox="1247 1094 1341 1241">Monitor Host</td> <td data-bbox="1341 1094 1492 1241">Enter the Monitor Host for CEPH</td> </tr> <tr> <td data-bbox="1247 1241 1341 1381">Monitor Members</td> <td data-bbox="1341 1241 1492 1381">Enter the Monitor Members for CEPH</td> </tr> <tr> <td data-bbox="1247 1381 1341 1528">Secret UUID</td> <td data-bbox="1341 1381 1492 1528">Enter the Secret UUID for CEPH</td> </tr> <tr> <td data-bbox="1247 1528 1341 1766">NOVA Boot from</td> <td data-bbox="1341 1528 1492 1766">You can choose CEPH or local from the drop-down list.</td> </tr> <tr> <td data-bbox="1247 1766 1341 1839">NOVA RBD</td> <td data-bbox="1341 1766 1492 1839">Enter the NOVA</td> </tr> </tbody> </table>	CEPH Mode	By default Ceph Mode is Central.	Cluster ID	Enter the Cluster ID.	Monitor Host	Enter the Monitor Host for CEPH	Monitor Members	Enter the Monitor Members for CEPH	Secret UUID	Enter the Secret UUID for CEPH	NOVA Boot from	You can choose CEPH or local from the drop-down list.	NOVA RBD	Enter the NOVA					
CEPH Mode	By default Ceph Mode is Central.																			
Cluster ID	Enter the Cluster ID.																			
Monitor Host	Enter the Monitor Host for CEPH																			
Monitor Members	Enter the Monitor Members for CEPH																			
Secret UUID	Enter the Secret UUID for CEPH																			
NOVA Boot from	You can choose CEPH or local from the drop-down list.																			
NOVA RBD	Enter the NOVA																			

	Command or Action	Purpose	
		Name	Description
		POOL	RBD Pool (default's to vms)
		CEPH NAT	CEPH NAT is required for Central Ceph and when mgmt network is not routable.
			<p>2. When Object Storage Backend is selected as <i>Dedicated</i> in the blueprint initial setup.</p>  <p>Create Blueprint configuration</p> <ul style="list-style-type: none"> • CEPH Mode: By default Dedicated. • NOVA Boot: From drop-down selection you can choose CEPH or local. <p>3. When Object Storage Backend is selected as <i>NetApp</i> in the blueprint initial setup.</p>  <p>Create Blueprint configuration</p>

	Command or Action	Purpose										
		<table border="1"> <thead> <tr> <th data-bbox="927 275 1187 331">Name</th> <th data-bbox="1187 275 1490 331">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 331 1187 758">GLANCE</td> <td data-bbox="1187 331 1490 758"> <p>1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p>  </td> </tr> <tr> <td data-bbox="1198 785 1344 867">Store Backend</td> <td data-bbox="1344 785 1490 867">By default CEPH.</td> </tr> <tr> <td data-bbox="1198 867 1344 982">Glance RBD Pool field</td> <td data-bbox="1344 867 1490 982">By default images.</td> </tr> <tr> <td data-bbox="1198 982 1344 1098">Glance Client Key</td> <td data-bbox="1344 982 1490 1098">Enter GLANCE Client Key</td> </tr> </tbody> </table> <p>2. When Object Storage Backend is selected as <i>Dedicated</i> in the blueprint initial setup.</p>  <p>By default Populated for CEPH Dedicated with Store Backend value as CEPH.</p>	Name	Description	GLANCE	<p>1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p> 	Store Backend	By default CEPH.	Glance RBD Pool field	By default images.	Glance Client Key	Enter GLANCE Client Key
Name	Description											
GLANCE	<p>1. When Object Storage Backend is selected as <i>Central</i> in the blueprint initial setup.</p> 											
Store Backend	By default CEPH.											
Glance RBD Pool field	By default images.											
Glance Client Key	Enter GLANCE Client Key											

	Command or Action	Purpose										
		<table border="1"> <thead> <tr> <th data-bbox="966 275 1227 329">Name</th> <th data-bbox="1227 275 1534 329">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 329 1227 485">CINDER</td> <td data-bbox="1227 329 1534 485">By default Populated for <i>CEPH Dedicated</i> with Volume Driver value as CEPH.</td> </tr> </tbody> </table> <div data-bbox="1234 499 1620 772"> <p>Create Blueprint configuration</p> <p>Blueprint Initial Setup Physical Setup OpenStack Setup</p> <p> ✗ HA Proxy ✓ Keystone ✓ Neutron ✗ CEPH </p> <p>Volume Driver *</p> <p>CEPH</p> <p>Cinder Client Key *</p> <p>Enter CINDER Client Key</p> </div> <table border="1"> <tbody> <tr> <td data-bbox="1234 804 1382 884">Volume Driver</td> <td data-bbox="1382 804 1534 884">By default CEPH.</td> </tr> <tr> <td data-bbox="1234 884 1382 997">Cinder RBD Pool field</td> <td data-bbox="1382 884 1534 997">By default volumes.</td> </tr> <tr> <td data-bbox="1234 997 1382 1115">Cinder Client Key</td> <td data-bbox="1382 997 1534 1115">Enter Cinder Client Key</td> </tr> </tbody> </table> <div data-bbox="1234 1161 1620 1423"> <p>Create Blueprint configuration</p> <p>Blueprint Initial Setup Physical Setup OpenStack Setup</p> <p> ✗ HA Proxy ✓ Keystone ✓ Neutron ✗ C </p> <p>Volume Driver *</p> <p>CEPH</p> </div>	Name	Description	CINDER	By default Populated for <i>CEPH Dedicated</i> with Volume Driver value as CEPH .	Volume Driver	By default CEPH.	Cinder RBD Pool field	By default volumes.	Cinder Client Key	Enter Cinder Client Key
Name	Description											
CINDER	By default Populated for <i>CEPH Dedicated</i> with Volume Driver value as CEPH .											
Volume Driver	By default CEPH.											
Cinder RBD Pool field	By default volumes.											
Cinder Client Key	Enter Cinder Client Key											




	Command or Action	Purpose	
		Name	Description
		VMTP VMTP optional section will only be visible once VMTP is selected from Blueprint Initial Setup.	




	Command or Action	Purpose														
		<table border="1"> <thead> <tr> <th data-bbox="885 273 1226 325">Name</th> <th data-bbox="1226 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="885 325 1226 1852"></td> <td data-bbox="1226 325 1534 1852"> <p>Check one of the check boxes to specify a VMTP network:</p> <ul style="list-style-type: none"> • Provider Network • External Network <p>For the Provider Network complete the following:</p> <p>Create Blueprint configuration</p>  <table border="1"> <tbody> <tr> <td data-bbox="1242 1071 1372 1218">Network Name field</td> <td data-bbox="1372 1071 1534 1218">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1242 1218 1372 1375">Subnet field</td> <td data-bbox="1372 1218 1534 1375">Enter the Subnet for Provider Network.</td> </tr> <tr> <td data-bbox="1242 1375 1372 1564">Network IP Start field</td> <td data-bbox="1372 1375 1534 1564">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1564 1372 1753">Network IP End field</td> <td data-bbox="1372 1564 1534 1753">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1753 1372 1852">Network Gateway field</td> <td data-bbox="1372 1753 1534 1852">Enter the IPv4 address for</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description		<p>Check one of the check boxes to specify a VMTP network:</p> <ul style="list-style-type: none"> • Provider Network • External Network <p>For the Provider Network complete the following:</p> <p>Create Blueprint configuration</p>  <table border="1"> <tbody> <tr> <td data-bbox="1242 1071 1372 1218">Network Name field</td> <td data-bbox="1372 1071 1534 1218">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1242 1218 1372 1375">Subnet field</td> <td data-bbox="1372 1218 1534 1375">Enter the Subnet for Provider Network.</td> </tr> <tr> <td data-bbox="1242 1375 1372 1564">Network IP Start field</td> <td data-bbox="1372 1375 1534 1564">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1564 1372 1753">Network IP End field</td> <td data-bbox="1372 1564 1534 1753">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1753 1372 1852">Network Gateway field</td> <td data-bbox="1372 1753 1534 1852">Enter the IPv4 address for</td> </tr> </tbody> </table>	Network Name field	Enter the name for the external network.	Subnet field	Enter the Subnet for Provider Network.	Network IP Start field	Enter the start of the floating IPv4 address.	Network IP End field	Enter the end of the floating IPv4 address.	Network Gateway field	Enter the IPv4 address for
Name	Description															
	<p>Check one of the check boxes to specify a VMTP network:</p> <ul style="list-style-type: none"> • Provider Network • External Network <p>For the Provider Network complete the following:</p> <p>Create Blueprint configuration</p>  <table border="1"> <tbody> <tr> <td data-bbox="1242 1071 1372 1218">Network Name field</td> <td data-bbox="1372 1071 1534 1218">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1242 1218 1372 1375">Subnet field</td> <td data-bbox="1372 1218 1534 1375">Enter the Subnet for Provider Network.</td> </tr> <tr> <td data-bbox="1242 1375 1372 1564">Network IP Start field</td> <td data-bbox="1372 1375 1534 1564">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1564 1372 1753">Network IP End field</td> <td data-bbox="1372 1564 1534 1753">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1242 1753 1372 1852">Network Gateway field</td> <td data-bbox="1372 1753 1534 1852">Enter the IPv4 address for</td> </tr> </tbody> </table>	Network Name field	Enter the name for the external network.	Subnet field	Enter the Subnet for Provider Network.	Network IP Start field	Enter the start of the floating IPv4 address.	Network IP End field	Enter the end of the floating IPv4 address.	Network Gateway field	Enter the IPv4 address for					
Network Name field	Enter the name for the external network.															
Subnet field	Enter the Subnet for Provider Network.															
Network IP Start field	Enter the start of the floating IPv4 address.															
Network IP End field	Enter the end of the floating IPv4 address.															
Network Gateway field	Enter the IPv4 address for															




	Command or Action	Purpose									
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1192 331">Name</th> <th data-bbox="1192 275 1494 331">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 331 1192 415"></td> <td data-bbox="1192 331 1494 415">the Gateway.</td> </tr> <tr> <td data-bbox="854 415 1192 569">DNS Server field</td> <td data-bbox="1192 415 1494 569">Enter the DNS server IPv4 address.</td> </tr> <tr> <td data-bbox="854 569 1192 688">Segmentation ID field</td> <td data-bbox="1192 569 1494 688">Enter the segmentation ID.</td> </tr> </tbody> </table>	Name	Description		the Gateway.	DNS Server field	Enter the DNS server IPv4 address.	Segmentation ID field	Enter the segmentation ID.	<p>For External Network fill in the following details:</p> 
Name	Description										
	the Gateway.										
DNS Server field	Enter the DNS server IPv4 address.										
Segmentation ID field	Enter the segmentation ID.										

	Command or Action	Purpose																
		<table border="1"> <thead> <tr> <th data-bbox="889 273 1226 325">Name</th> <th data-bbox="1226 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="889 325 1226 483"></td> <td data-bbox="1226 325 1534 483"> <table border="1"> <tr> <td data-bbox="1226 325 1380 483">Network Name field</td> <td data-bbox="1380 325 1534 483">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1226 483 1380 640">Subnet field</td> <td data-bbox="1380 483 1534 640">Enter the Subnet for the external Network.</td> </tr> <tr> <td data-bbox="1226 640 1380 819">Network IP Start field</td> <td data-bbox="1380 640 1534 819">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 819 1380 997">Network IP End field</td> <td data-bbox="1380 819 1534 997">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 997 1380 1176">Network Gateway field</td> <td data-bbox="1380 997 1534 1176">Enter the IPv4 address for the Gateway.</td> </tr> <tr> <td data-bbox="1226 1176 1380 1354">DNS Server field</td> <td data-bbox="1380 1176 1534 1354">Enter the DNS server IPv4 address.</td> </tr> </table></td></tr></tbody> </table>	Name	Description		<table border="1"> <tr> <td data-bbox="1226 325 1380 483">Network Name field</td> <td data-bbox="1380 325 1534 483">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1226 483 1380 640">Subnet field</td> <td data-bbox="1380 483 1534 640">Enter the Subnet for the external Network.</td> </tr> <tr> <td data-bbox="1226 640 1380 819">Network IP Start field</td> <td data-bbox="1380 640 1534 819">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 819 1380 997">Network IP End field</td> <td data-bbox="1380 819 1534 997">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 997 1380 1176">Network Gateway field</td> <td data-bbox="1380 997 1534 1176">Enter the IPv4 address for the Gateway.</td> </tr> <tr> <td data-bbox="1226 1176 1380 1354">DNS Server field</td> <td data-bbox="1380 1176 1534 1354">Enter the DNS server IPv4 address.</td> </tr> </table>	Network Name field	Enter the name for the external network.	Subnet field	Enter the Subnet for the external Network.	Network IP Start field	Enter the start of the floating IPv4 address.	Network IP End field	Enter the end of the floating IPv4 address.	Network Gateway field	Enter the IPv4 address for the Gateway.	DNS Server field	Enter the DNS server IPv4 address.
Name	Description																	
	<table border="1"> <tr> <td data-bbox="1226 325 1380 483">Network Name field</td> <td data-bbox="1380 325 1534 483">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="1226 483 1380 640">Subnet field</td> <td data-bbox="1380 483 1534 640">Enter the Subnet for the external Network.</td> </tr> <tr> <td data-bbox="1226 640 1380 819">Network IP Start field</td> <td data-bbox="1380 640 1534 819">Enter the start of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 819 1380 997">Network IP End field</td> <td data-bbox="1380 819 1534 997">Enter the end of the floating IPv4 address.</td> </tr> <tr> <td data-bbox="1226 997 1380 1176">Network Gateway field</td> <td data-bbox="1380 997 1534 1176">Enter the IPv4 address for the Gateway.</td> </tr> <tr> <td data-bbox="1226 1176 1380 1354">DNS Server field</td> <td data-bbox="1380 1176 1534 1354">Enter the DNS server IPv4 address.</td> </tr> </table>	Network Name field	Enter the name for the external network.	Subnet field	Enter the Subnet for the external Network.	Network IP Start field	Enter the start of the floating IPv4 address.	Network IP End field	Enter the end of the floating IPv4 address.	Network Gateway field	Enter the IPv4 address for the Gateway.	DNS Server field	Enter the DNS server IPv4 address.					
Network Name field	Enter the name for the external network.																	
Subnet field	Enter the Subnet for the external Network.																	
Network IP Start field	Enter the start of the floating IPv4 address.																	
Network IP End field	Enter the end of the floating IPv4 address.																	
Network Gateway field	Enter the IPv4 address for the Gateway.																	
DNS Server field	Enter the DNS server IPv4 address.																	


 TLS This optional section will only be visible once TLS is selected from Blueprint Initial Setup Page. | **TLS** has two options: - **External LB VIP FQDN** - -Text field. - **External LB VIP TLS** True/False. By default this option is false. |

	Command or Action	Purpose				
		<table border="1"> <thead> <tr> <th data-bbox="854 275 1188 331">Name</th> <th data-bbox="1188 275 1490 331">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="854 331 1188 1230"> <p>Under the OpenStack setup tab, Vim_admins tab will be visible only when Vim_admins is selected from the Optional Features & Services under the Blueprint Initial setup tab</p> </td> <td data-bbox="1188 331 1490 1230"> <p>Following are the field descriptions for VIM Admins:</p>  <ul style="list-style-type: none"> • User Name - Text field. • Password - Password field. Admin hash password should always start with \$6. </td> </tr> </tbody> </table>	Name	Description	<p>Under the OpenStack setup tab, Vim_admins tab will be visible only when Vim_admins is selected from the Optional Features & Services under the Blueprint Initial setup tab</p>	<p>Following are the field descriptions for VIM Admins:</p>  <ul style="list-style-type: none"> • User Name - Text field. • Password - Password field. Admin hash password should always start with \$6.
Name	Description					
<p>Under the OpenStack setup tab, Vim_admins tab will be visible only when Vim_admins is selected from the Optional Features & Services under the Blueprint Initial setup tab</p>	<p>Following are the field descriptions for VIM Admins:</p>  <ul style="list-style-type: none"> • User Name - Text field. • Password - Password field. Admin hash password should always start with \$6. 					

	Command or Action	Purpose																
		<table border="1"> <thead> <tr> <th data-bbox="966 273 1226 325">Name</th> <th data-bbox="1226 273 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="966 325 1226 829"> <p>SwiftStack optional section will be visible once SwiftStack is selected from Blueprint Initial Setup Page. SwiftStack is only supported with KeyStonev2 . If you select Keystonev3, swiftstack will not be available for configuration.</p> </td> <td data-bbox="1226 325 1534 829"> <p>Following are the options that needs to be filled for SwiftStack:</p>  </td> </tr> <tr> <td data-bbox="966 829 1226 997"> <p>Cluster End Point field</p> </td> <td data-bbox="1226 829 1534 997"> <p>IP address of PAC (By Account) endpoint.</p> </td> </tr> <tr> <td data-bbox="966 997 1226 1144"> <p>Admin User field</p> </td> <td data-bbox="1226 997 1534 1144"> <p>Admin user for swift to authenticate in keystone.</p> </td> </tr> <tr> <td data-bbox="966 1144 1226 1375"> <p>Admin Tenant field</p> </td> <td data-bbox="1226 1144 1534 1375"> <p>The service tenant corresponding to the Account Account used by the Swiftstack.</p> </td> </tr> <tr> <td data-bbox="966 1375 1226 1690"> <p>Reseller Prefix field</p> </td> <td data-bbox="1226 1375 1534 1690"> <p>Reseller_prefix as configured for Keysone Auth Auth support in Swiftstack. Example: KEY_</p> </td> </tr> <tr> <td data-bbox="966 1690 1226 1795"> <p>Admin Password field</p> </td> <td data-bbox="1226 1690 1534 1795"> <p>swiftadmin swiftadmin</p> </td> </tr> <tr> <td data-bbox="966 1795 1226 1869"> <p>Protocol</p> </td> <td data-bbox="1226 1795 1534 1869"> <p>http or https</p> </td> </tr> </tbody> </table>	Name	Description	<p>SwiftStack optional section will be visible once SwiftStack is selected from Blueprint Initial Setup Page. SwiftStack is only supported with KeyStonev2 . If you select Keystonev3, swiftstack will not be available for configuration.</p>	<p>Following are the options that needs to be filled for SwiftStack:</p> 	<p>Cluster End Point field</p>	<p>IP address of PAC (By Account) endpoint.</p>	<p>Admin User field</p>	<p>Admin user for swift to authenticate in keystone.</p>	<p>Admin Tenant field</p>	<p>The service tenant corresponding to the Account Account used by the Swiftstack.</p>	<p>Reseller Prefix field</p>	<p>Reseller_prefix as configured for Keysone Auth Auth support in Swiftstack. Example: KEY_</p>	<p>Admin Password field</p>	<p>swiftadmin swiftadmin</p>	<p>Protocol</p>	<p>http or https</p>
Name	Description																	
<p>SwiftStack optional section will be visible once SwiftStack is selected from Blueprint Initial Setup Page. SwiftStack is only supported with KeyStonev2 . If you select Keystonev3, swiftstack will not be available for configuration.</p>	<p>Following are the options that needs to be filled for SwiftStack:</p> 																	
<p>Cluster End Point field</p>	<p>IP address of PAC (By Account) endpoint.</p>																	
<p>Admin User field</p>	<p>Admin user for swift to authenticate in keystone.</p>																	
<p>Admin Tenant field</p>	<p>The service tenant corresponding to the Account Account used by the Swiftstack.</p>																	
<p>Reseller Prefix field</p>	<p>Reseller_prefix as configured for Keysone Auth Auth support in Swiftstack. Example: KEY_</p>																	
<p>Admin Password field</p>	<p>swiftadmin swiftadmin</p>																	
<p>Protocol</p>	<p>http or https</p>																	

	Command or Action	Purpose												
		<p>9. For SolidFire, enter the following:</p> <table border="1" data-bbox="927 323 1492 1344"> <thead> <tr> <th data-bbox="927 323 1206 380">Name</th> <th data-bbox="1206 323 1492 380">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="927 380 1206 766"> SolidFire is visible for configuration on day0 SolidFire is not allowed as a day-2 deployment option SolidFire is always available with CEPH. </td> <td data-bbox="1206 380 1492 1344">  <table border="1" data-bbox="1214 766 1492 1323"> <tbody> <tr> <td data-bbox="1214 766 1333 926">Cluster MVIP field</td> <td data-bbox="1333 766 1492 926">Management IP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 926 1333 1050">Cluster SVIP field</td> <td data-bbox="1333 926 1492 1050">Storage VIP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 1050 1333 1165">Admin Username</td> <td data-bbox="1333 1050 1492 1165">Admin user on SolidFire cluster</td> </tr> <tr> <td data-bbox="1214 1165 1333 1323">Admin Password</td> <td data-bbox="1333 1165 1492 1323">Admin password on SolidFire cluster.</td> </tr> </tbody> </table> </td> </tr> </tbody> </table> <p>10. If Syslog Export or NFVBENCH is selected in Blueprint Initial Setup, the Services Setup pane is enabled for the user to view.</p> <p>Following are the options under Services Setup Tab:</p>	Name	Description	SolidFire is visible for configuration on day0 SolidFire is not allowed as a day-2 deployment option SolidFire is always available with CEPH.	 <table border="1" data-bbox="1214 766 1492 1323"> <tbody> <tr> <td data-bbox="1214 766 1333 926">Cluster MVIP field</td> <td data-bbox="1333 766 1492 926">Management IP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 926 1333 1050">Cluster SVIP field</td> <td data-bbox="1333 926 1492 1050">Storage VIP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 1050 1333 1165">Admin Username</td> <td data-bbox="1333 1050 1492 1165">Admin user on SolidFire cluster</td> </tr> <tr> <td data-bbox="1214 1165 1333 1323">Admin Password</td> <td data-bbox="1333 1165 1492 1323">Admin password on SolidFire cluster.</td> </tr> </tbody> </table>	Cluster MVIP field	Management IP of SolidFire cluster.	Cluster SVIP field	Storage VIP of SolidFire cluster.	Admin Username	Admin user on SolidFire cluster	Admin Password	Admin password on SolidFire cluster.
Name	Description													
SolidFire is visible for configuration on day0 SolidFire is not allowed as a day-2 deployment option SolidFire is always available with CEPH.	 <table border="1" data-bbox="1214 766 1492 1323"> <tbody> <tr> <td data-bbox="1214 766 1333 926">Cluster MVIP field</td> <td data-bbox="1333 766 1492 926">Management IP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 926 1333 1050">Cluster SVIP field</td> <td data-bbox="1333 926 1492 1050">Storage VIP of SolidFire cluster.</td> </tr> <tr> <td data-bbox="1214 1050 1333 1165">Admin Username</td> <td data-bbox="1333 1050 1492 1165">Admin user on SolidFire cluster</td> </tr> <tr> <td data-bbox="1214 1165 1333 1323">Admin Password</td> <td data-bbox="1333 1165 1492 1323">Admin password on SolidFire cluster.</td> </tr> </tbody> </table>	Cluster MVIP field	Management IP of SolidFire cluster.	Cluster SVIP field	Storage VIP of SolidFire cluster.	Admin Username	Admin user on SolidFire cluster	Admin Password	Admin password on SolidFire cluster.					
Cluster MVIP field	Management IP of SolidFire cluster.													
Cluster SVIP field	Storage VIP of SolidFire cluster.													
Admin Username	Admin user on SolidFire cluster													
Admin Password	Admin password on SolidFire cluster.													

	Command or Action	Purpose																
		<table border="1"> <thead> <tr> <th data-bbox="889 275 1209 325">Name</th> <th data-bbox="1209 275 1534 325">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="889 325 1209 1388">Syslog Export</td> <td data-bbox="1209 325 1534 1388"> <p>Following are the options for Syslog Settings:</p>  <table border="1"> <tbody> <tr> <td data-bbox="1218 777 1372 861">Remote Host</td> <td data-bbox="1372 777 1526 861">Enter Syslog IP address.</td> </tr> <tr> <td data-bbox="1218 861 1372 945">Protocol</td> <td data-bbox="1372 861 1526 945">Only UDP is supported.</td> </tr> <tr> <td data-bbox="1218 945 1372 1039">Facility</td> <td data-bbox="1372 945 1526 1039">Defaults to local5.</td> </tr> <tr> <td data-bbox="1218 1039 1372 1123">Severity</td> <td data-bbox="1372 1039 1526 1123">Defaults to debug.</td> </tr> <tr> <td data-bbox="1218 1123 1372 1207">Clients</td> <td data-bbox="1372 1123 1526 1207">Defaults to ELK.</td> </tr> <tr> <td data-bbox="1218 1207 1372 1388">Port</td> <td data-bbox="1372 1207 1526 1388">Defaults to 514 but can be modified by the User.</td> </tr> </tbody> </table> </td> </tr> </tbody> </table>	Name	Description	Syslog Export	<p>Following are the options for Syslog Settings:</p>  <table border="1"> <tbody> <tr> <td data-bbox="1218 777 1372 861">Remote Host</td> <td data-bbox="1372 777 1526 861">Enter Syslog IP address.</td> </tr> <tr> <td data-bbox="1218 861 1372 945">Protocol</td> <td data-bbox="1372 861 1526 945">Only UDP is supported.</td> </tr> <tr> <td data-bbox="1218 945 1372 1039">Facility</td> <td data-bbox="1372 945 1526 1039">Defaults to local5.</td> </tr> <tr> <td data-bbox="1218 1039 1372 1123">Severity</td> <td data-bbox="1372 1039 1526 1123">Defaults to debug.</td> </tr> <tr> <td data-bbox="1218 1123 1372 1207">Clients</td> <td data-bbox="1372 1123 1526 1207">Defaults to ELK.</td> </tr> <tr> <td data-bbox="1218 1207 1372 1388">Port</td> <td data-bbox="1372 1207 1526 1388">Defaults to 514 but can be modified by the User.</td> </tr> </tbody> </table>	Remote Host	Enter Syslog IP address.	Protocol	Only UDP is supported.	Facility	Defaults to local5.	Severity	Defaults to debug.	Clients	Defaults to ELK.	Port	Defaults to 514 but can be modified by the User.
Name	Description																	
Syslog Export	<p>Following are the options for Syslog Settings:</p>  <table border="1"> <tbody> <tr> <td data-bbox="1218 777 1372 861">Remote Host</td> <td data-bbox="1372 777 1526 861">Enter Syslog IP address.</td> </tr> <tr> <td data-bbox="1218 861 1372 945">Protocol</td> <td data-bbox="1372 861 1526 945">Only UDP is supported.</td> </tr> <tr> <td data-bbox="1218 945 1372 1039">Facility</td> <td data-bbox="1372 945 1526 1039">Defaults to local5.</td> </tr> <tr> <td data-bbox="1218 1039 1372 1123">Severity</td> <td data-bbox="1372 1039 1526 1123">Defaults to debug.</td> </tr> <tr> <td data-bbox="1218 1123 1372 1207">Clients</td> <td data-bbox="1372 1123 1526 1207">Defaults to ELK.</td> </tr> <tr> <td data-bbox="1218 1207 1372 1388">Port</td> <td data-bbox="1372 1207 1526 1388">Defaults to 514 but can be modified by the User.</td> </tr> </tbody> </table>	Remote Host	Enter Syslog IP address.	Protocol	Only UDP is supported.	Facility	Defaults to local5.	Severity	Defaults to debug.	Clients	Defaults to ELK.	Port	Defaults to 514 but can be modified by the User.					
Remote Host	Enter Syslog IP address.																	
Protocol	Only UDP is supported.																	
Facility	Defaults to local5.																	
Severity	Defaults to debug.																	
Clients	Defaults to ELK.																	
Port	Defaults to 514 but can be modified by the User.																	


	Command or Action	Purpose	
		Name	Description
		NFVBENCH	<p>NFVBENCH enable checkbox which by default is <i>False</i>.</p>  <p>Add ToR information connected to switch:</p> <ul style="list-style-type: none"> • Select a TOR Switch and enter the Switch name. • Enter the port number. For example: eth1/5. VTEP VLANS (mandatory and needed only for VXLAN): Enter 2 different VLANs for VLAN1 and VLAN2 • NIC Ports: INT1 and INT2 optional input. Enter the 2 port numbers of the 4-port 10G Intel NIC at the management node used for the NFVBench.
		ENABLE_ESC_PRIV	Enable the checkbox to set it as True. By default it is <i>False</i> .

Creating a Blueprint for C-Series Server Platform

Create a Cisco VIM Unified Management User Account and register the respective Pod.

- Step 1** Log into **CISCO VIM Unified Management**.
- Step 2** In the **Navigation** pane, expand the **Pre-Install Section**.
- Step 3** Click **Blueprint Setup**.
- Step 4** To create a **C Series Blueprint**:

1. On the **Blueprint Initial Setup** page of the Cisco VIM Unified Management, complete the following fields:




Name	Description
Blueprint Name field.	Enter the name for the blueprint configuration.
Platform Type drop-down list	Choose one of the following platform types: <ul style="list-style-type: none"> • B-Series (By default) • C-Series (Select C Series)

Name	Description
Tenant Network drop-down list	<p>Choose one of the following tenant network types:</p> <ul style="list-style-type: none"> • Linux Bridge/VXLAN • OVS/VLAN • VTS/VLAN • VPP/VLAN • ACI/VLAN <p>Note when VTS/VLAN or ACI/VLAN is selected then respective tabs are available on Blueprint setup. When Mechanism driver OVS or ACI is selected, VM_HUGEPAGE_PERCENTAGE field is enabled for all standalone compute nodes, when NFV_HOSTS is enabled.</p>
Pod Type drop-down list	<p>Choose one of the following pod type :</p> <ul style="list-style-type: none"> • Fullon(By Default) • Micro • UMHC • NGENAHC <p>Note</p> <ul style="list-style-type: none"> • UMHC pod type is only supported for OVS/VLAN tenant type. • NGENAHC is supported for VPP/VLAN tenant type with no SRIOV • Pod type micro is supported for OVS/VLAN, ACI/VLAN,VPP/VLAN.
Ceph Mode drop-down list	<p>Choose one of the following Ceph types:</p> <ul style="list-style-type: none"> • Dedicated (By Default) • Central. Central is not supported in Production
Optional and Services Features checkbox	<p>Swiftstack, LDAP, Syslog Export Settings, Install Mode, TorSwitch Information, TLS, NFVMON, Pod Name, VMTP, NFVBench, Autbackup, Heat, Keystone v3, Enable Esc Priv.</p> <p>If any one is selected, the corresponding section is visible in various Blueprint sections.</p> <p>By default all features are disabled except Auto Backup.</p>

Name	Description
Import Existing YAML file	If you have an existing C Series YAML file you can use this feature to upload the file. Unified Management will automatically fill in the fields and any missed mandatory field will be highlighted in the respective section.


2. Click **Physical Setup** to advance to the **Registry Setup** configuration page. Fill in the following details for Registry Setup:



Name	Description
Registry User Name text field	User-Name for Registry (Mandatory).
Registry Password text field	Password for Registry (Mandatory).
Registry Email text field	Email ID for Registry (Mandatory).

Once all the mandatory fields are filled the **Validation Check Registry Page** will be changed to a Green Tick.


3. Click **CIMC Common Tab** and complete the following fields:



Name	Description
User Name disabled field	By default value is Admin.


Password text field	Enter Password for UCSM Common (Mandatory).
----------------------------	--

- Click **Networking** to advance to the networking section of the Blueprint.



Name	Description
Domain Name field	Enter the domain name. (Mandatory)
HTTP Proxy Server field	If your configuration uses an HTTP proxy server, enter the IP address of the server.
HTTPS Proxy Server field	If your configuration uses an HTTPS proxy server, enter the IP address of the server.
IP Tables on Management Pods	Specifies the list of IP Address with Mask.
NTP Servers field	Enter a maximum of four and minimum of one IPv4 and/or IPv6 addresses in the table.
Domain Name Servers field	Enter a maximum of three and minimum of one IPv4 and/or IPV6 addresses.


Name	Description
Networks table	

Name	Description		
	<p>Network table is pre-populated with Segments. To add Networks you can either clear all the table with Delete all or click edit icon for each segment and fill in the details.</p> <p>You can add, edit, or delete network information in the table.</p>  <ul style="list-style-type: none"> • Click Add (+) to add new entries (networks) to the table. • Specify the following fields in the Edit Entry to Networks dialog: 		
<table border="1"> <thead> <tr> <th data-bbox="894 1262 1192 1310">Name</th> <th data-bbox="1192 1262 1487 1310">Description</th> </tr> </thead> </table>	Name	Description	
Name	Description		
<table border="1"> <tbody> <tr> <td data-bbox="894 1310 1192 1478">VLAN field</td> <td data-bbox="1192 1310 1487 1478">Enter the VLAN ID. For Segment - Provider, the VLAN ID value is 'none'.</td> </tr> </tbody> </table>	VLAN field	Enter the VLAN ID . For Segment - Provider, the VLAN ID value is 'none'.	
VLAN field	Enter the VLAN ID . For Segment - Provider, the VLAN ID value is 'none'.		
<table border="1"> <tbody> <tr> <td data-bbox="894 1478 1192 1845">Segment drop-down list</td> <td data-bbox="1192 1478 1487 1845">When you add/edit new segment then following segments types are available in the form of dropdown list and you can select only one. <ul style="list-style-type: none"> • API • Management/provision • Tenant </td> </tr> </tbody> </table>	Segment drop-down list	When you add/edit new segment then following segments types are available in the form of dropdown list and you can select only one. <ul style="list-style-type: none"> • API • Management/provision • Tenant 	
Segment drop-down list	When you add/edit new segment then following segments types are available in the form of dropdown list and you can select only one. <ul style="list-style-type: none"> • API • Management/provision • Tenant 		

Name	Description	
		<ul style="list-style-type: none"> • Storage • External • Provider • ACIINFRA <p>Note Acinfra segment is available only when ACI/VLAN tenant type is selected) Depending upon the segment some of the entries below are not needed. Please refer to the example file in openstack-configs dir for details.</p>
	Subnet field	Enter the IPv4 address for the subnet.
	IPv6 Subnet field	Enter IPv6 Address. This field will be available only for Management provision and API
	Gateway field	Enter the IPv4 address for the Gateway.
	Gateway IPv6 field	Enter the IPv6 address for the gateway. This will support for API and management provision.
	Pool field	Enter the pool information in the required format, for example: 10.1.15-10.1.1.10,102.15-102.1.10 This field is available only for the Mgmt/Provision, Storage, and Tenant segments.
	IPv6 Pool field	

Name	Description
	Enter the pool information in the required format. For example: 10.1.15-10.1.1.10,10.2.15-10.2.1.10
	Click Save .

- On the **Servers and Roles** page of the Cisco VIM Suite wizard, a pre-populated table filled with Roles : Control, Compute and Block Storage (Only if CEPH Dedicated is selected in Blueprint Initial Setup is available).



Note If you choose mechanism driver as OVS or ACI, VM_HUGEPAGE_PERCENTAGE field column is available for compute nodes, where you can fill values from 0 to 100%, when NFV_HOSTS: ALL is chosen.

Name	Description
Server User Name field	Enter the username of the Server.
Disable Hyperthreading	Default value is false. You can set it as true or false.

Name	Description	
Cobbler	Enter the Cobbler details in the following fields:	
	Name	Description
	Cobbler Timeout field	The default value is 45 min. This is an optional parameter. Timeout is displayed in minutes, and its value ranges from 30 to 120.
	Block Storage Kickstart field	Kickstart file for Storage Node.
	Admin Password Hash field	Enter the Admin Password. Password should be Alphanumeric. Password should contain minimum 8 characters and maximum of 32 characters.
	Cobbler Username field	Enter the cobbler username to access the cobbler server.
	Control Kickstart field	Kickstart file for Control Node.
	Compute Kickstart field	Kickstart file for Compute Node.
Cobbler Admin Username field	Enter the admin username of the Cobbler.	

Name	Description
<p>Add Entry to Servers and Roles</p> <p>Note when Pod type micro is selected then all the three servers will be associated with control, compute and block storage role.</p> <p>For Example:</p> <p>Roles</p> <ul style="list-style-type: none"> • Block Storage <ul style="list-style-type: none"> • -Server 1 • -Server 2 • -Server 3 • Control <ul style="list-style-type: none"> • -Server 1 • -Server 2 • -Server 3 • Compute <ul style="list-style-type: none"> • -Server 1 • -Server 2 • -Server 3 <p>Note When Pod type UMHC is selected then auto ToR configuration is not supported and the ToR info at server and roles level is not allowed to be entered.</p>	

Name	Description																
	<p>Click Edit or + to add a new server and role to the table.</p> <p>If mechanism driver is either OVS or ACI, an additional optional field VM_HUGEPAGE_PERCENTAGE is shown when compute role is chosen; This option is only valid when NFV_HOSTS is set to ALL; If no value is entered then the global value of VM_HUGEPAGE_PERCENTAGE is used.</p> <div data-bbox="906 527 1437 1323"> <p>Server And Roles</p> </div> <table border="1" data-bbox="898 1350 1526 1869"> <tbody> <tr> <td>Server Name</td> <td>Entry the name of the server.</td> </tr> <tr> <td>Rack ID field</td> <td>The rack ID for the server.</td> </tr> <tr> <td>VIC Slot field</td> <td>Enter a VIC Slot.</td> </tr> <tr> <td>CIMC IP field</td> <td>Enter a IP address.</td> </tr> <tr> <td>CIMC Username field</td> <td>Enter a Username.</td> </tr> <tr> <td>CIMC Password field</td> <td>Enter a Password for CIMC.</td> </tr> <tr> <td>Select the Role from the drop down list</td> <td>Choose Control or Compute or Block Storage from the drop-down list.</td> </tr> <tr> <td>Management IP</td> <td>It is an optional field but if</td> </tr> </tbody> </table>	Server Name	Entry the name of the server.	Rack ID field	The rack ID for the server.	VIC Slot field	Enter a VIC Slot.	CIMC IP field	Enter a IP address.	CIMC Username field	Enter a Username.	CIMC Password field	Enter a Password for CIMC.	Select the Role from the drop down list	Choose Control or Compute or Block Storage from the drop-down list.	Management IP	It is an optional field but if
Server Name	Entry the name of the server.																
Rack ID field	The rack ID for the server.																
VIC Slot field	Enter a VIC Slot.																
CIMC IP field	Enter a IP address.																
CIMC Username field	Enter a Username.																
CIMC Password field	Enter a Password for CIMC.																
Select the Role from the drop down list	Choose Control or Compute or Block Storage from the drop-down list.																
Management IP	It is an optional field but if																

Name	Description	
		provided for one Server then it is mandatory to provide it for other Servers as well.
	Management IPv6	Routable and valid IPv6 address. It is an optional field but if provided for one server then it is mandatory for all other servers as well.
Click Save or Add .	On clicking Save or Add all information related to Servers and Roles gets saved.	
If Configure ToR checkbox is True with at-least one switch detail, these fields will be displayed for each server and this is similar to DP Tor: Port Channel and Switch Name (Mandatory if Configure ToR is true)	<ul style="list-style-type: none"> • Port Channel field • Switch Name field • Switch Port Info field 	<ul style="list-style-type: none"> • Enter the port channel input. • Enter the switch name. • Enter the switch port information.
DP ToR (Only for Control and Compute) : Mandatory if Intel NIC and Configure TOR is True.	<ul style="list-style-type: none"> • Port Channel field • Switch Name field • Switch Port Info field 	<ul style="list-style-type: none"> • Enter the port channel input. • Enter the switch name. • Enter the switch port information.
SRIOV TOR INFO (Only for Compute Nodes). It is mandatory in server and roles if Intel NIC and Configure TOR is True. with TOR TYPE Nexus. For TOR TYPE NCS-5500 these fields are optional Switch Name (Mandatory if Configure ToR is true) . This field appears only when Intel NIC support is true, as Auto TOR config is not supported in VIC_NIC combo	<ul style="list-style-type: none"> • Switch Name field • Switch Port Info field 	<ul style="list-style-type: none"> • Enter the switch name. • Enter the switch port information.
Intel SRIOV VFS (valid for Intel NIC testbeds) and can be integer.	For SRIOV support for Intel NIC. By Default, SRIOV support is disabled. To enable, define a value in the range # * 1-32 when INTEL_NIC_SUPPORT is set True (X710 Max VFs = 32) # * 1-63 when CISCO_VIC_INTEL_SRIOV is set True (X520 Max VFs = 63)	
INTEL_SRIOV_PHYS_PORTS (valid for Intel NIC test beds) and can be of value 2 or 4 (default is 2)	In some cases the # of Physical SRIOV port needed is 4; to meet that requirement, define the following: # this is optional, if nothing is defined code will assume it to be 2; the only 2 integer values this parameter # takes is 2 or 4 and is true when INTEL_NIC_SUPPORT is True and INTEL_SRIOV_VFS is valid.. For Cisco NCS 5500 this value is set to 4 and is non-editable.	


Name	Description
Click Save or Add .	If all mandatory fields are filled click Save or Add to add information on Servers and Roles.
Disable Hyperthreading	Default value is false. You can set it as true or false.
Click Save	

Note Maximum two ToR info needs to be configured for each connection type on each node (control, compute and block_storage node).

Note If pod type UMHC is selected then CISCO_VIC_INTEL_SRIOV is enabled to be TRUE. CISCO_VIC_INTEL_SRIOV is also supported on Micro pod with expanded computes

Note For Tenant type **ACI/VLAN**, port channel for each ToR port will not be available in servers and roles, as APIC will automatically assign port-channel numbers. Also, for ACI in full on mode you can select Intel NIC Support in the “Servers and Roles” section.

- Click **ToR Switch** checkbox in **Blueprint Initial Setup** to enable the **TOR SWITCH** configuration page. It is an **Optional** section in Blueprint Setup but once all the fields are filled in then it will become a part of the Blueprint.



Name	Description
Configure ToR optional checkbox.	Enabling this checkbox, changes the configure ToR section from false to true.
Note If UMHC is selected as podtype, configure TOR is not allowed.	Note Configure tor is true then ToR switch info maps in servers

Name	Description
ToR Switch Information mandatory table if you want to enter ToR information.	

Name	Description														
	<p>Click (+) to add information for ToR Switch.</p> <p>Switch Details</p> <div style="border: 1px solid #ccc; padding: 10px; margin: 10px 0;"> <p>Hostname * ⓘ</p> <input type="text" value="Enter Switch Hostname"/> <p>Username * ⓘ</p> <input type="text" value="Enter Switch Username"/> <p>Password * ⓘ</p> <input type="text" value="Enter Password"/> <p>SSH-IP * ⓘ</p> <input type="text" value="Enter IP Address"/> <p>SSN Num ⓘ</p> <input type="text" value="Enter SSN Num"/> <p>VPC Peer Keepalive ⓘ</p> <input type="text" value="Enter IP Address"/> <p>VPC Domain ⓘ</p> <input type="text" value="Enter VPC Domain"/> <p>VPC Peer Port Info ⓘ</p> <input type="text" value="Enter VPC Port"/> <p>VPC Peer VLAN Info ⓘ</p> <input type="text" value="Enter VPC VLAN Info"/> <p>BR Management Port Info ⓘ</p> <input type="text" value="Enter BR Port Info"/> <p>BR Management PO Info ⓘ</p> <input type="text" value="Enter BR PO Info"/> <p style="text-align: right;"> <input type="button" value="Save"/> <input type="button" value="Cancel"/> </p> </div> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 50%;">Name</th> <th style="width: 50%;">Description</th> </tr> </thead> <tbody> <tr> <td>Name</td> <td>ToR switch name.</td> </tr> <tr> <td>Username</td> <td>ToR switch username.</td> </tr> <tr> <td>Password</td> <td>ToR switch password.</td> </tr> <tr> <td>SSH IP</td> <td>ToR switch SSH IP.</td> </tr> <tr> <td>SSN Num</td> <td>ToR switch ssn num.</td> </tr> <tr> <td>VPC Peer Keepalive</td> <td>Peer Management IP. You cannot define if there is no peer.</td> </tr> </tbody> </table>	Name	Description	Name	ToR switch name.	Username	ToR switch username.	Password	ToR switch password.	SSH IP	ToR switch SSH IP.	SSN Num	ToR switch ssn num.	VPC Peer Keepalive	Peer Management IP. You cannot define if there is no peer.
Name	Description														
Name	ToR switch name.														
Username	ToR switch username.														
Password	ToR switch password.														
SSH IP	ToR switch SSH IP.														
SSN Num	ToR switch ssn num.														
VPC Peer Keepalive	Peer Management IP. You cannot define if there is no peer.														

Name	Description	
	VPC Domain	Cannot define if there is no peer.
	VPC Peer Port Info	Interface for vpc peer ports.
	VPC Peer VLAN Info	VLAN ids for vpc peer ports (optional).
	BR Management Port Info	Management interface of build node.
	BR Management PO Info	Port channel number for management interface of build node.
	BR Management VLAN info	VLAN id for management interface of build node (access).
Click Save .		

Note When tenant type ACI/VLAN is selected, the TOR switch information table differs and is mandatory.


Name	Description
<p>Configure ToR optional checkbox.</p> <p>Note If UMHC is selected as podtype, configure TOR is not allowed.</p>	<p>Enabling this checkbox, changes the configure ToR section from false to true.</p> <p>Note Configure tor is true then ToR switch info maps in servers</p>

Name	Description
ToR Switch Information mandatory table if you want to enter ToR information.	

Name	Description														
	<p>Click (+) to add information for ToR Switch.</p> <p>Switch Details</p> <div style="border: 1px solid #ccc; padding: 10px;"> <p>Hostname * ?</p> <input type="text" value="Enter Switch Hostname"/> <p>Username * ?</p> <input type="text" value="Enter Switch Username"/> <p>Password * ?</p> <input type="text" value="Enter Password"/> <p>SSH-IP * ?</p> <input type="text" value="Enter IP Address"/> <p>SSN Num ?</p> <input type="text" value="Enter SSN Num"/> <p>VPC Peer Keepalive ?</p> <input type="text" value="Enter IP Address"/> <p>VPC Domain ?</p> <input type="text" value="Enter VPC Domain"/> <p>VPC Peer Port Info ?</p> <input type="text" value="Enter VPC Port"/> <p>VPC Peer VLAN Info ?</p> <input type="text" value="Enter VPC VLAN Info"/> <p>BR Management Port Info ?</p> <input type="text" value="Enter BR Port Info"/> <p>BR Management PO Info ?</p> <input type="text" value="Enter BR PO Info"/> <p style="text-align: right;"> <input type="button" value="Save"/> <input type="button" value="Cancel"/> </p> </div> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th data-bbox="808 1373 1146 1428">Name</th> <th data-bbox="1146 1373 1484 1428">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="808 1428 1146 1482">Name</td> <td data-bbox="1146 1428 1484 1482">ToR switch name.</td> </tr> <tr> <td data-bbox="808 1482 1146 1537">Username</td> <td data-bbox="1146 1482 1484 1537">ToR switch username.</td> </tr> <tr> <td data-bbox="808 1537 1146 1591">Password</td> <td data-bbox="1146 1537 1484 1591">ToR switch password.</td> </tr> <tr> <td data-bbox="808 1591 1146 1646">SSH IP</td> <td data-bbox="1146 1591 1484 1646">ToR switch SSH IP.</td> </tr> <tr> <td data-bbox="808 1646 1146 1701">SSN Num</td> <td data-bbox="1146 1646 1484 1701">ToR switch ssn num.</td> </tr> <tr> <td data-bbox="808 1701 1146 1835">VPC Peer Keepalive</td> <td data-bbox="1146 1701 1484 1835">Peer Management IP. You cannot define if there is no peer.</td> </tr> </tbody> </table>	Name	Description	Name	ToR switch name.	Username	ToR switch username.	Password	ToR switch password.	SSH IP	ToR switch SSH IP.	SSN Num	ToR switch ssn num.	VPC Peer Keepalive	Peer Management IP. You cannot define if there is no peer.
Name	Description														
Name	ToR switch name.														
Username	ToR switch username.														
Password	ToR switch password.														
SSH IP	ToR switch SSH IP.														
SSN Num	ToR switch ssn num.														
VPC Peer Keepalive	Peer Management IP. You cannot define if there is no peer.														

Name	Description	
	VPC Domain	Cannot define if there is no peer.
	VPC Peer Port Info	Interface for vpc peer ports.
	VPC Peer VLAN Info	VLAN ids for vpc peer ports (optional).
	BR Management Port Info	Management interface of build node.
	BR Management PO Info	Port channel number for management interface of build node.
	BR Management VLAN info	VLAN id for management interface of build node (access).
Click Save .		

Note When the Tenant type ACI/VLAN is selected, the ToR switch information table differs and is mandatory.

Name	Description										
<p>Configure ToR</p>	<p>Is not checked, as by default ACI will configure the ToRs</p> <p>Switch Details</p>  <table border="1" data-bbox="894 911 1484 1320"> <tbody> <tr> <td>Host Name</td> <td>ToR switch name.</td> </tr> <tr> <td>VPC Peer keep alive</td> <td>Enter Peer must be exist pair.</td> </tr> <tr> <td>VPC Domain</td> <td>Enter an integer.</td> </tr> <tr> <td>BR management port info</td> <td>Enter BR management port info eg. Eth1/19 ,atleast one pair to be exist.</td> </tr> <tr> <td>Enter Node ID</td> <td>Entered integer must be unique.</td> </tr> </tbody> </table>	Host Name	ToR switch name.	VPC Peer keep alive	Enter Peer must be exist pair.	VPC Domain	Enter an integer.	BR management port info	Enter BR management port info eg. Eth1/19 ,atleast one pair to be exist.	Enter Node ID	Entered integer must be unique.
Host Name	ToR switch name.										
VPC Peer keep alive	Enter Peer must be exist pair.										
VPC Domain	Enter an integer.										
BR management port info	Enter BR management port info eg. Eth1/19 ,atleast one pair to be exist.										
Enter Node ID	Entered integer must be unique.										

Note If TOR_TYPE is selected as NCS-5500, the TOR switch information table differs and is mandatory.

Name	Description
<p>Configure ToR optional checkbox</p> <p>Note If NSC-5500 is selected as TOR_TYPE, configure TOR is set as mandatory.</p>	<p>Enabling this checkbox, changes the configure ToR section from false to true.</p> <p>Note Configure TOR is true then ToR switchinfo maps in servers.</p>

Name	Description
If you want to enter NCS details fill in the NCS-5500 Information table.	

Name	Description
	<p>Click (+) to add information for NCS-500 Switch.</p> <p>Switch Details</p> <div style="border: 1px solid #ccc; padding: 10px;"> <p>Hostname * +</p> <input type="text" value="Enter Switch Hostname"/> <p>Username * +</p> <input type="text" value="Enter Switch Username"/> <p>Password * +</p> <input type="text" value="Enter Password"/> <p>SSH-IP * +</p> <input type="text" value="Enter IP Address"/> <p>VPC Peer Keepalive +</p> <input type="text" value="Enter IP Address"/> <p>VPC Peer Port Info +</p> <input type="text" value="Enter VPC Port"/> <p>VPC Peer Port Address +</p> <input type="text" value="Enter VPC Port Address"/> <p>ISIS Loopback Address +</p> <input type="text" value="Enter ISIS Loopback Address"/> <p>ISIS Net Entity Title +</p> <input type="text" value="Enter ISIS net entity title"/> <p>ISIS Prefix SID +</p> <input type="text" value="Enter ISIS Prefix SID"/> <p>BR Management Port Info +</p> <input type="text" value="Enter BR Port Info"/> <p>BR Management PO Info +</p> <input type="text" value="Enter BR PO Info"/> <p style="text-align: right;"> <input type="button" value="Save"/> <input type="button" value="Cancel"/> </p> </div>
Name	Description
Name	Enter the NCS-5500 hostname.
User Name	Enter the NCS-5500 username.
Password	Enter the NCS-5500 password.
SSH IP	Enter the NCS-5500 ssh IP Address.
VPC Peer Link	Peer management IP.

Name	Description	
	Name	Description
	BR Management PO Info	Port channel number for management interface of build node.
	BR Management VLAN info	VLAN id for management interface of build node (access).
	VPC Peer Port Info	Interface for vpc peer ports.
	VPC Peer Port Address	Address for ISIS exchange.
	ISIS Loopback Interface address	ISIS loopback IP Address.
	ISIS net entity title	Enter a String.
	ISIS prefix SID	Integer between 16000 to 1048575. Optional, if TOR-TYPE is NCS-5500. Entry not allowed when ESI_PREFIX is defined.


When TOR-TYPE selected as NCS-5500 and 2 NCS-5500 are configured, it is mandatory to configure MULTI_SEGMENT_ROUTING_INFO

Name	Description
BGP AS Number field	Integer between 1 to 65535.
ISIS Area Tag field	A valid string.
Loopback Interface name field	Loopback Interface name.
API bundle ID field	Integer between 1 to 65535.
API bridge domain field	String (Optional, only needed when br_api of mgmt node is also going through NCS-5500; this item and api_bundle_id are mutually exclusive).
EXT bridge domain field	A valid string (user pre-provisions physical, bundle interface, sub-interface and external BD for external uplink and provides external BD info setup_data).


When TOR-TYPE is NCS-5500, you can optionally define ESI_PREFIX field.

Name	Description
ESI_PREFIX	Ethernet-segment identifier type Example: 91.<Pod_number>.<pod_region_number>.00.00.00.00.


- Click **NFVI Monitoring** checkbox in Blueprint Initial Setup to enable the NFVI Monitoring configuration tab.




Name	Description
Admin IP	IP Address of Control Center VM
Management VIP	VIP for ceilometer/dispatcher to use, must be unique across VIM Pod
Host Name	Hostname of Collector VM
Password	Password of Collector VM
CCUSER Password	Password of CCUSER
Admin IP	SSH IP of Collector VM
Management IP	Management IP of Collector VM

Name	Description				
<p>Collector ToR Connections</p>	<ol style="list-style-type: none"> 1. Click on (+) icon to Add Collector ToR Connections. 2. Select the ToR switches from list to add the information. 3. It is optional and available for ToR type NCS-5500 4. For now, it supports adding only one Collector ToR Connection <p>Add Collector Tor Connections</p>  <table border="1" data-bbox="933 947 1523 1073"> <tr> <td>Port Channel</td> <td>Enter port channel.</td> </tr> <tr> <td>Switch - {torSwitch-hostname}</td> <td>Enter port number, E.g:eth1/15.</td> </tr> </table> <p>Click Save</p>	Port Channel	Enter port channel.	Switch - {torSwitch-hostname}	Enter port number, E.g:eth1/15.
Port Channel	Enter port channel.				
Switch - {torSwitch-hostname}	Enter port number, E.g:eth1/15.				
<p>Rabbit MQ User Name</p>	<p>Enter Rabbit MQ username.</p>				

8. Click **OpenStack Setup** Tab to advance to the **OpenStack Setup** Configuration page. On the **OpenStack Setup** Configuration page of the Cisco VIM Unified Management wizard, complete the following fields:


Name	Description										
<p>HA Proxy</p>	<p>Fill in the following details:</p>  <table border="1" data-bbox="813 806 1484 1220"> <tr> <td data-bbox="813 806 1151 898">External VIP Address field</td> <td data-bbox="1151 806 1484 898">Enter IP address of External VIP.</td> </tr> <tr> <td data-bbox="813 898 1151 991">External VIP Address IPv6 field</td> <td data-bbox="1151 898 1484 991">Enter IPv6 address of External VIP.</td> </tr> <tr> <td data-bbox="813 991 1151 1045">Virtual Router ID field</td> <td data-bbox="1151 991 1484 1045">Enter the Router ID for HA.</td> </tr> <tr> <td data-bbox="813 1045 1151 1138">Internal VIP Address IPv6 field</td> <td data-bbox="1151 1045 1484 1138">Enter IPv6 address of Internal IP.</td> </tr> <tr> <td data-bbox="813 1138 1151 1220">Internal VIP Address field</td> <td data-bbox="1151 1138 1484 1220">Enter IP address of Internal VIP.</td> </tr> </table>	External VIP Address field	Enter IP address of External VIP.	External VIP Address IPv6 field	Enter IPv6 address of External VIP.	Virtual Router ID field	Enter the Router ID for HA.	Internal VIP Address IPv6 field	Enter IPv6 address of Internal IP.	Internal VIP Address field	Enter IP address of Internal VIP.
External VIP Address field	Enter IP address of External VIP.										
External VIP Address IPv6 field	Enter IPv6 address of External VIP.										
Virtual Router ID field	Enter the Router ID for HA.										
Internal VIP Address IPv6 field	Enter IPv6 address of Internal IP.										
Internal VIP Address field	Enter IP address of Internal VIP.										
<p>Keystone</p>	<p>Mandatory fields are pre-populated.</p>  <table border="1" data-bbox="813 1591 1484 1703"> <tr> <td data-bbox="813 1591 1151 1646">Admin User Name</td> <td data-bbox="1151 1591 1484 1646">admin.</td> </tr> <tr> <td data-bbox="813 1646 1151 1703">Admin Tenant Name</td> <td data-bbox="1151 1646 1484 1703">admin.</td> </tr> </table>	Admin User Name	admin.	Admin Tenant Name	admin.						
Admin User Name	admin.										
Admin Tenant Name	admin.										

Name	Description
LDAP	

Name	Description																										
	<p>LDAP enable checkbox which by default is false, if LDAP is enabled on keystone.</p>  <table border="1" data-bbox="813 940 1487 1841"> <tbody> <tr> <td>Domain Name field</td> <td>Enter name for Domain name.</td> </tr> <tr> <td>Object Class for Users field</td> <td>Enter a string as input.</td> </tr> <tr> <td>Object Class for Groups field</td> <td>Enter a string.</td> </tr> <tr> <td>Domain Name Tree for Users field</td> <td>Enter a string.</td> </tr> <tr> <td>Domain Name Tree for Groups field</td> <td>Enter a string.</td> </tr> <tr> <td>Suffix for Domain Name field</td> <td>Enter a string.</td> </tr> <tr> <td>URL field</td> <td>Enter a URL with ending port number.</td> </tr> <tr> <td>Domain Name of Bind User field</td> <td>Enter a string.</td> </tr> <tr> <td>Password field</td> <td>Enter Password as string format.</td> </tr> <tr> <td>User Filter field</td> <td>Enter filter name as string.</td> </tr> <tr> <td>User ID Attribute field</td> <td>Enter a string.</td> </tr> <tr> <td>User Name Attribute field</td> <td>Enter a string.</td> </tr> <tr> <td>User Mail Attribute field</td> <td>Enter a string.</td> </tr> </tbody> </table>	Domain Name field	Enter name for Domain name.	Object Class for Users field	Enter a string as input.	Object Class for Groups field	Enter a string.	Domain Name Tree for Users field	Enter a string.	Domain Name Tree for Groups field	Enter a string.	Suffix for Domain Name field	Enter a string.	URL field	Enter a URL with ending port number.	Domain Name of Bind User field	Enter a string.	Password field	Enter Password as string format.	User Filter field	Enter filter name as string.	User ID Attribute field	Enter a string.	User Name Attribute field	Enter a string.	User Mail Attribute field	Enter a string.
Domain Name field	Enter name for Domain name.																										
Object Class for Users field	Enter a string as input.																										
Object Class for Groups field	Enter a string.																										
Domain Name Tree for Users field	Enter a string.																										
Domain Name Tree for Groups field	Enter a string.																										
Suffix for Domain Name field	Enter a string.																										
URL field	Enter a URL with ending port number.																										
Domain Name of Bind User field	Enter a string.																										
Password field	Enter Password as string format.																										
User Filter field	Enter filter name as string.																										
User ID Attribute field	Enter a string.																										
User Name Attribute field	Enter a string.																										
User Mail Attribute field	Enter a string.																										


Name	Description	
	Group Name Attribute field	Enter a string.



Name	Description
Neutron	



Name	Description
	<p>Neutron fields would change on the basis of Tenant Network Type Selection from Blueprint Initial Setup. Following are the options available for Neutron for OVS/VLAN:</p>  <p>Tenant Network Type field Auto Filled based on the Tenant Network Type selected in the Blueprint Initial Setup page.</p> <p>Mechanism Drivers field Auto Filled based on the Tenant Network Type selected in Blueprint Initial Setup page.</p> <p>NFV Hosts field Auto filled with the Compute you added in Server and Roles. If you select All in this section NFV_HOSTS: ALL will be added to the Blueprint or you can select one particular compute. For Eg: NFV_HOSTS: compute-server-1, compute-server-2.</p> <p>Tenant VLAN Ranges field List of ranges separated by comma form start:end.</p> <p>Provider VLAN Ranges field List of ranges separated by comma form start:end.</p> <p>VM Hugh Page Size (available for NFV_HOSTS option) field 2M or 1G (optional, defaults to 2M)</p> <p>VM_HUGHPAGE_PERCENTAGE Optional, defaults to 100%; can range between 0 and 100</p>

Name	Description
	<p>VSWITCH_WORKER_PROFILE Allowed only for VPP</p> <p>Optionally available options: numa_zero and even</p> <ul style="list-style-type: none"> • numa_zero: Reserved cores will always reside in NUMA node 0. • Even : Reserved cores will be evenly distributed across all NUMA.
	<p>NR_RESERVED_VSWITCH_PCORES Allowed only for VPP</p> <p>Number of cores associated to VPP, defaults to 2.</p>
	<p>Enable Jumbo Frames field Enable the checkbox</p>
<p>For Tenant Network Type Linux Bridge everything remains the same but Tenant VLAN Ranges will be removed.</p>	


Name	Description
CEPH	


Name	Description																
	<p>1. 1. When Object Storage Backend is selected Central in blueprint initial setup.</p>  <p>The screenshot shows the 'OpenStack Setup' configuration page. The 'Ceph Mode' dropdown is set to 'Central'. Other fields include 'Cluster ID', 'Monitor Host', 'Monitor Members', 'Secret UUID', 'NOVA RBD POOL' (set to 'vms'), and 'NOVA Boot From' (set to 'Local'). The 'CEPH NAT' checkbox is checked.</p> <table border="1" data-bbox="857 751 1489 1255"> <tbody> <tr> <td>CEPH Mode</td> <td>By default Central.</td> </tr> <tr> <td>Cluster ID</td> <td>Enter Cluster ID.</td> </tr> <tr> <td>Monitor Host</td> <td>Enter Monitor Host for CEPH</td> </tr> <tr> <td>Monitor Members</td> <td>Enter Monitor Members for CEPH</td> </tr> <tr> <td>Secret UUID</td> <td>Enter Secret UUID for CEPH</td> </tr> <tr> <td>NOVA Boot from</td> <td>Drop down selection. You can choose CEPH or local.</td> </tr> <tr> <td>NOVA RBD POOL</td> <td>Enter NOVA RBD Pool (default's to vms)</td> </tr> <tr> <td>CEPH NAT</td> <td>Optional, needed for Central Ceph and when mgmt network is not routable</td> </tr> </tbody> </table> <p>2. When Object Storage Backend is selected Dedicated in blueprint initial setup.</p>  <p>The screenshot shows the 'OpenStack Setup' configuration page. The 'Ceph Mode' dropdown is set to 'Dedicated'. The 'NOVA Boot From' dropdown is set to 'Local'. The 'CEPH NAT' checkbox is unchecked.</p> <ul style="list-style-type: none"> • CEPH Mode: By default Dedicated. • NOVA Boot: From drop down selection you can choose CEPH or local. <p>3. When Object Storage Backend is selected NetApp in blueprint initial setup.</p>	CEPH Mode	By default Central.	Cluster ID	Enter Cluster ID.	Monitor Host	Enter Monitor Host for CEPH	Monitor Members	Enter Monitor Members for CEPH	Secret UUID	Enter Secret UUID for CEPH	NOVA Boot from	Drop down selection. You can choose CEPH or local.	NOVA RBD POOL	Enter NOVA RBD Pool (default's to vms)	CEPH NAT	Optional, needed for Central Ceph and when mgmt network is not routable
CEPH Mode	By default Central.																
Cluster ID	Enter Cluster ID.																
Monitor Host	Enter Monitor Host for CEPH																
Monitor Members	Enter Monitor Members for CEPH																
Secret UUID	Enter Secret UUID for CEPH																
NOVA Boot from	Drop down selection. You can choose CEPH or local.																
NOVA RBD POOL	Enter NOVA RBD Pool (default's to vms)																
CEPH NAT	Optional, needed for Central Ceph and when mgmt network is not routable																


Name	Description
	<p>Create Blueprint configuration</p> 
<p>GLANCE</p>	<p>1. When Object Storage Backend is selected Central in blueprint initial setup.</p> <p>Create Blueprint configuration</p>  <p>When Object Storage Backend is selected Dedicated in blueprint initial setup.</p> <p>Create Blueprint configuration</p>  <p>Note By default Populated for CEPH Dedicated with Store Backend value as CEPH.</p>


Name	Description
<p>CINDER</p>	<p>By default Populated for CEPH Dedicated with Volume Driver value as CEPH.</p>  <p>2. When Object Storage Backend is selected Dedicated in blueprint initial setup.</p>  <p>Note By default Populated for CEPH Dedicated with Volume Driver value as CEPH.</p>

Name	Description
VMTP optional section, this will be visible only if VMTP is selected from Blueprint Initial Setup. For VTS tenant type Provider network is only supported.	

Name	Description		
	<p>Check one of the check boxes to specify a VMTP network:</p> <ul style="list-style-type: none"> • Provider Network • External Network <p>For the Provider Network complete the following:</p> <p>Create Blueprint configuration</p> 		
	<table border="1"> <tr> <td data-bbox="813 926 1149 1003">Network Name field</td> <td data-bbox="1149 926 1482 1003">Enter the name for the external network.</td> </tr> </table>	Network Name field	Enter the name for the external network.
Network Name field	Enter the name for the external network.		
	<table border="1"> <tr> <td data-bbox="813 1016 1149 1094">Subnet field</td> <td data-bbox="1149 1016 1482 1094">Enter the Subnet for Provider Network.</td> </tr> </table>	Subnet field	Enter the Subnet for Provider Network.
Subnet field	Enter the Subnet for Provider Network.		
	<table border="1"> <tr> <td data-bbox="813 1106 1149 1184">Network IP Start field</td> <td data-bbox="1149 1106 1482 1184">Enter the starting floating IPv4 address.</td> </tr> </table>	Network IP Start field	Enter the starting floating IPv4 address.
Network IP Start field	Enter the starting floating IPv4 address.		
	<table border="1"> <tr> <td data-bbox="813 1197 1149 1274">Network IP End field</td> <td data-bbox="1149 1197 1482 1274">Enter the ending floating IPv4 address.</td> </tr> </table>	Network IP End field	Enter the ending floating IPv4 address.
Network IP End field	Enter the ending floating IPv4 address.		
	<table border="1"> <tr> <td data-bbox="813 1287 1149 1365">Network Gatewayfield</td> <td data-bbox="1149 1287 1482 1365">Enter the IPv4 address for the Gateway.</td> </tr> </table>	Network Gateway field	Enter the IPv4 address for the Gateway.
Network Gateway field	Enter the IPv4 address for the Gateway.		
	<table border="1"> <tr> <td data-bbox="813 1377 1149 1455">DNS Server field</td> <td data-bbox="1149 1377 1482 1455">Enter the DNS server IPv4 address.</td> </tr> </table>	DNS Server field	Enter the DNS server IPv4 address.
DNS Server field	Enter the DNS server IPv4 address.		
	<table border="1"> <tr> <td data-bbox="813 1467 1149 1545">Segmentation ID field</td> <td data-bbox="1149 1467 1482 1545">Enter the segmentation ID.</td> </tr> </table>	Segmentation ID field	Enter the segmentation ID.
Segmentation ID field	Enter the segmentation ID.		
	<p>For External Network fill in the following details:</p> 		


Name	Description												
	<table border="1"> <tr> <td data-bbox="847 289 1187 365">Network Name field</td> <td data-bbox="1190 289 1528 365">Enter the name for the external network.</td> </tr> <tr> <td data-bbox="847 369 1187 445">IP Start field</td> <td data-bbox="1190 369 1528 445">Enter the starting floating IPv4 address.</td> </tr> <tr> <td data-bbox="847 449 1187 525">IP End field</td> <td data-bbox="1190 449 1528 525">Enter the ending floating IPv4 address.</td> </tr> <tr> <td data-bbox="847 529 1187 604">Gateway field</td> <td data-bbox="1190 529 1528 604">Enter the IPv4 address for the Gateway.</td> </tr> <tr> <td data-bbox="847 609 1187 684">DNS Server field</td> <td data-bbox="1190 609 1528 684">Enter the DNS server IPv4 address.</td> </tr> <tr> <td data-bbox="847 688 1187 764">Subnet field</td> <td data-bbox="1190 688 1528 764">Enter the Subnet for External Network.</td> </tr> </table>	Network Name field	Enter the name for the external network.	IP Start field	Enter the starting floating IPv4 address.	IP End field	Enter the ending floating IPv4 address.	Gateway field	Enter the IPv4 address for the Gateway.	DNS Server field	Enter the DNS server IPv4 address.	Subnet field	Enter the Subnet for External Network.
Network Name field	Enter the name for the external network.												
IP Start field	Enter the starting floating IPv4 address.												
IP End field	Enter the ending floating IPv4 address.												
Gateway field	Enter the IPv4 address for the Gateway.												
DNS Server field	Enter the DNS server IPv4 address.												
Subnet field	Enter the Subnet for External Network.												
<p>TLS optional section, this will be visible only if TLS is selected from Blueprint Initial Setup Page.</p>	<p>TLS has two options:</p> <ul style="list-style-type: none"> • External LB VIP FQDN - Text Field. • External LB VIP TLS - True/False. By default this option is false. 												
<p>Under the OpenStack setup tab, Vim_admins tab will be visible only when Vim_admins is selected from the Optional Features & Services under the Blueprint Initial setup tab</p>	<p>Following are the field descriptions for VIM Admins:</p>  <table border="1"> <tr> <td data-bbox="847 1619 1187 1675">User Name</td> <td data-bbox="1190 1619 1528 1675">Enter username</td> </tr> <tr> <td data-bbox="847 1680 1187 1801">Password</td> <td data-bbox="1190 1680 1528 1801">Password field. Admin hash password should always start with \$6.</td> </tr> </table>	User Name	Enter username	Password	Password field. Admin hash password should always start with \$6.								
User Name	Enter username												
Password	Password field. Admin hash password should always start with \$6.												

Name	Description												
<p>SwiftStack optional section will be visible only if SwiftStack is selected from Blueprint Initial Setup Page. SwiftStack is only supported with KeyStone2. If you select Keystone3, swiftstack will not be available to configure.</p>	<p>Following are the options that needs to be filled for SwiftStack:</p>  <table border="1" data-bbox="820 688 1487 1318"> <tr> <td data-bbox="820 688 1149 814">Cluster End Point</td> <td data-bbox="1149 688 1487 814">IP address of PAC (proxy-account-container) endpoint.</td> </tr> <tr> <td data-bbox="820 814 1149 903">Admin User</td> <td data-bbox="1149 814 1487 903">Admin user for swift to authenticate in keystone.</td> </tr> <tr> <td data-bbox="820 903 1149 1056">Admin Tenant</td> <td data-bbox="1149 903 1487 1056">The service tenant corresponding to the Account-Container used by Swiftstack.</td> </tr> <tr> <td data-bbox="820 1056 1149 1209">Reseller Prefix</td> <td data-bbox="1149 1056 1487 1209">Reseller_prefix as configured for Keysone Auth,AuthToken support in Swiftstack E.g KEY_</td> </tr> <tr> <td data-bbox="820 1209 1149 1264">Admin Password</td> <td data-bbox="1149 1209 1487 1264">swiftstack_admin_password</td> </tr> <tr> <td data-bbox="820 1264 1149 1318">Protocol</td> <td data-bbox="1149 1264 1487 1318">http or https</td> </tr> </table>	Cluster End Point	IP address of PAC (proxy-account-container) endpoint.	Admin User	Admin user for swift to authenticate in keystone.	Admin Tenant	The service tenant corresponding to the Account-Container used by Swiftstack.	Reseller Prefix	Reseller_prefix as configured for Keysone Auth,AuthToken support in Swiftstack E.g KEY_	Admin Password	swiftstack_admin_password	Protocol	http or https
Cluster End Point	IP address of PAC (proxy-account-container) endpoint.												
Admin User	Admin user for swift to authenticate in keystone.												
Admin Tenant	The service tenant corresponding to the Account-Container used by Swiftstack.												
Reseller Prefix	Reseller_prefix as configured for Keysone Auth,AuthToken support in Swiftstack E.g KEY_												
Admin Password	swiftstack_admin_password												
Protocol	http or https												

Name	Description																								
<p>APICINFO tab is available in Openstack setup, when the Tenant type ACI/VLAN is selected in blueprint initial setup.</p>																									
<p>Note When ACI/VLAN is selected then ToR switch from initial setup is mandatory.</p>	<table border="1"> <thead> <tr> <th data-bbox="857 674 1187 724">Name</th> <th data-bbox="1195 674 1520 724">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="857 730 1187 842"> <p>APIC Hosts field</p> </td> <td data-bbox="1195 730 1520 842"> <p>Enter host input. Example: <ip1 host1>:[port] . max of 3, min of 1, not 2;</p> </td> </tr> <tr> <td data-bbox="857 848 1187 898"> <p>apic_username field</p> </td> <td data-bbox="1195 848 1520 898"> <p>Enter a string format.</p> </td> </tr> <tr> <td data-bbox="857 905 1187 955"> <p>apic_password field</p> </td> <td data-bbox="1195 905 1520 955"> <p>Enter Password.</p> </td> </tr> <tr> <td data-bbox="857 961 1187 1052"> <p>apic_system_id field</p> </td> <td data-bbox="1195 961 1520 1052"> <p>Enter input as string. Max length 8.</p> </td> </tr> <tr> <td data-bbox="857 1058 1187 1108"> <p>apic_resource_prefix field</p> </td> <td data-bbox="1195 1058 1520 1108"> <p>Enter string max length 6.</p> </td> </tr> <tr> <td data-bbox="857 1115 1187 1165"> <p>apic_tep_address_pool field</p> </td> <td data-bbox="1195 1115 1520 1165"> <p>Allowed only 10.0.0.0/16</p> </td> </tr> <tr> <td data-bbox="857 1171 1187 1249"> <p>multiclass_address_pool field</p> </td> <td data-bbox="1195 1171 1520 1249"> <p>Allowed only 225.0.0.0/15</p> </td> </tr> <tr> <td data-bbox="857 1255 1187 1306"> <p>apic_pod_id field</p> </td> <td data-bbox="1195 1255 1520 1306"> <p>Enter integer(1- 65535)</p> </td> </tr> <tr> <td data-bbox="857 1312 1187 1362"> <p>apic_installer_tenant field</p> </td> <td data-bbox="1195 1312 1520 1362"> <p>Enter String, max length 32</p> </td> </tr> <tr> <td data-bbox="857 1369 1187 1419"> <p>apic_installer_vrf field</p> </td> <td data-bbox="1195 1369 1520 1419"> <p>Enter String, max length 32</p> </td> </tr> <tr> <td data-bbox="857 1425 1187 1476"> <p>api_l3out_network field</p> </td> <td data-bbox="1195 1425 1520 1476"> <p>Enter String, max length 32</p> </td> </tr> </tbody> </table>	Name	Description	<p>APIC Hosts field</p>	<p>Enter host input. Example: <ip1 host1>:[port] . max of 3, min of 1, not 2;</p>	<p>apic_username field</p>	<p>Enter a string format.</p>	<p>apic_password field</p>	<p>Enter Password.</p>	<p>apic_system_id field</p>	<p>Enter input as string. Max length 8.</p>	<p>apic_resource_prefix field</p>	<p>Enter string max length 6.</p>	<p>apic_tep_address_pool field</p>	<p>Allowed only 10.0.0.0/16</p>	<p>multiclass_address_pool field</p>	<p>Allowed only 225.0.0.0/15</p>	<p>apic_pod_id field</p>	<p>Enter integer(1- 65535)</p>	<p>apic_installer_tenant field</p>	<p>Enter String, max length 32</p>	<p>apic_installer_vrf field</p>	<p>Enter String, max length 32</p>	<p>api_l3out_network field</p>	<p>Enter String, max length 32</p>
Name	Description																								
<p>APIC Hosts field</p>	<p>Enter host input. Example: <ip1 host1>:[port] . max of 3, min of 1, not 2;</p>																								
<p>apic_username field</p>	<p>Enter a string format.</p>																								
<p>apic_password field</p>	<p>Enter Password.</p>																								
<p>apic_system_id field</p>	<p>Enter input as string. Max length 8.</p>																								
<p>apic_resource_prefix field</p>	<p>Enter string max length 6.</p>																								
<p>apic_tep_address_pool field</p>	<p>Allowed only 10.0.0.0/16</p>																								
<p>multiclass_address_pool field</p>	<p>Allowed only 225.0.0.0/15</p>																								
<p>apic_pod_id field</p>	<p>Enter integer(1- 65535)</p>																								
<p>apic_installer_tenant field</p>	<p>Enter String, max length 32</p>																								
<p>apic_installer_vrf field</p>	<p>Enter String, max length 32</p>																								
<p>api_l3out_network field</p>	<p>Enter String, max length 32</p>																								


Name	Description														
<p>VTS tab is available in Openstack setup, when Tenant Type is VTS/VLAN selected.</p> <p>If vts day0 is enabled then SSH username and SSH password is mandatory.</p> <p>If SSH_username is input present then SSH password is mandatory vice-versa</p>	 <table border="1" data-bbox="820 556 1485 997"> <thead> <tr> <th>Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>VTS Day0 (checkbox)</td> <td>True or false default is false.</td> </tr> <tr> <td>VTS User name</td> <td>Enter as string does not contain special characters.</td> </tr> <tr> <td>VTS Password</td> <td>Enter password</td> </tr> <tr> <td>VTS NCS IP</td> <td>Enter IP Address format.</td> </tr> <tr> <td>VTC SSH Username</td> <td>Enter a string</td> </tr> <tr> <td>VTC SHH Password</td> <td>Enter password</td> </tr> </tbody> </table>	Name	Description	VTS Day0 (checkbox)	True or false default is false.	VTS User name	Enter as string does not contain special characters.	VTS Password	Enter password	VTS NCS IP	Enter IP Address format.	VTC SSH Username	Enter a string	VTC SHH Password	Enter password
Name	Description														
VTS Day0 (checkbox)	True or false default is false.														
VTS User name	Enter as string does not contain special characters.														
VTS Password	Enter password														
VTS NCS IP	Enter IP Address format.														
VTC SSH Username	Enter a string														
VTC SHH Password	Enter password														

9. For SolidFire, enter the following:

Name	Description								
<p>SolidFire is visible for configuration on day0</p> <p>SolidFire is not allowed as a day-2 deployment option</p> <p>SolidFire is always available with CEPH.</p>	 <table border="1" data-bbox="901 1522 1477 1816"> <tbody> <tr> <td>Cluster MVIP field</td> <td>Management IP of SolidFire cluster.</td> </tr> <tr> <td>Cluster SVIP field</td> <td>Storage VIP of SolidFire cluster.</td> </tr> <tr> <td>Admin Username</td> <td>Admin user on SolidFire cluster</td> </tr> <tr> <td>Admin Password</td> <td>Admin password on SolidFire cluster.</td> </tr> </tbody> </table>	Cluster MVIP field	Management IP of SolidFire cluster.	Cluster SVIP field	Storage VIP of SolidFire cluster.	Admin Username	Admin user on SolidFire cluster	Admin Password	Admin password on SolidFire cluster.
Cluster MVIP field	Management IP of SolidFire cluster.								
Cluster SVIP field	Storage VIP of SolidFire cluster.								
Admin Username	Admin user on SolidFire cluster								
Admin Password	Admin password on SolidFire cluster.								

10. If **Syslog Export** or **NFVBENCH** is selected in **Blueprint Initial Setup** Page, then **Services Setup** page will be enabled for user to view. Following are the options under **Services Setup** Tab:

Name	Description												
<p>Syslog Export</p>	<p>Following are the options for Syslog Settings:</p> <p>User can add maximum of three entries.</p> <p>To add new SysLog information, click on Add SysLog button, fill all the required information listed below and hit Save button.</p>  <table border="1" data-bbox="667 877 1536 1255"> <tr> <td>Remote Host</td> <td>Enter Syslog IP address.</td> </tr> <tr> <td>Protocol</td> <td>Only UDP is supported.</td> </tr> <tr> <td>Facility</td> <td>Defaults to local5.</td> </tr> <tr> <td>Severity</td> <td>Defaults to debug.</td> </tr> <tr> <td>Clients</td> <td>Defaults to ELK.</td> </tr> <tr> <td>Port</td> <td>Defaults to 514 but can be modified by the User.</td> </tr> </table>	Remote Host	Enter Syslog IP address.	Protocol	Only UDP is supported.	Facility	Defaults to local5.	Severity	Defaults to debug.	Clients	Defaults to ELK.	Port	Defaults to 514 but can be modified by the User.
Remote Host	Enter Syslog IP address.												
Protocol	Only UDP is supported.												
Facility	Defaults to local5.												
Severity	Defaults to debug.												
Clients	Defaults to ELK.												
Port	Defaults to 514 but can be modified by the User.												

Name	Description
NFVBENCH	<p>NFVBENCH enable checkbox by default is false.</p> <p>Add ToR information connect to Switch:</p>  <ul style="list-style-type: none"> • Select a TOR Switch and enter the Switch name. • Enter the port number. For example, eth1/5 . VTEP VLANS (mandatory and needed only for VTS/VXLAN). Enter two different VLANs for VLAN1 and VLAN2. • NIC Ports: INT1 and INT2 optional input. Enter the two port numbers of the 4-port 10G Intel NIC at the management node used for NFVBench. <p>NIC Slot: Optional input, indicates which NIC to use in case there are multiple NICs.</p> <p>Note NIC port and slot need to be together.</p>
ENABLE_ESC_PRIV	Enable the checkbox to set it as True. By default it is False .


Step 5 Click **Offline validation** button to initiate an offline validation of the Blueprint.

Step 6 Once the **Offline validation** is successful, **Save** option will be enabled for you which when clicked would redirect you to the **Blueprint Management** Page.


Redeploy Multiple Install Stages during Cisco VIM Installation using Unified Management

You can redeploy Cisco VIM in multiple stages during blueprint installation using the Cisco VIM Unified Management dashboard.

Step 1 When the blueprint installation status is in Active/failed/Installation failed and stage install status as Failed/NotRun/Skipped., the redeployed icon is displayed.



Step 2 Click **Redeploy** icon to redeploy multiple stages during installation. A confirmation dialogue box appears.



Step 3 Select the stages to be installed.

- Step 4** You can select the stages only in sequence. For example, you can select the VMTP stage (current) stage only if the Orchestration (previous) stage is selected for blueprint installation (assuming Orchestration was in Failed/NotRun state)
- Step 5** Click **Proceed** to run the installation.
-

Downloading Blueprint

Before you begin

You must have atleast one blueprint (In any state Active/In-Active or In-progress), in the **Blueprint Management Page**.

- Step 1** Log in to **CISCO VIM Unified Management**.
- Step 2** In the navigation pane, expand the **Pre-Install Section**.
- Step 3** Click **Blueprint Management**.
- Step 4** Go-to **Download** for any Blueprint under Action title. (**Download Button** > **Downward Arrow** (with tooltip Preview & Download YAML)).
- Step 5** Click the **Download** icon.
A pop to view the Blueprint in the YAML format is displayed.
- Step 6** Click the **Download** button at the bottom left of the pop-up window.
YAML is saved locally with the same name of the Blueprint.
-

Validating Blueprint

- Step 1** Log in to **CISCO VIM Unified Management**.
- Step 2** In the **Navigation** pane, expand the **Pre-Install Section**.
- Step 3** Click **Blueprint Creation**.
- Step 4** Upload an existing YAML, or create a **New Blueprint**.
Fill all the mandatory fields so that all Red Cross changes to **Green Tick**.
- Step 5** Enter the name of the Blueprint.
- Step 6** Click **Offline Validation**.
Only, if the Validation is successful, the Unified Management allows you to save the blueprint.
-

What to do next

If you see any errors, a hyperlink is created for those errors. Click the link to be navigated to the page where error has been encountered.

Managing Post Install Features


Cisco VIM provides an orchestration that helps in lifecycle management of a cloud. VIM is responsible for pod management activities which includes fixing both hardware and software issues with one-touch automation. VIM Unified Management provides the visualization of the stated goal. As a result, it integrates with POST install features that Cisco VIM offers through its Rest API. These features are enabled only if there is an active Blueprint deployment on the pod.

Monitoring the Pod

Cisco VIM uses EFK (Elasticsearch, Fluentd, and Kibana) to monitor the OpenStack services, by cross-launching the Kibana dashboard.

To cross launch Kibana, complete the following instructions:

- Step 1** In the navigation pane, click **Post-Install > Logging**.
- Step 2** Click **Click here to view Kibana in new tab**.
- Step 3** Enter the **Username** as Admin.
- Step 4** Enter the **Kibana_PASSWORD** password that is obtained from `/root/installer-<tagid>/openstack-configs/secrets.yaml` in the management node.



Cross Launching Horizon

Horizon is the canonical implementation of OpenStack's Dashboard, which provides a web-based user interface to OpenStack services including Nova, Swift and, Keystone.



-
- Step 1** In the navigation pane, click **Post-Install > Horizon**.
- Step 2** Click the link **Click here to view Horizon logs in new tab**. You will be redirected to Horizon landing page in a new tab.
- Step 3** Enter the ADMIN_USER_PASSWORD obtained from /root/installer-`<tagid>/openstack-configs/secrets.yaml` in the management node.
-

NFVI Monitoring

NFVI monitoring is the Cross launch browser same as Horizon. NFVI monitoring link is available in the post install only if the setupdata has NFVI Monitoring configuration during the cloud deployment. NFVI Monitoring checks the status of **Collector VM1 Info** and **Collector VM2 Info**.

-
- Step 1** In the navigation pane, click **Post-Install > NFVI Monitoring**.
- Step 2** Click the link **Click here to view NFVI monitoring**.
You will be redirected to NFVI Monitoring page.
-

Run VMTP

Run VMTP is divided in two sections:

- **Results for Auto Run:** This shows the results of VMTP which was run during the cloud deployment (Blueprint Installation).
- **Results for Manual Run:** Run the VMTP on demand. To run VMTP on demand, click **Run VMTP**.



Note If VMTP stage was skipped or has not-run during Blueprint Installation, this section of POST Install would be disabled for the user.

Run CloudPulse

In VIM 2.0 and later, we provide an integrated tool, called Cloud Pulse, that periodically checks the cloud services endpoint. The results of these tests are reflected under the Cloud Pulse link. Also, you can run these API endpoint tests on demand, and fetch the result of these tests by refreshing the table.

OpenStack CloudPulse tool is used to verify Cisco NFVI health. CloudPulse servers are installed in containers on all Cisco NFVI control nodes and CloudPulse clients are installed on the management node.

CloudPulse has two test sets: endpoint scenario (runs as a cron or manually) and operator test (run manually).

Following are the tests which are supported in CloudPulse:

Endpoint tests include

- cinder_endpoint
- glance_endpoint
- keystone_endpoint
- nova_endpoint
- neutron_endpoint

Operator tests include

- ceph_check
- docker_check
- galera_check
- node_check
- rabbitmq_check

CloudPulse

Cloudpulse Monitoring for : **Fixadent-BP**

cinder_endpoint

Name	Result	State	Test Type	Created Date	Updated Date
neutron_endpoint	success	success	periodic	05/04/2018, 11:51:28	05/04/2018, 11:51:29
docker_check	All docker containers are ...	success	periodic	05/04/2018, 11:55:17	05/04/2018, 11:55:20
nova_endpoint	success	success	periodic	05/04/2018, 11:51:29	05/04/2018, 11:51:30
cinder_endpoint	success	success	periodic	05/04/2018, 11:55:20	05/04/2018, 11:55:27
keystone_endpoint	success	success	periodic	05/04/2018, 11:55:20	05/04/2018, 11:55:28
rabbitmq_check	Running Nodes : [rabbit...	success	periodic	05/04/2018, 11:55:20	05/04/2018, 11:55:27
galera_check	Active Nodes : 10.10.35...	success	periodic	05/04/2018, 11:55:22	05/04/2018, 11:55:25
glance_endpoint	success	success	periodic	05/04/2018, 11:55:28	05/04/2018, 11:55:28
neutron_endpoint	success	success	periodic	05/04/2018, 11:55:28	05/04/2018, 11:55:29
nova_endpoint	success	success	periodic	05/04/2018, 11:55:29	05/04/2018, 11:55:30

14 1 10 items per page

To run a cloud pulse test, choose a particular test from the dropdown and click **Run Test**. Once the test is in progress, Click **(Spin/refresh)** icon to fetch the latest result. This grid does not fetch the latest result automatically.

Run Cloud Sanity Test


You can use the cloud sanity tool to test the Cisco NFVI pod and cloud infrastructure (host connectivity, basic mraiadb, rabbit, ceph cluster check, and RAID disks).

Following are the test available to run from Unified Management.

- Control
- Compute
- Cephmon
- Cephosd
- Management
- All

Step 1 To run a Cloud sanity test choose a particular test from the dropdown.

Step 2 Click **Run Test** to proceed with the operation. Once the test is completed, click **See Details** for more



Run NFV Bench

You can **Run NFV Bench** for **B** and **C** series Pod, through Cisco VIM Unified Management. On a pod running with CVIM, choose a *NFVbench* link on the NAV-Menu.

You can run either fixed rate test or NDR/PDR test. As the settings and results for the test types differ, the options to run these tests are presented in two tabs, with its own settings and results. To run a particular test, you can either select a particular hypervisor from the available list or allow the system to select any hypervisor.

NDR/PDR Test

- Step 1** Log in to **CISCO VIM Unified Management**.
- Step 2** In the Navigation pane, click **Post-Install** > **Run NFV Bench**.
- Step 3** Click **NDR/PDR test** and complete the following fields

Name	Description
Select a hypervisor (Optional)	Select any hypervisor to run the NDR/PDR. By default, the option Use any hypervisor is selected.
Iteration Duration	Choose duration from 10 to 60 sec. Default is 20 sec.
Frame Size	Choose the correct frame size to run.
VXLAN	Enable VXLAN encapsulation, only if VXLAN is enabled.
Run NDR/PDR test	Click Run NDR/PDR test . After, completion it displays each type of test with its own settings and results.

Reconfiguring CIMC Password Through Unified Management

Update the `cimc_password` in the `CIMC-COMMON` section, or the individual `cimc_password` for each server and then run the update password option.

To update a password, you have to follow the password rules:

- Must contain at least one lower-case letter.
- Must contain at least one upper-case letter.
- Must contain at least one digit between 0 to 9.
- One of these special characters `!$#@%^_+*=&`
- Your password has to be 8 to 14 characters long.

Before you begin

You must have a C-series pod up and running with Cisco VIM to reconfigure CIMC password.



Note Reconfigure CIMC password section is disabled if the pod is in failed state as indicated by `ciscovim install-status`.

Step 1 Log in to **CISCO VIM Unified Management**.

Step 2 In the navigation pane, choose **Post-Install**

Step 3 Click **Reconfigure CIMC Password**.

Step 4 On the Reconfigure CIMC Password page of the Cisco VIM UM, complete the following fields:

Name	Description
<code>CIMC_COMMON</code> old Password	<code>CIMC_COMMON</code> old password field cannot be edited.
<code>CIMC-COMMON</code> new Password	Enter the <code>CIMC-COMMON</code> password. Password has to be alphanumeric according to the password rule.
Click Update	Old <code>CIMC-COMMON</code> password can be updated with new <code>CIMC-COMMON</code> password.



CHAPTER 9

Managing Pod Through Cisco VIM Unified Management

The following are the naming conventions used in the Cisco VIM UM

1. Super Administrator (UM Admin): User having access to UM Admin profile
2. POD Administrator: User having access to register a Pod in the system(Only UM can add new Pod Admin in the system)
3. Pod users (Normal users):
 - o All the users which are associated with the Pod. Full-pod-access: Role assigned to user which gives full access of a specific Pod(This has nothing to do with Pod Admins)

The following are the Key Points

- User who are UM admin or Pod admin but not associated with any Pod are not counted in UM admin dashboard user count section
- Only Pod Admins can register a new Pod
- Every Pod must a user with “Full-pod-Access” role.
- User cannot be revoked/delete if the users is the last user on the pod with “Full-Pod-Access” role.
- User cannot be delete if user is a Pod admin or UM admin.

The following topics tell you how to install and replace Cisco Virtual Infrastructure Manager (VIM) nodes using Cisco VIM Unified Management.

- [Monitoring Pod Status, on page 285](#)
- [Managing Hardware, on page 286](#)
- [Power Management, on page 294](#)
- [Managing Software, on page 298](#)
- [Pod User Administration, on page 315](#)

Monitoring Pod Status

The unified management application manages the pods and displays the pod management action status with a cloud icon.

The following table displays a summary of the pod operation, the corresponding cloud-icon color, and the pod status.

Table 17: Pod Operation Status

Pod Operation	UM Icon-Color	Pod Status
Active cloud with no failures	Green	Active
Cloud installation or pod management operation is in progress	Blue	In-progress
Software update (auto) rollback is failed	Red	Critical Warnings
Pending commit post software update	Amber	Warning
Reconfigure failed (for any operation)	Red	Critical Warning
Update, commit, or Rollback failed	Red	Critical Warning
Power management operation fails	Amber	Warning
Management not reachable	Red	Not Reachable

Managing Hardware

Management of your Cisco VIM pods includes adding, removing, or replacing the nodes.

In a pod, multiple nodes cannot be changed at the same time. For example, if you want to replace two control nodes, you must successfully complete the replacement of the first node before you begin to replace the second node. Same restriction applies for addition and removal of storage nodes. Only, in case of Compute Nodes you can add or remove multiple nodes together. However, there must always be one active compute node in the pod at any given point. VNF manager stays active and monitors the compute nodes so that moving the VNFs accordingly as compute node management happens.




Note When you change a control, storage, or compute node in a Cisco VIM pod using Unified Management, it automatically updates the server and role in the active blueprint, as a result, your OpenStack deployment changes. When a node is removed from Cisco VIM, sensitive data may remain on the drives of the server. Administrator advice you to use Linux tools to wipe the storage server before using the same server for another purpose. The drives that are used by other application server must be wiped out before adding to Cisco VIM.

Searching Compute and Storage Nodes

This functionality allows you to search the Compute and Storage nodes by server names only. The search result is generated or shows an empty grid if there are no results.


Figure 18: Search Storage Nodes



POD Management

Cisco VIM allows the admin to perform pod life-cycle management from a hardware and software perspective. Cisco VIM provides the ability to power on/off compute node, add, remove or replace nodes based on the respective roles when the nodes of a given pod corrupts at times.

Figure 19: POD Management



Pod Management page has two sections—

1. **Node Summary:** This section shows how many nodes are available and the detailed count of Control, Compute and Storage type.

2. IP Pool Summary: This section shows the Total Pool Summary and the current available pool count.

The operations performed on the running pod are:

Replace Control Nodes: Double fault scenario is not supported. Only the replacement of one controller at a time is supported.



Note If the TOR type is Cisco NCS 5500, an additional popup is displayed to enable the user to update splitter configuration before replacing the control node.

Add Computes/Storage Nodes: N-computes nodes can be replaced simultaneously; however at any given point, at least one compute node has to be active.



Note If the TOR type is Cisco NCS 5500, an option is available to update the splitter cable configuration.

Power On/ Off compute Nodes: You can Power On or Power Off compute node. At least one compute node must be powered on.

Remove Compute/Storage Nodes: You can add one node at a time, when Ceph is run as a distributed storage offering.



Note If TOR type is Cisco NCS 5500, an additional popup is displayed to enable the user to update the splitter cable configuration, before the removal of compute or storage node.

Add Pool: You can increase pool size at any time.

Managing Storage Nodes

Before you add or remove a storage node, review the following guidelines for Managing Storage Nodes.

- **Required Number of Storage Nodes:** A Cisco VIM pod must have a minimum of three and a maximum of 20 storage nodes. If your pod has only two storage nodes, you cannot delete a storage node until you add another storage node. If you have fewer than three storage nodes, you can add one node at a time until you get to 20 storage nodes.
- **Validation of Nodes:** When you add a storage node to a pod, Cisco VIM Unified Management validates that all the nodes in the pod meet the minimum requirements and are in active state. If you have a control or compute node in a faulty state, you must either correct, delete or replace that node before you can add a storage node.
- **Update Blueprint:** When you add or delete a storage node, Unified Management updates the blueprint for the Cisco VIM pod.
- **Storage Node Logs:** You can access the logs for each storage node from the link in the Log column on the **Storage Nodes** tab.

Adding Storage Node

Complete the following instructions to add a storage node:



Note You cannot add more than one storage node at a time.

Before you begin

- Remove the non-functional storage node from the pod. You can have maximum 20 storage nodes in a Cisco VIM pod.
- Ensure that the server for the new storage node is in powered state in OpenStack for C Series.

Step 1 In the navigation pane, choose **Post-Install > Pod Management > Storage**.

Step 2 Click on Add Storage node button on the Storage tab. A popup will open where you can provide information about the new Storage node.

Step 3 For C Series, add the following details:

- **Server Name:** Name for the Storage Server to be added.
- **Rack ID:** Enter the Rack ID. (Accepts String format).
- **CIMC IP:** Enter the CIMC IP.
- **CIMC User Name:** User name for the CIMC.
- **CIMC Password:** Enter the password for the CIMC
- **VIC Slot:** Enter the VIC Slot (Optional).
- **ToR switch info:** Mandatory if ToR is configured as True
 - **Management IPv6:** Enter IPv6 Address.

Step 4 For B Series, add the following details:

- **Server Name:** Name for the Storage Server to be added.
- **Rack ID:** Enter the Rack ID. (Accepts String format).
- **Rack Unit ID:** Enter the Rack Unit ID.
- **Management IPv6:** Enter IPv6 Address.

Note Cancel will discard the changes and popup will be closed

If all mandatory fields are filled in correctly then **Add Storage** button will be enabled.

Step 5 Click **Initiate Add Storage**. Add node initialized message will be displayed.

Step 6 To view logs, click **View logs** under Logs column.
The status of the POD will change to Active.

Step 7 Two kinds of failure may occur:

- **Add Node Pre-Failed:** When addition of node failed before the bare-metal stage (step 4), the Active Blueprint is modified but the Node is not yet added in the Cloud. If you press **X** Icon, then Unified Management will delete the node information from the Blueprint and the state would be restored.
- **Add Node Post-Failed:** When addition of node failed after the bare-metal stage (step 4), the Active Blueprint is modified and the node is registered in the cloud. If you press **X** Icon, then Unified Management will first delete the node from the Blueprint and then node removal from cloud would be initiated.

You can view the logs for this operation under **Logs** column.

Deleting Storage Node

You cannot delete more than one storage node at a time.

Step 1 In the Navigation pane, choose **Post-Install > POD Management > Storage**.

Step 2 Click **X** adjacent to the storage node you want to delete.

You can delete a storage node with Force option for hyper-converged POD. The Force option is useful when VM's are running on the node.

Step 3 **Node Removal Initiated successfully** message will be displayed.

To view logs, click **View logs** under logs column.

- If the Storage Node is deleted successfully, the storage node will be removed from the list under **Add/Remove storage Node**.
- In deletion failed, a new button **Clear Failed Nodes** will be displayed. Click **Clear Failed Nodes** to remove the node from cloud and Blueprint.

Managing Compute Nodes

Before you add or remove a compute node, review the following guidelines:

- **Required Number of Compute Nodes:** Cisco VIM pod must have a minimum of one compute node and a maximum of 61 compute nodes (with 3 ceph nodes). If your pod has only one compute node, you cannot delete that node until you add another compute node.
- **Update Blueprint:** When you add or remove a compute node, Unified Management updates the blueprint for the Cisco VIM pod.
- **Compute Node Logs:** You can access the Logs for each compute node from the link in the Log column on the Compute Nodes table.

Adding Compute Node

Add IP Pool

If all the existing pool size is already used, then you need to increase the pool size. On the Add compute or Add storage popup, Click **Expand Management IP pool** to add a new Pool.

Complete the instructions, to add a compute node:

Before you begin

Ensure that the server for the new compute node is in powered state in OpenStack. You can add more than one compute node at a time.

-
- Step 1** In the navigation pane, click **Post-Install > Pod Management > Compute**.
- Step 2** Click **Add Compute Node** on the Compute tab a popup opens . Add the required information in the popup. To add another node click **Add Another Node** if you planned to add another compute node OR hit Initiate Add Compute if you so not plan to add any more compute node. If you hit “Add Another Node” button, the existing form will be emptied. You will have to fill the information for the new compute node and then repeat step 1. You may use Previous and Next button to navigate among different added node information.
- Step 3** For C Series, add the following details:
- **Server Name:** Name for the Compute Server.
 - **Rack ID:** Enter the Rack ID. (Accepts String format).
 - **CIMC IP:** Enter the CIMC IP.
 - **CIMC User Name:** User name for the CIMC.
 - **CIMC Password:** Enter the password for the CIMC.
 - **VIC Slot:** Enter the VIC Slot (Optional).
 - **ToR switch info:** Mandatory if configured ToR is true.
 - **DP ToR switch info:** Enter input as string format.
 - **SRIVO ToR info :** Enter input as string format.
 - **Management IPv6 :** Enter IPv6 Address.
 - **Vtep IPs:** IP address from vxlan-tenant and vxlan-tenant.

Step 4 For B Series, add the following details:

- **Server Name:** Name for the Storage Server to be added.
- **Rack ID:** Enter the Rack ID. (Accepts String format).
- **Rack Unit ID:** Enter the Rack Unit ID.
- **Chassis ID:** Enter the Chassis ID. Range for Chassis ID is 1-24.
- **Blade ID:** Enter the Blade ID. Range for Blade ID is 1-8.
- **CIMC Password:** Enter the CIMC Password.
- **Management IPv6:** Enter IPv6 address.

If all mandatory fields are filled in correctly then click **Save**

Note Add Compute process can initiate multiple add of compute nodes. Fill in the mandatory fields to save new compute node or press cancel to exit message will be displayed.

Fields of Pod management will remain mandatory for user input based on setup-data.

Step 5 You may perform one among these steps mentioned below:

- Clicking **Cancel** displays the compute node information listed in the table and **Add Compute Node** button is enabled.
- If you feel you have filled in a wrong entry for the compute node information, click **Delete**. This will delete the entry from the table as this information is not added in the Blueprint.
- Click **Initiate Add Compute**, displays Add node initialized message.

Step 6 To view logs, click **View logs** under Logs column. The status of the POD will change to Active.

Step 7 Two kinds of failure may occur:

- **Add Node Pre-Failed:** When addition of node failed before the bare-metal stage (step 4) the Active Blueprint will be modified but the Node is not yet added in the Cloud. If you press **X** Icon, then Unified Management will delete the node information from the Blueprint and the state would be restored.
- **Add Node Post-Failed:** When addition of node failed after the bare-metal stage (step 4) the Active Blueprint will be modified and the node is registered in the cloud. If you press **X** Icon, then Unified Management will first delete the node from the Blueprint and then node removal from cloud would be initiated.

You can view the logs for this operation under **Logs** column.

Deleting Compute Node

Compute node is deleted due to a hardware failure. You can delete one compute node at a time.



Note If your pod has only one compute node, you cannot delete that node until you add another compute node.

-
- Step 1** In the navigation pane, choose **Post-Install > POD Management > Compute**.
- Step 2** Click **X** for the compute node to be deleted. To remove multiple compute nodes, choose the target compute nodes which is on the extreme left column, then click **Trash** to remove multiple computes.
- You can delete a compute node with Force option which is useful when VM's are running on the node.
- "Node removal initiated successfully" message is displayed.
- Step 3** To view the Logs, click **View logs** under Logs column.
- If compute nodes are deleted successfully, you cannot view the compute node in the list under **Add or Remove Compute Node**.
 - If Compute Note is deleted, a new button **Clear Failed Nodes** is displayed.
- Step 4** Click **Clear Failed Nodes** to remove the node form Cloud and Blueprint.
-

Managing Control Nodes

Before you replace a control node, review the following guidelines:

- **Required Number of Control Nodes:** A Cisco VIM pod must have three control nodes and you can only replace one node at a time.
- **Validation of Nodes:** When you replace a control node, Cisco VIM Unified Management validates if all the other nodes in the pod meet the minimum requirements and are in active state. If you have a storage or a compute node in a faulty state, you must correct the faulty state or delete or replace that node before you can replace the control node.
- **Update Blueprint:** When you replace a control node, Unified Management updates the Active blueprint for the Cisco VIM pod.
- **Control Node Logs:** You can access the logs for each control node from the link in the **Logs** column of Control Nodes table.

Replacing Control Node

You can replace only one control node at a time.

-
- Step 1** In the navigation pane, click **Post-Install > Pod Management > Control**.
- Step 2** Click (Spin) icon. A confirmation pop-up appears, Click **Proceed** to continue.
- You can replace a control node with Force option for Micropod. The Force option is useful when VM's are running on the node.
- Step 3** If you want to edit a specific control node before replace, click **Edit** to update the changes.
- Step 4** On success, **Replace Node Initiated** successfully message is displayed.
- Step 5** You can view the logs in the **Logs** column on the Control Nodes table.
-

What to do next

If the replacement of the control node fails, do the following:

- Click the link in the Logs column.
- Check the logs to determine the cause of the failure.
- Correct the issue and attempt to replace the control node again.



Note For replace controller, you can change only a subset of the server information. For C-series, you can change the server information such as CIMC IP, CIMC Username, CIMC password, rack_id, and tor_info. For B-series, you can change the rack_id, chassis_id, and blade_id, but not the server hostname and management IP during the operation of replace controller.

Power Management

Compute node can be powered on or powered off from the Compute Tab in Pod Management section. There is a power button associated with each compute with information provided as tooltip when you hover on that icon.

Following are the steps to power on/off multiple compute node:

1. Click **Power** button located to the left of delete button.
2. Choose the compute nodes by selecting the check box, the corresponding power button gets enabled.

Power On a Compute Node

Following are the steps to power on the compute node:

1. Click the **Compute** tab.
2. In the Pod Management area, check the check box corresponding to the Compute node that you want to power on.



Note The **Power** button of a Compute node is enabled only after you select the Compute node.

Figure 20: Powering On a Compute Node

Server...	Rack Id	CIMC L...	CIMC ...	CIMC ...	VIC Sl...	Manag...	Manag...	Tor Info	DP Tor...	SRIOV...	VM_H...	Status	Actions	Logs
comput...	RackE	172.31...		*****		10.1.1.19		{^ po^:5...				Active		View Logs
comput...	RackD	10.23.2...	admin	*****		10.1.1.18		{^ po^:3...				Active		View Logs
comput...	RackF	172.31...		*****		10.1.1.17		{^ po^:2...				InActive		View Logs

- Under the Actions column, click the **Power** button of the Compute node. It may take a few minutes for the Compute node to power on. The tooltip of the power button displays the status of the Compute node. Once the compute node is powered on, the Power button stops blinking and its color changes to green.

Figure 21: Power On Operation

Started PowerOn operation

Total Control Compute Storage

IP Pool Summary

11 2

Total Available

Server...	Rack Id	CIMC L...	CIMC ...	CIMC ...	VIC Sl...	Manag...	Manag...	Tor Info	DP Tor...	SRIOV...	VM_H...	Status	Actions	Logs
comput...	RackE	172.31...		*****		10.1.1.19		{^ po^:5...				Active		View Logs
comput...	RackD	10.23.2...	admin	*****		10.1.1.18		{^ po^:3...				Active		View Logs
comput...	RackF	172.31...		*****		10.1.1.17		{^ po^:2...				InActive		View Logs

You can add a Compute node only once a power on task is complete.


Powering Off Compute Node




Note You cannot power off all the Compute nodes. There must be at least one Compute node that is in the On state.

Follow these steps to power off a Compute node:

- Click the **Compute** tab.
- In the Pod Management area, under the Actions column, click the **Power** button of the Compute node that you want to power off.



3. Click **Yes** in the confirmation dialog box.



It may take a few minutes for the Compute node to power off. The tooltip of the power button displays the status of the Compute node. Once the compute node is powered off, the Power button stops blinking and its color changes to grey.



Note If there is only one compute node in the grid, and you try to power off it, a message *Last compute node can't be powered off* is displayed. Also, when you power off the last available compute node in the list of nodes, then the message *At least one compute node should be powered on* is displayed.

Multiple compute power/ delete/ reboot operation

You can perform power, delete, and reboot operation on multiple compute nodes using the global buttons located at the top of grid. To enable this operation, select at least one compute node.

Rebooting Compute Node


To reboot the compute node, follow the below steps:

1. Click on **Compute** tab.
2. In the **Pod Management** pane, under the **Actions** column, click **Reboot** of the compute node that you want to reboot.
3. Click **Yes** in the confirmation dialog box, to perform reboot. You can reboot a compute node with Force option which is useful when VM's are running on the node.

Multiple compute power/ delete/ reboot operation

You can perform power, delete, and reboot operation on multiple compute nodes using the global buttons located at the top of grid. To enable this operation, select at least one compute node.


Figure 22: Pod Management



Searching Compute and Storage Nodes

This functionality allows you to search the Compute and Storage nodes by server names only. The search result is generated or shows an empty grid if there are no results.

Figure 23: Search Storage Nodes



Managing Software

Software management of your Cisco VIM pods includes software update, reconfigure of openstack services and password, etc.

VIM Software Update

As part of the lifecycle management of the cloud, VIM has the ability to bring in patches (bug fixes related to code, security, etc.), thereby providing cloud management facility from software point of view. Software

update of the cloud is achieved by uploading a valid tar file, following initiation of a System Update form the Unified Management as follows:

-
- Step 1** In the Navigation pane, click **Post-Install > System Update**.
- Step 2** Click **Browse** and select the valid tar file.
- Step 3** Click **Open**.
- Step 4** Click **Upload and Update**.
Update started Successfully message will be displayed.
- Step 5** Update status will be shown as **ToUpdate**.
Click the hyperlink to view the reconfigure logs for install logs.
Reconfigure status will be available on the page or the dashboard under **POD Operation** details.
-

What to do next

System Update has been initiated message will be displayed. Logs front-ended by hyperlink will be in the section below in-front of **Update Logs** which shows the progress of the update. During the software update, all other pod management activities will be disabled. Post-update, normal cloud management will commence. Once update has completed you will see the status of update in the box below.

If log update fails, **Auto-RollBack** will be initiated automatically.

If log update is successful, you will have two options to be performed:

1. **Commit**—To proceed with the update.
2. **RollBack**—To cancel the update.

If Auto-rollback fails during software update fails through Unified Management UI, it is advised that the administrator contact Cisco TAC for help. Do not re-try the update or delete the new or the old installer workspace.

If the update is successful and reboot is required for at least one compute node:

- Only commit or rollback is allowed.
- Following operations are not permitted:
 - Reconfigure
 - System update
 - Pod management




Note You can reboot the node, only after the commit or rollback operation.

Reconfigure Openstack Passwords

There are two options to regenerate the passwords:

- **Regenerate all passwords:** Click **Regenerate all passwords** checkbox and click **Set Password**. This will automatically regenerate all passwords in alphanumeric format.
- **Regenerate single or more password:** This will set a specific password by doing an inline edit for any service like Horizon's ADMIN_USER_PASSWORD. Double click on the field under Password and enter the password to enable **Set Password** button.



During the reconfiguration of password, all other pod management activities will be disabled. Post-update, normal cloud management will commence. If the reconfigure of the password fails, all subsequent pod management operations will be blocked. It is advised to contact Cisco TAC to resolve the situation through CLI.

Reconfigure OpenStack Services, TLS Certificates, and ELK Configurations

Cisco VIM supports the reconfiguration of OpenStack log level services, TLS certificates, and ELK configuration. Following are the steps to reconfigure the OpenStack and other services:

-
- Step 1** In the navigation pane, click **Post-Install > Reconfigure Openstack Config**.
 - Step 2** Click the specific item that you want to change and update. For example: to update the TLS certificate click the path to the certificate location.
 - Step 3** Enter **Set Config** to commence the process.
-

What to do next

During the reconfiguration process, all other pod management activities are disabled. Post-update, normal cloud management commences. If reconfigure of OpenStack Services fails, all subsequent pod management operations are blocked. Contact, Cisco TAC to resolve the situation through CLI.

Reconfiguring CIMC Password through Unified Management

Cisco VIM allows you to Update the `cimc_password` in the CIMC-COMMON section, and/or the individual `cimc_password` for each server and then run the update password option.

You need to match the following Password rule to update the Password:

- Must contain at least one lower case letter.
- Must contain at least one upper case letter.
- Must contain at least one digit between 0 to 9.
- One of these special characters `!$#@%^-_=*&`
- Your password has to be 8 to 14 characters long.

Before you begin

You must have a C-series pod up and running with Cisco VIM to reconfigure CIMC password.



Note Reconfigure CIMC password section will be disabled if the pod is in failed state as indicated by `ciscovim install-status`.

-
- Step 1** Log-in to **CISCO VIM Unified Management**.
 - Step 2** In the navigation pane, select **Post-Install**.
 - Step 3** Click **Reconfigure CIMC Password**.
 - Step 4** You can reconfigure the CIMC Password at global level by adding new CIMC_COMMON Password or to reconfigure CIMC Password for individual servers double click the server password you want to edit.
 - Step 5** Click **Reconfigure** to initiate reconfigure process.
-

Reconfigure Optional Services

Cisco VIM offers optional services such as heat, migration to Keystone v3, NFVBench, NFMON, etc, that can be enabled post-pod deployment. These services can be enabled in one-shot or selectively.

Listed below are the steps to enable optional services:

-
- Step 1** In the Navigation pane, click **Post-Install > Reconfigure Optional Services**.
 - Step 2** Choose the right services and update the fields with the right values.

Step 3 Click **Offline validation**. Once offline validation is successful.

Step 4 Click **Reconfigure** to commence the process.

During the reconfiguration process, all other pod management activities will be disabled. Post-update, normal cloud management will commence.

If reconfigured OpenStack Services fail, all subsequent pod management operations are blocked. Contact Cisco TAC to resolve the situation through CLI.

Note All reconfigure operation features contain repeated re-deployment option set to true or false.

- Repeated re-deployment true - Feature can be re-deployed again.
- Repeated re-deployment false- Deployment of feature allowed only once.

Deployment Status :

Optional Features	Repeated re-deployment Option
APICINFO	True
EXTERNAL_LB_VIP_FQDN	False
EXTERNAL_LB_VIP_TLS	False
INSTALL_MODE	True
HTTP_PROXY & HTTPS_PROXY	True
LDAP	True
NETWORKING	True
NFVBENCH	False
NFVIMON	False
PODNAME	False
PROVIDER_VLAN_RANGES	True
SWIFTSTACK	True
SYSLOG_EXPORT_SETTINGS	False
TENANT_VLAN_RANGES	True
TORSWITCHINFO	False
VIM_ADMINIS	True
VMTP	False
VTS_PARAMETERS	False

Optional Features	Repeated re-deployment Option
AUTOBACKUP	True
Heat	False
Keystone v3	False
Cobbler	True
ES Remote Backup	True
CVIMMON	True
NETAPP_SUPPORT	True
Enable Read-only OpenStack Admins	True

Reconfiguring Optional Features Through Unified Management

- Step 1** Log into Cisco VIM UM.
- Step 2** In the **Navigation** pane, expand the **Post-Install Section**.
- Step 3** Click **Reconfiguring Optional Feature through UM**.
- Step 4** On the **Reconfiguring Optional Feature through UM** page of the Cisco VIM UM, enter the data for the following fields:

Name	Description
Heat check box	<ul style="list-style-type: none"> • Enable Heat. • Click Offline Validation. • When Offline Validation is successful, click Reconfigure to commence the process.
Enable Read-only OpenStack Admins checkbox	<ul style="list-style-type: none"> • Check/uncheck Enable Read-only OpenStack Admins • Click Offline Validation <p>When Offline Validation is successful, click Reconfigure to commence the process.</p>

Name	Description
Keystone v3 check box	<ul style="list-style-type: none"> • Enable Keystone v3. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
ENABLE_ESC_PRIV	<ul style="list-style-type: none"> • Enable ENABLE_ESC_PRIV . • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
Autobackup check box	<ul style="list-style-type: none"> • Enable/Disable Autobackup. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
External LB VIP TLS check box	<ul style="list-style-type: none"> • Enable External LB VIP TLS. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
External LB VIP FQDN check box	<ul style="list-style-type: none"> • Enter Input as a string. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
Pod Name	<ul style="list-style-type: none"> • Enter Input as a string. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.
Tenant Vlan Ranges	<ul style="list-style-type: none"> • Augment tenant vlan ranges input. For Example: 3310:3315. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process.

Name	Description												
<p>Provider VLAN Ranges</p>	<ul style="list-style-type: none"> • Enter input to tenant vlan ranges. For Example: 3310:3315. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 												
<p>Install Mode</p>	<ul style="list-style-type: none"> • Select Connected or Disconnected, any one form the drop-down list. • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 												
<p>Registry Setup Settings checkbox</p>	<p>For Registry Setup:</p> <ul style="list-style-type: none"> • Enter the Registry User Name. It is a mandatory field • Enter the Registry Password. The minimum length of the password is three. • Enter the Registry Email. It is a mandatory field. • Enter the Registry Name. For example, Registry FQDN name. It is a mandatory field, only when Cisco VIM Software Hub is enabled. • Click Offline Validation • If offline validation is successful, click Reconfigure to commence the process. 												
<p>Syslog Export Settings</p>	<p>Following are the options for Syslog Settings:</p> <table border="1" data-bbox="901 1367 1521 1732"> <tbody> <tr> <td data-bbox="901 1367 1214 1421">Remote Host</td> <td data-bbox="1218 1367 1521 1421">Enter Syslog IP Address.</td> </tr> <tr> <td data-bbox="901 1425 1214 1480">Facility</td> <td data-bbox="1218 1425 1521 1480">Defaults to local5</td> </tr> <tr> <td data-bbox="901 1484 1214 1539">Severity</td> <td data-bbox="1218 1484 1521 1539">Defaults to debug</td> </tr> <tr> <td data-bbox="901 1543 1214 1598">Clients</td> <td data-bbox="1218 1543 1521 1598">Defaults to ELK</td> </tr> <tr> <td data-bbox="901 1602 1214 1686">Port</td> <td data-bbox="1218 1602 1521 1686">Defaults to 514 but is modified by the User.</td> </tr> <tr> <td data-bbox="901 1690 1214 1732">Protocol</td> <td data-bbox="1218 1690 1521 1732">Supports only UDP</td> </tr> </tbody> </table> <p>Click Offline Validation .</p> <ul style="list-style-type: none"> • When Offline Validation is successful, click Reconfigure to commence the process. 	Remote Host	Enter Syslog IP Address.	Facility	Defaults to local5	Severity	Defaults to debug	Clients	Defaults to ELK	Port	Defaults to 514 but is modified by the User.	Protocol	Supports only UDP
Remote Host	Enter Syslog IP Address.												
Facility	Defaults to local5												
Severity	Defaults to debug												
Clients	Defaults to ELK												
Port	Defaults to 514 but is modified by the User.												
Protocol	Supports only UDP												

Name	Description																										
Configure ToR checkbox	True or False . Default is false.																										
ToR Switch Information	Click + to add information for ToR Switch.																										
	<table border="1"> <thead> <tr> <th data-bbox="862 399 1175 445">Name</th> <th data-bbox="1175 399 1481 445">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="862 445 1175 506">Name</td> <td data-bbox="1175 445 1481 506">ToR switch name.</td> </tr> <tr> <td data-bbox="862 506 1175 567">Username</td> <td data-bbox="1175 506 1481 567">ToR switch username.</td> </tr> <tr> <td data-bbox="862 567 1175 627">Password</td> <td data-bbox="1175 567 1481 627">ToR switch Password.</td> </tr> <tr> <td data-bbox="862 627 1175 688">SSH IP</td> <td data-bbox="1175 627 1481 688">ToR switch SSH IP Address.</td> </tr> <tr> <td data-bbox="862 688 1175 770">SSN Num</td> <td data-bbox="1175 688 1481 770">ToR switch ssn num. output of show license host-id.</td> </tr> <tr> <td data-bbox="862 770 1175 890">VPC Peer Keepalive</td> <td data-bbox="1175 770 1481 890">Peer Management IP. You need not define if there is no peer.</td> </tr> <tr> <td data-bbox="862 890 1175 980">VPC Domain</td> <td data-bbox="1175 890 1481 980">Need not define if there is no peer.</td> </tr> <tr> <td data-bbox="862 980 1175 1041">VPC Peer port</td> <td data-bbox="1175 980 1481 1041">Interface for vpc peer ports.</td> </tr> <tr> <td data-bbox="862 1041 1175 1131">VPC Peer VLAN Info</td> <td data-bbox="1175 1041 1481 1131">vlan ids for vpc peer ports (optional).</td> </tr> <tr> <td data-bbox="862 1131 1175 1222">BR Management Port Info</td> <td data-bbox="1175 1131 1481 1222">Management interface of the build node.</td> </tr> <tr> <td data-bbox="862 1222 1175 1341">BR Management PO Info</td> <td data-bbox="1175 1222 1481 1341">Port channel number for the management interface of the build node.</td> </tr> <tr> <td colspan="2" data-bbox="854 1341 1489 1543"> Click Save <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. </td> </tr> </tbody> </table>	Name	Description	Name	ToR switch name.	Username	ToR switch username.	Password	ToR switch Password.	SSH IP	ToR switch SSH IP Address.	SSN Num	ToR switch ssn num. output of show license host-id.	VPC Peer Keepalive	Peer Management IP. You need not define if there is no peer.	VPC Domain	Need not define if there is no peer.	VPC Peer port	Interface for vpc peer ports.	VPC Peer VLAN Info	vlan ids for vpc peer ports (optional).	BR Management Port Info	Management interface of the build node.	BR Management PO Info	Port channel number for the management interface of the build node.	Click Save <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 	
	Name	Description																									
	Name	ToR switch name.																									
	Username	ToR switch username.																									
	Password	ToR switch Password.																									
	SSH IP	ToR switch SSH IP Address.																									
	SSN Num	ToR switch ssn num. output of show license host-id.																									
	VPC Peer Keepalive	Peer Management IP. You need not define if there is no peer.																									
	VPC Domain	Need not define if there is no peer.																									
	VPC Peer port	Interface for vpc peer ports.																									
	VPC Peer VLAN Info	vlan ids for vpc peer ports (optional).																									
	BR Management Port Info	Management interface of the build node.																									
BR Management PO Info	Port channel number for the management interface of the build node.																										
Click Save <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 																											

Note When setup data is ACI VLAN with TOR then reconfigure options are:

<p>TORSwitch Information mandatory table if you want to enter ToR information</p>	<p>Click + to add information for ToR Switch.</p> <table border="1" data-bbox="901 283 1523 592"> <thead> <tr> <th data-bbox="901 283 1214 338">Name</th> <th data-bbox="1219 283 1523 338">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="901 344 1214 396">Host Name</td> <td data-bbox="1219 344 1523 396">ToR switch name.</td> </tr> <tr> <td data-bbox="901 403 1214 455">VPC Peer Keepalive</td> <td data-bbox="1219 403 1523 455">Peer Management IP.</td> </tr> <tr> <td data-bbox="901 462 1214 514">VPC Domain</td> <td data-bbox="1219 462 1523 514">Do not define if there is no</td> </tr> <tr> <td data-bbox="901 520 1214 592">Node ID</td> <td data-bbox="1219 520 1523 592">Integer, unique across all switches</td> </tr> </tbody> </table> <p>Click Save</p> <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 	Name	Description	Host Name	ToR switch name.	VPC Peer Keepalive	Peer Management IP.	VPC Domain	Do not define if there is no	Node ID	Integer, unique across all switches
Name	Description										
Host Name	ToR switch name.										
VPC Peer Keepalive	Peer Management IP.										
VPC Domain	Do not define if there is no										
Node ID	Integer, unique across all switches										
<p>NFVBench</p>	<p>Enable check box which by default is false.</p> <p>Add ToR information connected to switch:</p> <ul style="list-style-type: none"> • Select a ToR Switch and enter the Switch name. • Enter the port number. For example: eth1/5 • NIC Ports: INT1 and INT2 optional input, enter the two port numbers of the 4-port 10G Intel NIC at the management node used for NFVBench. <p>For mechanism driver VPP, there are two optional fields in NFVBENCH if network option is available:</p> <ul style="list-style-type: none"> • VTEP IPs: Mandatory for NFVBench with VXLAN. It must be comma separated IP pair in vxlan-tenant network, but not in the tenant pool. • VNIs: Mandatory for NFVBench with VXLAN, and must be comma separated vnid_id pairs. <p>For mechanism driver VTS:</p> <p>VTEP IPs: Mandatory for VTS/VXLAN only. It must be comma separated IP pair belonging to tenant network segment, but not in the tenant network pool.</p> <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. <p>Note If ToR is already present in setup-data or already deployed, Tor info need not be added. By default ToR information switch name is mapped in NFV bench.</p>										

<p>Swiftstack</p> <p>SwiftStack is only supported with Keystone v2. If you select Keystone v3, swiftstack will not be available for configuration.</p>	Cluster End Point	IP address of PAC (proxy-account-container) endpoint.
	Admin User	Admin user for swift to authenticate in keystone.
	Admin Tenant	The service tenant corresponding to the Account-Container used by Swiftstack.
	Reseller Prefix	Reseller_prefix as configured for Keystone Auth,AuthToken support in Swiftstack E.g KEY_
	Admin Password	swiftstack_admin_password
	Protocol drop-down list	http or https
	<ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 	

LDAP with Keystone v3	Domain Name field	Enter the Domain name.
	Object Class for Users field	Enter a string as input.
	Object Class for Groups	Enter a string.
	Domain Name Tree for Users	Enter a string.
	Domain Name Tree for Groups field	Enter a string.
	Suffix for Domain Name field	Enter a string.
	URL field	Enter a URL with port number.
	Domain Name for Bind User field	Enter a string.
	Password field	Enter Password as string format.
	User Filter	Enter filter name as string.
	User ID Attribute	Enter a string.
	User Name Attribute	Enter a string.
	User Mail Attribute	Enter a string.
	Group Name Attribute	Enter a string.
<ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 		

<p>NFVI Monitoring</p>	<p>Followings are the field values for NFVI monitoring:</p> <table border="1"> <tr> <td data-bbox="862 281 1175 338">Master Admin IP field.</td> <td data-bbox="1175 281 1484 338">Enter Input as IP format.</td> </tr> <tr> <td data-bbox="862 338 1175 428">Collector Management IP field</td> <td data-bbox="1175 338 1484 428">Enter Input as IP format.</td> </tr> <tr> <td colspan="2" data-bbox="862 428 1484 478">Collector VM1 info</td> </tr> <tr> <td data-bbox="862 478 1175 535">Host Name field</td> <td data-bbox="1175 478 1484 535">Enter Host Name as a string.</td> </tr> <tr> <td data-bbox="862 535 1175 592">CCUSER password field</td> <td data-bbox="1175 535 1484 592">Enter Password.</td> </tr> <tr> <td data-bbox="862 592 1175 648">Password field</td> <td data-bbox="1175 592 1484 648">Enter password.</td> </tr> <tr> <td data-bbox="862 648 1175 705">Admin IP field</td> <td data-bbox="1175 648 1484 705">Enter Input as IP format.</td> </tr> <tr> <td data-bbox="862 705 1175 762">Management IP field</td> <td data-bbox="1175 705 1484 762">Enter Input as IP format.</td> </tr> <tr> <td colspan="2" data-bbox="862 762 1484 816">Collector VM2 info</td> </tr> <tr> <td data-bbox="862 816 1175 873">Host Namefield</td> <td data-bbox="1175 816 1484 873">Enter a string.</td> </tr> <tr> <td data-bbox="862 873 1175 930">CCUSER field</td> <td data-bbox="1175 873 1484 930">Enter Password.</td> </tr> <tr> <td data-bbox="862 930 1175 987">Management IP field</td> <td data-bbox="1175 930 1484 987">Enter Input as IP format.</td> </tr> <tr> <td colspan="2" data-bbox="862 987 1484 1043">Dispatcher</td> </tr> <tr> <td data-bbox="862 1043 1175 1134">Rabbit MQ Username Field</td> <td data-bbox="1175 1043 1484 1134">Enter a string.</td> </tr> </table> <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 	Master Admin IP field.	Enter Input as IP format.	Collector Management IP field	Enter Input as IP format.	Collector VM1 info		Host Name field	Enter Host Name as a string.	CCUSER password field	Enter Password.	Password field	Enter password.	Admin IP field	Enter Input as IP format.	Management IP field	Enter Input as IP format.	Collector VM2 info		Host Name field	Enter a string.	CCUSER field	Enter Password.	Management IP field	Enter Input as IP format.	Dispatcher		Rabbit MQ Username Field	Enter a string.
Master Admin IP field.	Enter Input as IP format.																												
Collector Management IP field	Enter Input as IP format.																												
Collector VM1 info																													
Host Name field	Enter Host Name as a string.																												
CCUSER password field	Enter Password.																												
Password field	Enter password.																												
Admin IP field	Enter Input as IP format.																												
Management IP field	Enter Input as IP format.																												
Collector VM2 info																													
Host Name field	Enter a string.																												
CCUSER field	Enter Password.																												
Management IP field	Enter Input as IP format.																												
Dispatcher																													
Rabbit MQ Username Field	Enter a string.																												
<p>VTS Parameter</p>	<p>Following are the fields to reconfigure for VTS parameters</p> <table border="1"> <tr> <td data-bbox="862 1360 1175 1417">VTC SSH Username field.</td> <td data-bbox="1175 1360 1484 1417">Enter the string.</td> </tr> <tr> <td data-bbox="862 1417 1175 1474">VTC SSH Username field.</td> <td data-bbox="1175 1417 1484 1474">Enter the password.</td> </tr> </table> <ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 	VTC SSH Username field.	Enter the string.	VTC SSH Username field.	Enter the password.																								
VTC SSH Username field.	Enter the string.																												
VTC SSH Username field.	Enter the password.																												

VMTP	<p>Check one of the check boxes to specify a VMTP network:</p> <ul style="list-style-type: none"> • Provider Network • External Network <p>For the Provider Network complete the following:</p>	
	Network Name field.	Enter the name for the external network.
	IP Start field.	Enter the starting floating IPv4 address.
	IP End field.	Enter the ending floating IPv4 address.
	Gateway field	Enter the IPv4 address for the Gateway.
	DNS Server field.	Enter the DNS server IPv4 address.
	Segmentation ID field.	Enter the segmentation ID.
	Subnet	Enter the Subnet for Provider Network.
	<p>For External Network fill in the following details:</p>	
	Network Name field.	Enter the name for the external network.
	Network IP Start field.	Enter the starting floating IPv4 address.
	Network IP End field.	Enter the ending floating IPv4 address.
	Network Gateway field	Enter the IPv4 address for the Gateway.
	DNS Server field.	Enter the DNS server IPv4 address.
	Subnet	Enter the Subnet for External Network.
<ul style="list-style-type: none"> • Click Offline Validation . • When Offline Validation is successful, click Reconfigure to commence the process. 		

<p>Networking</p> <p>In Reconfigure optional services networking, you can reconfigure IP tables, or add http_proxy/https_proxy.</p>	<p>To reconfigure networking, update the relevant information:</p>	
	<p>IP Tables</p>	<p>Click Add(+) to add a table. Enter input as subnet format. E.g. 12.1.0.1/2</p>
	<p>http_proxy_server</p>	<p>Enter HTTP_PROXY_SERVER E.g. <a.b.c.d:port></p>
	<p>https_proxy_server</p>	<p>Enter HTTP_PROXY_SERVER E.g. <a.b.c.d:port></p>
	<p>Head-end replication</p>	<p>Add VTEP IP address and comma separated VNI IDs. Multiple entries are allowed. You can change VTEP IP for individual compute/control servers.</p> <p>Note Whenever HER is removed from both vxlan-tenant and vxlan-tenant, all the vtep ips associated with the computes are removed.</p>
<p>Layer 3 BGP Adjacency</p>	<p>Applicable to control servers only when VXLAN is enabled in NETWORK OPTIONS. IPs are picked up from management subnet, but not from IP pool. You can change the existing IP values if required.</p>	
<ul style="list-style-type: none"> • Click Save. • Click Offline Validation. • When Offline Validation is successful, click Reconfigure to commence the process. 		

<p>APICINFO</p> <p>Note Reconfigure optional services only APIC hosts can be reconfigure.</p>	<p>To reconfigure APICINFO, follow the process:</p> <ul style="list-style-type: none"> • Enter input for APIC hosts format. <ip1 host1>:[port] or eg.12.1.0.12 • Click Save. • Click Offline Validation. • When Offline Validation is successful, click Reconfigure to commence the process. <p>Note APIC hosts can be reconfigure minimum 1 host and max 3 but not 2 hosts.</p>
<p>Vim_admins</p>	<p>To reconfigure vim_admins, follow the process:</p> <ul style="list-style-type: none"> • To add a new root user, Click + and add the Username and admin hash password (Starting with \$6). At least, one Vim Admin must be configured, when Permit root login is false. • To remove the existing user, Click -. • When Offline Validation is successful, click Reconfigure to commence the process.
<p>Cobbler</p>	<p>To reconfigure Cobbler, follow the process:</p> <ul style="list-style-type: none"> • Generate the admin password hash by executing the below command: <pre>python -c 'import crypt; print crypt.crypt("<plaintext_strong_password>")' on the management node.</pre> <ul style="list-style-type: none"> • Validate that the admin_password_hash starts with '\$6' • Enter Admin Password Hash. • Click Offline Validation. • When Offline Validation is successful, click Reconfigure to commence the process.

ES Remote Backup	<p>To reconfigure Elastic Search Remote Backup:</p> <p>Service field displays NFS by default, if the remote NFS server is used.</p> <ul style="list-style-type: none"> • Enter the Remote Host, which is IP of the NFS server. • Enter the Remote Path. . It is the path of the backup location in the remote server. • Click Offline Validation. • If Offline Validation is successful, click Reconfigure to commence the process.
CVIMMON	<p>To reconfigure CVIMMON, enter the following details:</p> <ul style="list-style-type: none"> • Enter the Low Frequency, such that it is higher than medium frequency. Minimum value is 1 minute. By default, it is set to 1 minute. • Enter the Medium Frequency such that it is more than high frequency. Minimum value is 30 seconds. By default, it is set to 30 seconds. • Enter the High Frequency such that the minimum value is 10 seconds. By default, it is set to 10 seconds. • Click Offline Validation. • If Offline Validation is successful, click Reconfigure to commence the process.
NETAPP_SUPPORT	<p>To reconfigure NETAPP_SUPPORT, enter the following details:</p> <ul style="list-style-type: none"> • Select the Server Port. It is the port of NetApp management or API server. Select 80 for HTTP and 443 for HTTPS. • Select the Transport Type of the NetApp management or API server. It can be HTTP or HTTPS. • Select the NetApp Cert Path. It is the root ca path for NetApp cluster, only if protocol is HTTPS. • Click Offline Validation. • If Offline Validation is successful, click Reconfigure to commence the process.

View Topology

You can view the graphical representation of the control, compute, and storage node that is associated with the various network segments.

Server Name	DMC IP	RACK ID	Model	Serial Number	Number of Storage	Number of Cores	NIC Type	Total Memory
starm-server-02		rack1	UCSB-E200-M0	FDH163L789C	2	16		65536
starm-server-03		rack4	UCSB-E200-M0	FDH161739D6	2	12		52768
starm-server-04		rack2	UCSB-E200-M4	FDH163473UJ	3	24		131072

You can click Control, Compute, or Storage from the topology, to view the details of respective node.


Pod User Administration

Cisco VIM UM offers Users (Pod Admins or Pod Users) to manage Users and roles that are associated with them.

Managing Roles

User can create multiple Roles and assign them to other pod users. System has a default role that is named as Full-Pod-Access which is assigned to the person who registers the Pod.

Manage Roles



Step 1 Click **Login as POD User**.

Step 2 Navigate to **Pod User Administration** and click **Manage Roles**. By default you see full-pod-access role in the table.

Step 3 Click **Add New Role** to create a new role.

Step 4 Complete the following fields in the **Add Roles** page in Cisco VIM UM:


Field Name	Field Description
Role	Enter the name of the role.
Description	Enter the description of the role.
Permission	Check the Permission check box to select the permission.
Click Save .	Once the Blueprint is in Active state all the permissions are same for C-series and B-series Pods other than Reconfigure CIMC Password which is missing for B-series Pod.

Note Permissions are divided in the granular level where viewing Dashboard is the default role that is implicitly added while creating a role.

Note Permissions are divided in the granular level where viewing **Dashboard** is the default role that is implicitly added while creating a role.

Managing Users

This section allows you to add the users. It shows all the users associated with the Pod. You can check the online status of all the user. Click **Refresh** on upper right corner to check the status.



To add a new user:

- Step 1** Click **Login as POD User**.
- Step 2** Navigate to **POD User Administration** and click **Manage Users**.
- Step 3** Click **Add Users** to add a new user.
- Step 4** Complete the following fields in the **Add Users** pane of the Cisco VIM Unified Management:

Field Name	Field Description
User auth	Select the User auth for the new user. This option is enabled only if LDAP mode is True.
Registration Type	Registration type can be User/Group only when User Auth is LDAP. Following fields are available when the Registration Type is 'Group': <ul style="list-style-type: none"> • Group Dn – Enter the distinguished name of the LDAP group. • Group Name – Enter the name of the LDAP group
Email ID	Enter the Email ID of the user or the LDAP user id if LDAP user attribute is set to uid.
User Name	Enter the User Name if the User is new. If the User is already registered to the Unified Management the User-Name gets auto-populated.
Role	Select the Role from the drop-down list.

- Step 5** Click **Save** Once the Blueprint is in Active state all the permissions are same for C-series and B-series Pods other than Reconfigure CIMC Password which is missing for B-series Pod.

Revoke Users

User with Full-Pod-Access or Manage Users permission can revoke other users from the specific Pod.

To revoke users:

- Step 1** Click **Undo** icon. A confirmation pop up will appear.

Step 2 Click **Proceed** to continue.

Note Self revoke is not permitted. After revoking the another user, if the user is not associated with any other pod then the revoked user will be auto deleted from the system.

Edit Users

User with Full-Pod-Access or Manage Users permission can edit other user's permission for that specific Pod.
To edit user's permission


Step 1 Click **Edit** icon.

Step 2 Update the permission.

Step 3 Click **Save**. The Grid will get refreshed automatically.

Managing Root CA Certificate

You can update the CA Certificate during the registration of the POD. Once, logged in as POD User and if you have the permission to update the certificate you can view under POD User Administration>> Manage Root CA Certificate.



The screenshot shows the 'Manage Root CA Certificate' page in the Cisco VIM Unified Management interface. The page title is 'Manage Root CA Certificate'. Below the title, there is a section titled 'Root CA Certificate Information' with a download icon. This section contains a table with the following data:

Country Name	US
State/Province Name	California
Locality Name	San Jose
Organizational Unit Name	IT
Issued By	10.30.116.244
Issued To	10.30.116.244
Expiry Date	2021-03-28 10:39:26

Below the table, there is a section titled 'Upload New Root CA Certificate' with a file input field and two buttons: 'Browse' and 'Upload and Update'.

To update the Certificate:

Step 1 Click **Login as POD User**

Step 2 Navigate to **POD User Administration>>Manage Root CA certificate**.

Step 3 Click **Browse** and select the certificate that you want to upload.

Step 4 Click **Upload**.

- If the certificate is Invalid, and does not matches with the certificate on the management node located at (var/www/mercury/mercury-ca.crt) then Unified Management reverts the certificate which was working previously.
- If the Certificate is valid, Unified Management runs a management node health check and then update the certificate with the latest one.

Note The CA Certificate which is uploaded should be same as the one which is in the management node.



CHAPTER 10

Day 2 Operations of Cisco VIM Unified Management

The following topic guides you the details about the Day 2 Operations of Cisco VIM Unified Management.

- [Shutting Down Cisco VIM Unified Management, on page 321](#)
- [Restarting Cisco VIM Unified Management, on page 322](#)
- [Restoring VIM Unified Management, on page 322](#)
- [Reconfiguring VIM Unified Management , on page 324](#)
- [Reconfiguring Unified Management MySQL Database Password, on page 330](#)
- [Update VIM Unified Management, on page 336](#)

Shutting Down Cisco VIM Unified Management

To stop the Cisco VIM Unified Management Container services, shut down Cisco UCS VIM Unified Management by running the `systemctl stop service` command.

Step 1 Log in to a server in which the Unified Management container is running.

Step 2 Stop the Unified Management service by running the following command from the Shell window:

```
systemctl stop docker-insight
```

a) Check the status of Unified Management Container by running the following command: `docker ps -a | grep insight`.

```
STATUS
Up 6 seconds
```

b) Check the status of the service by running the following command:

```
systemctl status docker-insight
```

The following information is displayed

```
Docker-insight.service - Insight Docker Service
Loaded: loaded (/usr/lib/systemd/system/docker-insight.service; enabled; vendor preset: disabled)
Active: inactive (dead) since <Date and Time since it was last active>
```

Restarting Cisco VIM Unified Management

Step 1 Log In to the server in which the Unified Management container was stopped.

Step 2 Restart the Unified Management service by running the following command from the shell window:

```
systemctl restart docker-insight
```

a) Check the status of Unified Management container by running the following command: **docker ps -a | grep insight**.

```
STATUS
Up 6 seconds
```

b) Check the status of the service by running the following command:

```
systemctl status docker-insight
```

The following output is displayed:

```
Docker-insight.service - Insight Docker Service
Loaded: loaded (/usr/lib/systemd/system/docker-insight.service; enabled; vendor preset: disabled)
Active: active (running) since <Date and Time when it got active.>
```

Restoring VIM Unified Management

Cisco VIM Unified Management can be restored to its previous running state which existed at the time of backup.



Note It is not recommended to run the Unified Management on the node on which restore operation is performed.

Step 1 Re-image the Unified Management management node with the ISO version with which you want to restore the node, and with the same IP address that is used before the failure of the node.

Note Skip Step 1 if re-image is done with the ISO during management node restore. Unified Management restore can also be performed without re-image with ISO. Uninstall the Unified Management through `bootstrap_insight.py` and then restoring it by following below mentioned steps but this needs to be only done when you face issues with Unified Management and not in case of management node failure.

Step 2 Navigate to `/var/cisco/insight_backup/` directory at the remote server where the backup directory was copied during the backup operation.

Step 3 Copy the backup file to the `/var/cisco/insight_backup/` directory of the re-imaged management node. For example, to copy the backup directory from the remote host 20.0.0.5 to the management node `/var/cisco/insight_backup/directory`, execute the following command sequence: `rsync -e ssh -go -rtvpX --numeric-ids root@20.0.0.5:/var/cisco/insight_backup/backup_2017-01-09_14-04-38 /var/cisco/insight_backup`.

Step 4 In `/var/cisco/insight_backup/backup_<date-time>` directory, execute the following command:

```
# ./insight_restore -h

insight_restore : Cisco VIM Insight Restore Script
-----

Usage: ./insight_restore

-v          : Enable verbose mode

-h          : To display this help message

# ./insight_restore
This will initiate an Insight install with the backed up data.

VIM Insight restore logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log

Management Node Validations!
+-----+-----+-----+
| Rule           | Status | Error |
+-----+-----+-----+
| Check Kernel Version | PASS | None |
| Check Docker Version | PASS | None |
| Check Management Node Tag | PASS | None |
| Check Bond Intf. Settings | PASS | None |
| Root Password Check | PASS | None |
| Check Boot Partition Settings | PASS | None |
| Check LV Swap Settings | PASS | None |
| Check Docker Pool Settings | PASS | None |
| Check Home Dir Partition | PASS | None |
| Check Root Dir Partition | PASS | None |
| Check /var Partition | PASS | None |
| Check LVM partition | PASS | None |
| Check RHEL Pkgs Install State | PASS | None |
+-----+-----+-----+

Insight standalone Input Validations!
+-----+-----+-----+
| Rule           | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS | None |
| Valid key check in Insight Setup Data | PASS | None |
| Duplicate key check In Insight Setup Data | PASS | None |
| CVIM/Insight workspace conflict check | PASS | None |
| Check registry connectivity | PASS | None |
| Check Email server for Insight | PASS | None |
+-----+-----+-----+

Setting up Insight, Kindly wait!!!
Cisco VIM Insight Installed successfully!
+-----+-----+-----+
| Description           | Status | Details |
+-----+-----+-----+
| VIM Insight UI URL | PASS | https://<br_api:9000> |
| VIM UI Admin Email ID | PASS | Check for info @: <abs path of insight_setup_data.yaml> |
| | | |
| VIM UI Admin Password | PASS | Check for info @ /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace | PASS | /root/<insight_ws> |
+-----+-----+-----+

Cisco VIM Insight Autobackup Service Info!
+-----+-----+-----+
| Description           | Status | Details |
+-----+-----+-----+
```

```

+-----+
| VIM Insight Autobackup | PASS | [ACTIVE]: Running 'insight-autobackup.service' |
+-----+

VIM Insight restore successfully completed!

Done with VIM Insight restore!
VIM Insight restore logs are at: /var/log/insight/bootstrap_insight/

As the summary table describes, your VIM Insight workspace is restored and hence you need to use
bootstrap_insight.py from the mentioned workspace for performing any actions from here on.

```

Step 5 Run the following command, to verify Unified Management status after the restore operation.

```

# cd /root/<insight_ws>
# ./bootstrap_insight.py -a install-status
          Cisco VIM Insight Install Status!
+-----+
| Description          | Status  | Details                                     |
+-----+
| VIM Insight Setup    | PASS   | Success                                   |
| VIM Insight Version  | PASS   | <release_tag>                             |
| VIM Insight UI URL   | PASS   | https://<br_api:9000>                       |
| VIM Insight Container | PASS   | insight_<tag_id>                           |
| VIM Mariadb Container | PASS   | mariadb_<tag_id>                           |
| VIM Insight Autobackup | PASS   | [ACTIVE]: Running 'insight-autobackup.service'|
| VIM Insight Workspace | PASS   | /root/installer-<tag_id>/insight           |
+-----+

```

Reconfiguring VIM Unified Management

UM reconfigure action provides you with three major functionalities:

1. Reconfigure Unified Management TLS Certificate.
2. Switch from Self Signed TLS Certificate to third-party TLS Certificate.
3. Reconfigure Unified Management MySQL Database Password.



Note Unified Management reconfiguration is not allowed after an update as the update is an intermediate stage between rollback and commit.

Reconfiguring Unified Management TLS Certificate

As the Unified Management web-service is protected by TLS, hence reconfigure action provides flexibility to change the existing TLS Certificate. As there were two approaches to configure it, there are also two approaches to change it.

Reconfiguring Third-party TLS Certificate

If you had provided your own TLS Certificate before Insight Installation through PEM_PATH key in insight_setup_data.yaml, then perform the following steps to reconfigure it.

- Step 1** Enter the command: `# cd <path insight_setup_data.yaml>`
- Step 2** Open the insight_setup_data.yaml file using the command `# vi insight_setup_data.yaml`
- Step 3** Edit the insight_setup_data.yaml to change the value of PEM_PATH and/or SSL_CERT_CHAIN_FILE key to point to the path of your new valid TLS/Cert Chain File Certificate. Then, save the file.

For example:

```
PEM_PATH: "/root/new_tls.pem"
SSL_CERT_CHAIN_FILE: "/root/new_ssl.crt"
```

- Step 4** Enter the following commands:

```
# cd <insight_ws>

# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml>

VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log

Perform the action. Continue (Y/N)y

Management node validation!
+-----+-----+-----+
| Rule | Status | Error |
+-----+-----+-----+
| Check Kernel Version | PASS | None |
| Check Docker Version | PASS | None |
| Check Management Node Tag | PASS | None |
| Check Bond Intf. Settings | PASS | None |
| Root Password Check | PASS | None |
| Check Boot Partition Settings | PASS | None |
| Check LV Swap Settings | PASS | None |
| Check Docker Pool Settings | PASS | None |
| Check Home Dir Partition | PASS | None |
| Check Root Dir Partition | PASS | None |
| Check /var Partition | PASS | None |
| Check LVM partition | PASS | None |
| Check RHEL Pkgs Install State | PASS | None |
+-----+-----+-----+

Insight standalone input validation!
+-----+-----+-----+
| Rule | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS | None |
| Valid key check in Insight setup data | PASS | None |
| Duplicate key check In Insight setup data | PASS | None |
| CVIM/Insight workspace conflict check | PASS | None |
| Check registry connectivity | PASS | None |
| Check Email server for Insight | PASS | None |
+-----+-----+-----+

WARNING!! reconfigure will have few secs of Outage for Insight!
```

```

Cisco VIM Insight Already Exists!
+-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| VIM Insight UI URL   | PASS   | https://<br_api:9000> |
| VIM UI Admin Email ID | PASS   | Check for info @: <abs path of insight_setup_data.yaml> |
|                      |        |                   |
| VIM UI Admin Password | PASS   | Check for info @ /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace | PASS   | /root/<insight_ws>   |
+-----+-----+-----+

```

```

Cisco VIM Insight backup Info!
+-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| Insight backup Status | PASS   | Backup done @
|                      |        | /var/cisco/insight_backup/backup-<release_tag>-<date_time> |
+-----+-----+-----+

```

Done with VIM Insight reconfigure!
 VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"

As the summary table describes Insight gets autobacked up after reconfigure at /var/cisco/insight_backup to preserve the latest state of Insight.

Reconfiguring Self Signed TLS Certificate

If you had created a new TLS Certificate through `tls_insight_cert_gen.py` before Unified Management Installation, follow the steps to reconfigure it.

Step 1 Run the following commands to reconfigure the self signed TLS certificate:

```

# cd <insight_ws>
# ./tls_insight_cert_gen.py -h
usage: tls_insight_cert_gen.py [-h] [--overwrite] --file INSIGHTSETUPDATA
TLS cert generator Insight

optional arguments:
  -h, --help            show this help message and exit
  --overwrite, -o       Overwrite Insight certificates if already present in openstack config directory
  --file INSIGHTSETUPDATA, -f INSIGHTSETUPDATA
                        Location of insight_setup_data.yaml
  # ./tls_insight_cert_gen.py -f <path insight_setup_data.yaml> --overwrite
                        This will overwrite the existing TLS certificate.

```

```

Management node validation
+-----+-----+-----+
| Rule          | Status | Error |
+-----+-----+-----+
| Check Kernel Version | PASS | None |
| Check Ansible Version | PASS | None |
| Check Docker Version | PASS | None |
| Check Management Node Tag | PASS | None |
| Check Bond Intf. Settings | PASS | None |
| Root Password Check | PASS | None |
| Check Boot Partition Settings | PASS | None |
| Check LV Swap Settings | PASS | None |

```

```

| Check Docker Pool Settings      | PASS | None |
| Check Home Dir Partition        | PASS | None |
| Check Root Dir Partition        | PASS | None |
| Check /var Partition            | PASS | None |
| Check LVM partition             | PASS | None |
| Check RHEL Pkgs Install State   | PASS | None |
+-----+-----+-----+

```

Insight standalone input validation

```

+-----+-----+-----+
| Rule                                | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS   | None   |
| Valid key check in Insight setup data | PASS   | None   |
| Duplicate key check In Insight setup data | PASS   | None   |
| CVIM/Insight workspace conflict check | PASS   | None   |
| Check registry connectivity          | PASS   | None   |
| Check Email server for Insight       | PASS   | None   |
+-----+-----+-----+

```

Generating a 4096 bit RSA private key

```

.....++
.....++
writing new private key to '../openstack-configs/insight.key'
```

Step 2 Use the following command, to run the bootstrap:

```
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml>
VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_date>_<time>.log
```

Perform the action. Continue (Y/N)y

Management node validations

```

+-----+-----+-----+
| Rule                                | Status | Error |
+-----+-----+-----+
| Check Kernel Version              | PASS   | None   |
| Check Ansible Version              | PASS   | None   |
| Check Docker Version               | PASS   | None   |
| Check Management Node Tag          | PASS   | None   |
| Check Bond Intf. Settings          | PASS   | None   |
| Root Password Check                | PASS   | None   |
| Check Boot Partition Settings      | PASS   | None   |
| Check LV Swap Settings              | PASS   | None   |
| Check Docker Pool Settings         | PASS   | None   |
| Check Home Dir Partition            | PASS   | None   |
| Check Root Dir Partition            | PASS   | None   |
| Check /var Partition                | PASS   | None   |
| Check LVM partition                | PASS   | None   |
| Check RHEL Pkgs Install state      | PASS   | None   |
+-----+-----+-----+

```

Insight standalone input validation

```

+-----+-----+-----+
| Rule                                | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS   | None   |
| Valid key check in Insight setup data | PASS   | None   |
| Duplicate key check In Insight setup data | PASS   | None   |
| CVIM/Insight workspace conflict check | PASS   | None   |
| Check registry connectivity          | PASS   | None   |
| Check Email server for Insight       | PASS   | None   |
+-----+-----+-----+

```

Switch from Self Signed TLS Certificate to Third-party TLS Certificate

```
WARNING!! Reconfiguration will have few secs of outage for Insight
Cisco VIM Insight Already Exists!
```

Description	Status	Details
VIM Insight UI URL	PASS	https://<br_api:9000>
VIM UI Admin Email ID	PASS	Check for info @: <abs path of insight_setup_data.yaml>
VIM UI Admin Password	PASS	Check for info @ /opt/cisco/insight/secrets.yaml
VIM Insight Workspace	PASS	/root/<insight_ws>

```
Cisco VIM Insight backup Info!
```

Description	Status	Details
Insight backup Status	PASS	Backup done @ /var/cisco/insight_backup/insight_backup_<release_tag>_<date_time>

```
Done with VIM Insight reconfigure!
```

```
VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"
```

```
Insight gets autobacked up after reconfiguration at /var/cisco/insight_backup, to preserve the latest state of Insight.
```

Switch from Self Signed TLS Certificate to Third-party TLS Certificate

If you had created a new TLS certificate through `tls_insight_cert_gen.py` before Insight Installation and want to switch to your own TLS Certificate, then perform the following steps.



Note You cannot switch from third-party TLS certificate to Self-signed TLS certificate.

Step 1 To switch from self-signed TLS certificate to third-party TLS certificate, open the `insight_setup_data.yaml` using the following command:

```
# cd <path insight_setup_data.yaml>
# vi insight_setup_data.yaml
```

Step 2 Edit the `insight_setup_data.yaml` to add `PEM_PATH` and `SSL_CERT_CHAIN_FILE` key to point to path of your new valid TLS and `SSL_CERT_CHAIN` certificate. Save the file after editing.

For example:

```
PEM_PATH: "/root/new_tls.pem"
SSL_CERT_CHAIN_FILE: "/root/new_ssl.crt"
```

Step 3 Following is the command to run the bootstrap:

```
# cd <insight_ws>
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml>
```

VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_date>_<time>.log
Perform the action. Continue (Y/N)y

Management node validation

Rule	Status	Error
Check Kernel Version	PASS	None
Check Ansible Version	PASS	None
Check Docker Version	PASS	None
Check Management Node Tag	PASS	None
Check Bond Intf. Settings	PASS	None
Root Password Check	PASS	None
Check Boot Partition Settings	PASS	None
Check LV Swap Settings	PASS	None
Check Docker Pool Settings	PASS	None
Check Home Dir Partition	PASS	None
Check Root Dir Partition	PASS	None
Check /var Partition	PASS	None
Check LVM partition	PASS	None
Check RHEL Pkgs Install State	PASS	None

Insight standalone input validation

Rule	Status	Error
Insight standalone schema validation	PASS	None
Valid key check in Insight setup data	PASS	None
Duplicate key check In Insight setup data	PASS	None
CVIM/Insight workspace conflict check	PASS	None
Check registry connectivity	PASS	None
Check Email server for Insight	PASS	None

WARNING!! Reconfiguration will have few secs of outage for Insight!

Cisco VIM Insight Already Exists!

Description	Status	Details
VIM Insight UI URL	PASS	https://<br_api:9000>
VIM UI Admin Email ID	PASS	Check for info @: <abs path of insight_setup_data.yaml>
VIM UI Admin Password	PASS	Check for info @ /opt/cisco/insight/secrets.yaml
VIM Insight Workspace	PASS	/root/<insight_ws>

Cisco VIM Insight backup Info!

Description	Status	Details
Insight backup Status	PASS	Backup done @
		/var/cisco/insight_backup/insight_backup_<release_tag>_<date_time>

```

Done with VIM Insight reconfigure!
VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"

Insight gets autobacked up after reconfiguration at /var/cisco/insight_backup to preserve the latest
state of Insight.

```

Reconfiguring Unified Management MySQL Database Password

There are two approaches to reconfigure the MySQL DB password:

1. System generated Unified Management DB password.
2. User supplied Unified Management DB password.

System-generated Unified Management DB Password

Following are the steps to generate MySQL Unified Management DB password:

Step 1 To generate the Unified Management DB Password run the following command:

```

# cd <insight_ws>
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml> --regenerate_secrets

```

```

VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Perform the action. Continue (Y/N)y
Management node validation

```

Rule	Status	Error
Check Kernel Version	PASS	None
Check Docker Version	PASS	None
Check Management Node Tag	PASS	None
Check Bond Intf. Settings	PASS	None
Root Password Check	PASS	None
Check Boot Partition Settings	PASS	None
Check LV Swap Settings	PASS	None
Check Docker Pool Settings	PASS	None
Check Home Dir Partition	PASS	None
Check Root Dir Partition	PASS	None
Check /var Partition	PASS	None
Check LVM partition	PASS	None
Check RHEL Pkgs Install State	PASS	None

```

Insight standalone input validation

```

Rule	Status	Error
Insight standalone schema validation	PASS	None
Valid key check in Insight setup data	PASS	None
Duplicate key check In Insight setup data	PASS	None
CVIM/Insight workspace conflict check	PASS	None
Check registry connectivity	PASS	None
Check Email server for Insight	PASS	None

```

+-----+-----+-----+
WARNING!! reconfiguration will have few secs of Outage for Insight!

Cisco VIM Insight Already Exists!
+-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| VIM Insight UI URL   | PASS   | https://<br_api:9000> |
| VIM UI Admin Email ID | PASS   | Check for info @: <abs path of insight_setup_data.yaml> |
|                      |        |                   |
| VIM UI Admin Password | PASS   | Check for info @ /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace | PASS   | /root/<insight_ws> |
+-----+-----+-----+

Cisco VIM Insight backup Info!
+-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| Insight backup Status | PASS   | Backup done @ |
|                      |        | /var/cisco/insight_backup/backup-<release_tag>-<date_time> |
+-----+-----+-----+

Done with VIM Insight reconfigure!
VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"
As the summary table describes Insight gets autobacked up after reconfigure at /var/cisco/insight_backup
to preserve the latest state of Insight.

```

Step 2 Verify the password change by running the following command:

```

# cat /opt/cisco/insight/secrets.yaml
DB_ROOT_PASSWORD: <new_db_password>

```

User-supplied Unified Management DB Password

Step 1 To provide your own MYSQL DB Password follow the below steps:

Note Your new DB password must contain alphanumeric characters and should be at least 8 characters long.

```

# cd <insight_ws>
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml> --setpassword

```

VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_date>_<time>.log

Perform the action. Continue (Y/N)y

Password for DB_ROOT_PASSWORD: <enter_valid_db_password>

Management node validation

```

+-----+-----+-----+
| Rule                | Status | Error |
+-----+-----+-----+
| Check Kernel Version | PASS  | None |
| Check Ansible Version | PASS  | None |
| Check Docker Version | PASS  | None |
| Check Management Node Tag | PASS | None |
| Check Bond Intf. Settings | PASS | None |
| Root Password Check | PASS  | None |
| Check Boot Partition Settings | PASS | None |
| Check LV Swap Settings | PASS  | None |

```

```

| Check Docker Pool Settings      | PASS | None |
| Check Home Dir Partition       | PASS | None |
| Check Root Dir Partition       | PASS | None |
| Check /var Partition           | PASS | None |
| Check LVM partition            | PASS | None |
| Check RHEL Pkgs Install State  | PASS | None |
+-----+-----+-----+

```

Insight standalone input validation

```

+-----+-----+-----+
| Rule                                | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS   | None  |
| Valid key check in Insight setup data | PASS   | None  |
| Duplicate key check In Insight setup data | PASS   | None  |
| CVIM/Insight workspace conflict check | PASS   | None  |
| Check registry connectivity         | PASS   | None  |
| Check Email server for Insight      | PASS   | None  |
+-----+-----+-----+

```

WARNING!!Reconfiguration will have few secs of Outage for Insight!

Cisco VIM Insight Already Exists!

```

+-----+-----+-----+
| Description                          | Status | Details |
+-----+-----+-----+
| VIM Insight UI URL                    | PASS   | https://<br_api:9000> |
| VIM UI Admin Email ID                 | PASS   | Check for info @: <abs path of insight_setup_data.yaml> |
| VIM UI Admin Password                 | PASS   | Check for info @ /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace                 | PASS   | /root/<insight_ws> |
+-----+-----+-----+

```

Cisco VIM Insight backup Info!

```

+-----+-----+-----+
| Description                          | Status | Details |
+-----+-----+-----+
| Insight backup Status                 | PASS   | Backup done @ |
|                                       |        | /var/cisco/insight_backup/insight_backup_<release_tag>_<date_time>|
+-----+-----+-----+

```

Done with VIM Insight reconfigure!

VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"

As the summary table describes Insight gets autobacked up after reconfigure at /var/cisco/insight_backup to preserve the latest state of Insight.

Step 2 Verify the password change by running the following command:

```

# cat /opt/cisco/insight/secrets.yaml
DB_ROOT_PASSWORD: <new_db_password>

```

Reconfiguring Unified Management SMTP Server

Unified Management requires a valid SMTP Server to send mails to users (Pod-Admin, UI-Admin, and regular users). If SMTP Server goes down, you can reconfigure it.

Following values can be reconfigured:

- INSIGHT_SMTP_SERVER
- INSIGHT_EMAIL_ALIAS_PASSWORD (only needed for Authenticated SMTP server)
- INSIGHT_EMAIL_ALIAS
- INSIGHT_SMTP_PORT (optional, defaults to 25)

Step 1 Run the following command to reconfigure the SMTP server:

```
# cd <path insight_setup_data.yaml>
Open insight_setup_data.yaml file
# vi insight_setup_data.yaml
Edit the insight_setup_data.yaml to change value of INSIGHT_SMTP_SERVER key. Save the file after editing.
```

Step 2 Run the bootstrap command as follows:

```
# cd <insight_ws>
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml>
VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Perform the action. Continue (Y/N)y
```

Management node validation

Rule	Status	Error
Check Kernel Version	PASS	None
Check Ansible Version	PASS	None
Check Docker Version	PASS	None
Check Management Node Tag	PASS	None
Check Bond Intf. Settings	PASS	None
Root Password Check	PASS	None
Check Boot Partition Settings	PASS	None
Check LV Swap Settings	PASS	None
Check Docker Pool Settings	PASS	None
Check Home Dir Partition	PASS	None
Check Root Dir Partition	PASS	None
Check /var Partition	PASS	None
Check LVM partition	PASS	None
Check RHEL Pkgs Install State	PASS	None

Insight standalone input validation

Rule	Status	Error
Insight standalone schema validation	PASS	None
Valid key check in Insight setup data	PASS	None
Duplicate key check In Insight setup data	PASS	None
CVIM/Insight workspace conflict check	PASS	None
Check registry connectivity	PASS	None
Check Email server for Insight	PASS	None

WARNING!! Reconfiguration will have few secs of Outage for Insight!

Cisco VIM Insight Already Exists!

Description	Status	Details
VIM Insight UI URL	PASS	https://<br_api:9000>
VIM UI Admin Email ID	PASS	Check for info @: <abs path of insight_setup_data.yaml>

```

| VIM UI Admin Password | PASS | Check for info @ /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace | PASS | /root/<insight_ws> |
+-----+-----+-----+
Cisco VIM Insight backup Info!
+-----+-----+-----+
| Description          | Status | Details |
+-----+-----+-----+
| Insight backup Status | PASS   | Backup done @
|                       |        | /var/cisco/insight_backup/insight_backup_<release_tag>_<date_time>|
+-----+-----+-----+

Done with VIM Insight reconfigure!
VIM Insight reconfigure logs are at: "/var/log/insight/bootstrap_insight/"

Insight gets autobacked up after reconfiguration at /var/cisco/insight_backup to preserve the latest
state of Insight.

```

Reconfiguring Unified Management LDAP Server

Unified Management supports both LDAP and LDAP over SSL (LDAPS) for an Active Directory (AD) environment. If the LDAP server is down or if you need to change any of its configuration, execute Unified Management reconfigure action.

Step 1 Reconfigure the LDAP(s) server:

a) Run the following command to open insight_setup_data.yaml file:

```
# cd <path insight_setup_data.yaml>
```

b) Edit the insight_setup_data.yaml, using the following command, to change the value of LDAP keys.

```
:
```

```
# vi insight_setup_data.yaml
```

LDAP keys are listed below:

- LDAP_MODE: This key can be reconfigured only to 'True', to allow the user to switch only from No-LDAP to LDAP, and not vice-versa.
- LDAP_SERVER: This key is reconfigurable to switch to new LDAP server.
- LDAP_PORT: Reconfiguration of this key is allowed.
- LDAP_ADMIN: Reconfiguration of this key is allowed.
- LDAP_ADMIN_PASSWORD: Reconfiguration of this key is allowed.
- LDAP_SECURE: This key can be reconfigured only to 'True', to allow the user to switch from non-secure LDAP to secure LDAP connection, and not vice-versa.
- LDAP_CERT_PATH: This key can be reconfigured, to switch from Self-signed certificate to CA-signed certificate, and not vice-versa.

- LDAP_USER_ID_ATTRIBUTE: This key can be reconfigured to point to new LDAP user id attribute.

c) Save the edited file.

Step 2 Run the bootstrap command

```
# cd <insight_ws>
# ./bootstrap_insight.py -a reconfigure -f <path_to insight_setup_data.yaml>

VIM Insight reconfigure logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Perform the action. Continue (Y/N)y
```

Management node validation

Rule	Status	Error
Check Kernel Version	PASS	None
Check Ansible Version	PASS	None
Check Docker Version	PASS	None
Check Management Node Tag	PASS	None
Check Bond Intf. Settings	PASS	None
Root Password Check	PASS	None
Check Boot Partition Settings	PASS	None
Check LV Swap Settings	PASS	None
Check Docker Pool Settings	PASS	None
Check Home Dir Partition	PASS	None
Check Root Dir Partition	PASS	None
Check /var Partition	PASS	None
Check LVM partition	PASS	None
Check RHEL Pkgs Install State	PASS	None

Insight standalone input validation

Rule	Status	Error
Insight standalone schema validation	PASS	None
Valid key check in Insight setup data	PASS	None
Duplicate key check In Insight setup data	PASS	None
CVIM/Insight workspace conflict check	PASS	None
Check registry connectivity	PASS	None
Check LDAP connectivity	PASS	None
Check Email server for Insight	PASS	None

WARNING!! Reconfiguration will have few secs of Outage for Insight!

Cisco VIM Insight Already Exists!

Description	Status	Details
VIM Insight UI URL	PASS	https://<br_api:9000>
VIM UI Admin Email ID	PASS	Check for info @: <abs path of insight_setup_data.yaml>
VIM UI Admin Password	PASS	Check for info @ /opt/cisco/insight/secrets.yaml
VIM Insight Workspace	PASS	/root/<insight_ws>

Cisco VIM Insight backup Info!

Description	Status	Details

- Step 3** Navigate to the tools directory inside the new workspace
(/root/Insight-<tag_id>/installer-<tag_id>/tools/).
- Step 4** Execute the script ./insight_upgrade.sh.
- Step 5** Press **Y/y** or **N/n**, to proceed or terminate the script respectively.

Output

```
[INFO]: This script will upgrade Insight but won't work if you want to do a fresh ISO on latest tag!!!
[INFO]: Post execution of this script 'Commit/Rollback' isn't required.
Do you want to proceed(Y/y/N/n)?
Taking backup of existing setup
INFO: UM-Node detected
PASS: DB backed up successfully
INFO: Please backup /var/cisco/insight_data_backup manually on some-other server in case of
fresh ISO
Uninstalling Insight from old workspace
```

Cisco VIM Insight uninstall logs are available at

/var/log/insight/bootstrap_insight/bootstrap_insight_2018-12-16_23:58:50.log

VIM Insight uninstallation in progress, Kindly wait!!!

```
Done with VIM Insight uninstall!
Setting up env prior upgrade
/root/insight-17013/tools
Copy Certificates and insight setupdata from Old WS to New WS
Setting up Insight with new tag
```

Cisco VIM Insight install logs are at:

/var/log/insight/bootstrap_insight/bootstrap_insight_2018-12-16_23:59:29.log

Management Node Validation!

Rule	Status	Error
Check Kernel Version	PASS	None
Check Ansible Version	PASS	None
Check Docker Version	PASS	None
Check Management Node Tag	PASS	None
Check Bond Intf. Settings	PASS	None
Root Password Check	PASS	None
Check Boot Partition Settings	PASS	None
Check LV Swap Settings	PASS	None
Check Docker Pool Settings	PASS	None
Check Home Dir Partition	PASS	None
Check Root Dir Partition	PASS	None
Check /var Partition	PASS	None
Check LVM partition	PASS	None
Check if /mnt dir is already mounted	PASS	None
Check Available Disk Space	PASS	None

Insight standalone Input Validation!

Rule	Status	Error
Insight standalone Schema Validation	PASS	None
Valid Key Check in Insight Setup Data	PASS	None

```

| Duplicate Key Check In Insight Setup Data      | PASS | None |
| CVIM/Insight Workspace Conflict Check        | PASS | None |
| Check LDAP configuration in Insight Setup Data | PASS | None |
+-----+-----+-----+

```

Setting up VIM Insight, Kindly wait!!!

Cisco VIM Insight Installed successfully!

```

+-----+-----+-----+
| Description          | Status | Details |
+-----+-----+-----+
| VIM Insight UI URL   | PASS   | https://172.28.120.189:9000 |
| VIM UI Admin Email ID | PASS   | Check for info @: |
| /root/insight-17013/openstack-configs/insight_setup_data.yaml |
| VIM UI Admin Password | PASS   | Check for info @: /opt/cisco/insight/secrets.yaml |
| VIM Insight Workspace | PASS   | /root/insight-17013/insight |
+-----+-----+-----+

```

Cisco VIM Insight backup Info!

```

+-----+-----+-----+
| Description          | Status | Details |
+-----+-----+-----+
| VIM Insight backup Status | PASS   | Backup done @ |
| /var/cisco/insight_backup/insight_backup_2.3.44_2018-12-16_23:59:29 |
+-----+-----+-----+

```

Cisco VIM Insight Autobackup Service Info!

```

+-----+-----+-----+
| Description          | Status | Details |
+-----+-----+-----+
| VIM Insight Autobackup | PASS   | [ACTIVE]: Running 'insight-autobackup.service' |
+-----+-----+-----+

```

Done with VIM Insight install!

Cisco VIM Insight install logs are at:

/var/log/insight/bootstrap_insight/bootstrap_insight_2018-12-16_23:59:29.log

Restoring data post install

/root/insight-17013/tools

INFO: UM-Node detected

PASS: DB Restored successfully

Insight upgraded to latest tag successfully

Updating UM from 2.4.10 to later versions

The update action makes the old docker containers of Unified Management and mariadb in exit state, and brings up new ones with the new tag. The old containers and images are restored until you perform the **Commit** action.

Update is an intermediate action and allows you to do either a **Commit** action to settle for the current version or do a **Rollback** to revert back to the old version.

The old workspace is preserved, if you want to do a rollback to the previous version.

After an update:

- Your Unified Management workspace is set as the new workspace that you just extracted out of the tarball.
- Backup and reconfigure action are not allowed either from old or new Unified Management workspace.

Update Scenarios

Following are the update scenarios:

- Insight and mariadb containers gets updated to a new tag.
- Either insight or mariadb container gets updated to a new tag.

Update VIM Unified Management with Internet Access

Following are the steps to update VIM Unified Management:

Step 1 Get the new installer tar ball, which will be available after each release.

Extract the tar ball to get the new Unified Management workspace by running the following command:

```
# tar -xvzf mercury-installer.tar.gz
```

Step 2 Update the VIM Unified Management by running the following commands:

```
# cd /root/<new_insight_ws>/insight/  
/bootstrap_insight.py -a update
```

VIM Insight update logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Management Node validation!

```
+-----+-----+-----+  
| Rule                                     | Status | Error |  
+-----+-----+-----+  
| Check Kernel Version                   | PASS  | None  |  
| Check Docker Version                   | PASS  | None  |  
| Check Management Node Tag              | PASS  | None  |  
| Check Bond Intf. Settings              | PASS  | None  |  
| Root Password Check                    | PASS  | None  |  
| Check Boot Partition Settings          | PASS  | None  |  
| Check LV Swap Settings                  | PASS  | None  |  
| Check Docker Pool Settings             | PASS  | None  |  
| Check Home Dir Partition                | PASS  | None  |  
| Check Root Dir Partition                | PASS  | None  |  
| Check /var Partition                    | PASS  | None  |  
| Check LVM partition                     | PASS  | None  |  
| Check RHEL Pkgs Install State          | PASS  | None  |  
+-----+-----+-----+
```

Insight standalone input validation

```
+-----+-----+-----+  
| Rule                                     | Status | Error |  
+-----+-----+-----+  
| Insight standalone schema validation   | PASS  | None  |  
| Valid key check in Insight setup data  | PASS  | None  |  
| Duplicate key check In Insight setup data | PASS  | None  |  
| CVIM/Insight workspace conflict check  | PASS  | None  |  
| Check registry connectivity             | PASS  | None  |  
| Check Email server for Insight          | PASS  | None  |  
+-----+-----+-----+
```

```

Downloading Updated VIM Insight Artifacts, will take time!!!
Cisco VIM Insight update Info!
+-----+-----+-----+
| Description                               | Status | Details                               |
+-----+-----+-----+
| VIM Insight Container: insight_<new_tag> | PASS   | Updated from insight_<old_tag>|
| VIM Mariadb Container: mariadb_<new_tag> | PASS   | Updated from mariadb_<old_tag>|
+-----+-----+-----+
Done with VIM Insight update!
VIM Insight update logs are at: "/var/log/insight/bootstrap_insight/"

```

Step 3 Verify the Unified Management Update.

```

# ./bootstrap_insight.py -a update-status
Cisco VIM Insight Update Status!
+-----+-----+-----+
| Description                               | Status | Details                               |
+-----+-----+-----+
| VIM Insight Container: insight_<new_tag> | PASS   | Updated from insight_<old_tag>|
| VIM Mariadb Container: insight_<new_tag> | PASS   | Updated from mariadb_<old_tag>|
+-----+-----+-----+

```

VIM Unified Management without Internet Access**Step 1** Copy the new installer tar ball to the Unified Management Management Node.

Extract the tar ball to get the new Unified Management workspace by running the following command:

```
# tar -xvzf mercury-installer.tar.gz
```

Step 2 To download the new Unified Management artifacts, follow the steps given in section Preparing to Install Cisco NFVI on Management Nodes Without Internet Access, of *Cisco VIM Install Guide*.**Step 3** Run Import Artifacts:

```

# cd /root/installer_<tag_id>/tools
# ./import_artifacts.sh
This verifies that /var/cisco/artifacts on the management node has the following Insight artifacts,
along with the other components 'insight-K9.tar' and 'mariadb-app-K9.tar'.'

```

Step 4 Update the Unified Management by running the following command:

```

# cd ../insight/
# ./bootstrap_insight.py -a update

VIM Insight update logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Management node validations!
+-----+-----+-----+
| Rule                               | Status | Error |
+-----+-----+-----+
| Check Kernel Version               | PASS   | None |
| Check Ansible Version              | PASS   | None |
| Check Docker Version               | PASS   | None |

```

```

| Check Management Node Tag      | PASS | None |
| Check Bond Intf. Settings     | PASS | None |
| Root Password Check           | PASS | None |
| Check Boot Partition Settings | PASS | None |
| Check LV Swap Settings        | PASS | None |
| Check Docker Pool Settings    | PASS | None |
| Check Home Dir Partition      | PASS | None |
| Check Root Dir Partition      | PASS | None |
| Check /var Partition          | PASS | None |
| Check LVM partition           | PASS | None |
| Check RHEL Pkgs Install State | PASS | None |
+-----+-----+-----+

```

Insight standalone input validation

```

+-----+-----+-----+
| Rule                                | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation | PASS   | None   |
| Valid key check in Insight setup data | PASS   | None   |
| Duplicate key check In Insight setup data | PASS   | None   |
| CVIM/Insight workspace conflict check | PASS   | None   |
| Check registry connectivity          | PASS   | None   |
| Check Email server for Insight       | PASS   | None   |
+-----+-----+-----+

```

Updating VIM Insight, Kindly wait!!!

Cisco VIM Insight update Info!

```

+-----+-----+-----+
| Description                          | Status | Details |
+-----+-----+-----+
| VIM Insight UI URL                   | PASS   | https://<br_api:9000> |
| VIM Insight Container: insight_<new_tag> | PASS   | Updated from insight_<old_tag> |
| VIM Mariadb Container: mariadb_<new_tag> | PASS   | Updated from mariadb_<old_tag> |
| VIM Insight Workspace                 | PASS   | /root/<new_insight_ws> |
+-----+-----+-----+

```

Done with VIM Insight update!

VIM Insight update logs are at: "/var/log/insight/bootstrap_insight/"

Step 5 Verify Unified Management update by running the following command:

```

# ./bootstrap_insight.py -a update-status
Cisco VIM Insight Update Status!
+-----+-----+-----+
| Description                          | Status | Details |
+-----+-----+-----+
| VIM Insight Container: insight_<new_tag> | PASS   | Updated from insight_<old_tag> |
| VIM Mariadb Container: insight_<new_tag> | PASS   | Updated from mariadb_<old_tag> |
+-----+-----+-----+

```

Rollback VIM Unified Management

VIM Unified Management Rollback provides feature to revert to the old UM release which is used before the update.

Following are some of the key points:

- The rollback action removes the new docker containers of Unified Management and mariadb which is created after an update and bring up old ones with the old tag.

- The new workspace is used to update the operation later or the VIM may be running from it.
- After rollback, your Unified Management workspace is the old workspace which you were using before the update.

Following are the steps to perform Unified Management rollback:

Step 1 Run the following command to rollback VIM Unified Management:

```
# cd /root/<new_insight_ws>
# ./bootstrap_insight.py -a rollback

VIM Insight rollback logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log

Management node validation!
+-----+-----+-----+
| Rule                                     | Status | Error |
+-----+-----+-----+
| Check Kernel Version                    | PASS   | None  |
| Check Ansible Version                    | PASS   | None  |
| Check Docker Version                    | PASS   | None  |
| Check Management Node Tag                | PASS   | None  |
| Check Bond Intf. Settings                | PASS   | None  |
| Root Password Check                     | PASS   | None  |
| Check Boot Partition Settings            | PASS   | None  |
| Check LV Swap Settings                   | PASS   | None  |
| Check Docker Pool Settings              | PASS   | None  |
| Check Home Dir Partition                 | PASS   | None  |
| Check Root Dir Partition                 | PASS   | None  |
| Check /var Partition                     | PASS   | None  |
| Check LVM partition                      | PASS   | None  |
| Check RHEL Pkgs Install State            | PASS   | None  |
+-----+-----+-----+

Insight standalone input validation
+-----+-----+-----+
| Rule                                     | Status | Error |
+-----+-----+-----+
| Insight standalone schema validation     | PASS   | None  |
| Valid key check in Insight setup data    | PASS   | None  |
| Duplicate key check In Insight setup data | PASS   | None  |
| CVIM/Insight workspace conflict check   | PASS   | None  |
| Check registry connectivity              | PASS   | None  |
| Check Email server for Insight           | PASS   | None  |
+-----+-----+-----+

VIM Insight rollback in progress, Kindly wait!!!
Cisco VIM Insight rollback Info!
+-----+-----+-----+
| Description                               | Status | Details |
+-----+-----+-----+
| VIM Insight UI URL                        | PASS   | https://<br_api:9000> |
| VIM Insight Container: insight_<old_tag> | PASS   | Rollback from insight_<new_tag>|
| VIM Mariadb Container: mariadb_<old_tag> | PASS   | Rollback from mariadb_<new_tag>|
| VIM Insight Workspace                     | PASS   | /root/<old_insight_ws> |
+-----+-----+-----+

Done with VIM Insight rollback!
VIM Insight rollback logs are at: "/var/log/insight/bootstrap_insight/"
```

Step 2 Verify the rollback status by running the following command:

```
# ./bootstrap_insight.py -a install-status
Cisco VIM Insight Install Status!
+-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| VIM Insight Version  | PASS   | <release_tag>   |
| VIM Insight UI URL   | PASS   | https://<br_api:9000> |
| VIM Insight Container | PASS   | insight_<tag_id> |
| VIM Mariadb Container | PASS   | mariadb_<tag_id> |
| VIM Insight Workspace | PASS   | /root/<insight_ws> |
+-----+-----+-----+
```

Commit VIM Unified Management

VIM Insight commit supports for a new Insight release after an update.

Following are some of the key points:

- The old workspace will not be deleted and remain as it is.
- After the commit, your Unified Management workspace which has been used for the update is the new workspace.

Step 1 Run the following command to commit VIM Insight:

```
# cd /root/<new_insight_ws>
# ./bootstrap_insight.py -a commit
VIM Insight commit logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log
Management Node Validation!
+-----+-----+-----+
| Rule                               | Status | Error |
+-----+-----+-----+
| Check Kernel Version               | PASS   | None |
| Check Ansible Version               | PASS   | None |
| Check Docker Version                | PASS   | None |
| Check Management Node Tag           | PASS   | None |
| Check Bond Intf. Settings           | PASS   | None |
| Root Password Check                 | PASS   | None |
| Check Boot Partition Settings        | PASS   | None |
| Check LV Swap Settings              | PASS   | None |
| Check Docker Pool Settings           | PASS   | None |
| Check Home Dir Partition             | PASS   | None |
| Check Root Dir Partition             | PASS   | None |
| Check /var Partition                 | PASS   | None |
| Check LVM partition                  | PASS   | None |
| Check RHEL Pkgs Install State        | PASS   | None |
+-----+-----+-----+

Insight standalone Input Validation!
+-----+-----+-----+
| Rule                               | Status | Error |
+-----+-----+-----+
| Insight standalone Schema Validation | PASS   | None |
+-----+-----+-----+
```

```

| Valid Key Check in Insight Setup Data      | PASS | None |
| Duplicate Key Check In Insight Setup Data | PASS | None |
| CVIM/Insight workspace conflict           | PASS | None |
| Check registry connectivity                | PASS | None |
| Check Email server for Insight            | PASS | None |
+-----+-----+-----+

```

VIM Insight commit in progress, Kindly wait!!!
Cisco VIM Insight commit Info!

```

+-----+-----+-----+
| Description                               | Status | Details                               |
+-----+-----+-----+
| VIM Insight UI URL                       | PASS   | https://<br_api:9000>                 |
| VIM Insight Container: insight_<old_tag> | PASS   | Rollback from insight_<new_tag>      |
| VIM Mariadb Container: mariadb_<old_tag> | PASS   | Rollback from mariadb_<new_tag>      |
| VIM Insight Workspace                     | PASS   | /root/<old_insight_ws>                |
+-----+-----+-----+

```

Done with VIM Insight commit!
VIM Insight commit logs are at: "/var/log/insight/bootstrap_insight/"

Step 2 Verify the commit status by running the following command:

```

# ./bootstrap_insight.py -a install-status
Cisco VIM Insight Install Status!
+-----+-----+-----+
| Description                               | Status | Details                               |
+-----+-----+-----+
| VIM Insight Version                       | PASS   | <release_tag>                        |
| VIM Insight UI URL                       | PASS   | https://<br_api:9000>                 |
| VIM Insight Container                     | PASS   | insight_<tag_id>                     |
| VIM Mariadb Container                     | PASS   | mariadb_<tag_id>                     |
| VIM Insight Workspace                     | PASS   | /root/<insight_ws>                    |
+-----+-----+-----+

```





CHAPTER 11

Overview to the Cisco Virtual Topology System

The Cisco Virtual Topology System (VTS) is an optional Cisco NFVI application that uses the Neutron driver and supports Cisco Vector Packet Processing. The following topics provide an overview to VTS architecture and features. When using VTS with Cisco NFVI, keep the following OpenStack tenant restrictions in mind:

Restriction	Description
Nova flavors: VM RAM > 512MB and equal to a multiple of 512MB	This limitation is due to NUMA and huge pages.
Nova Flavors: nova flavor-key m1.medium set hw:mem_page_size=large	VHOST mode is the only mode supported by the VTS installation at this time. To support VHOST connections nova needs the following configurations on each flavor that will be used.

- [Understanding Cisco VTS, on page 345](#)
- [Cisco VTS Architecture Overview, on page 346](#)
- [Virtual Topology Forwarder, on page 347](#)
- [Virtual Topology System High Availability, on page 349](#)

Understanding Cisco VTS

The Cisco Virtual Topology System (VTS) is a standards-based, open, overlay management, and provisioning system for data center networks. It automates the DC overlay fabric provisioning for both physical and virtual workloads.

Cisco VTS provides a network virtualization architecture and software-defined networking (SDN) framework that meets the requirements of multitenant data centers for cloud services. It enables a policy-based approach for overlay provisioning.

Cisco VTS automates complex network overlay provisioning and management tasks through integration with cloud orchestration systems such as OpenStack and VMware vCenter. It reduces the complexity involved in managing heterogeneous network environments.

You can manage the solution in the following ways:

- Using the embedded Cisco VTS GUI
- Using a set of northbound Representational State Transfer (REST) APIs that can be consumed by orchestration and cloud management systems.


Cisco VTS provides:

- Fabric automation
- Programmability
- Open, scalable, standards-based solution
- Cisco Nexus 2000, 3000, 5000, 7000, and 9000 Series Switches. For more information, see Supported Platforms in *Cisco VTS 2.6 Installation Guide*.
- Software forwarder (Virtual Topology Forwarder [VTF])

Cisco VTS Architecture Overview

Cisco VTS architecture has two main components, namely, the Policy Plane and the Control Plane. These components perform core functions such as SDN control, resource allocation, and core management function.

Figure 24: Cisco VTS Architecture



- **Policy Plane:** The Policy Plane enables Cisco VTS to implement a declarative policy model which is designed to capture intent and render of the user into a specific device-level construct. The solution exposes a set of modular policy constructs that can be flexibly organized into user-defined services for use cases across service provider and cloud environments. These policy constructs are exposed using REST APIs that are consumed by orchestrators and applications or using the Cisco VTS GUI. The policy models are exposed as system policies or service policies.

System policies allow administrators to logically group devices into pods within or across data centers to define Admin Domains with common system parameters. For example, BGP-EVPN Control Plane with distributed Layer 2 and 3 gateways.

The inventory module maintains a database of the available physical entities (for example, data center interconnect [DCI] routers and top-of-rack leaf, spine, and border-leaf switches) and virtual entities (for example, VTFs) in the Virtual Topology System domain. The database also includes interconnections between these entities and details about the services instantiated within a Virtual Topology System domain.

The resource management module manages the available resource pools in the Virtual Topology System domain, including VLANs, VXLAN Network Identifiers (VNIs), IP addresses, and multicast groups.

- **Control Plane:** The Control Plane module serves as the SDN control subsystem that programs the various data planes including the VTFs residing on the x86 servers, hardware leafs, DCI gateways. The Control Plane hosts Service Routing (SR) module, which provides routing services to Cisco VTS. The Service Routing (SR) module calculates the L2 and L3 tables and routes to provide connectivity between the different VMs for a given tenant and service chaining. The main components of this module are VTSR and VTF. VTSR is the controller and Virtual topology forwarder (VTF) runs on each compute server hosting the tenant VMs.

Virtual Topology Forwarder

Virtual Topology Forwarder (VTF) runs on each compute server in the DC and provides connectivity to all tenant VMs hosted on the compute server. VTF supports both intra and inter DC/WAN connectivity. VTF allows Cisco VTS to terminate the VXLAN tunnels on host servers by using the VTF as a Software VXLAN Tunnel Endpoint (VTEP). Cisco VTS also supports hybrid overlays by combining the physical and virtual endpoints into a single VXLAN segment.

VTF has two major components, namely, Cisco's VPP (Vector Packet Processing) and VPFA. VPFA is a Cisco agent running on each VMM compute resource. VPFA is the FIB agent that receives the L2/L3 table forwarding information from VTSR to provide connectivity to the local tenant VMs that are hosted on its compute, and programs them in the VPP.

VTF is deployed as a virtual machine or in vhost mode, to deliver a high-performance software Data Plane on a host server.

Overview to Cisco VTF and VPP


Cisco VTF is a Cisco Soft switch that is built on the Cisco Vector Packet Processing (VPP) technology.

The VPP platform is an extensible framework that provides productive and quality switch or router functionality. It is the open source version of the Cisco VPP technology, which is a high performance, packet-processing stack that can run on commodity CPUs.

The benefits of VPP are its high performance, proven technology, modularity, flexibility, and rich feature set.

The VPP platform is built on a packet-processing graph. This modular approach allows anyone to plugin new graph nodes. This makes extensibility rather simple, and the plugins can be customized for specific purposes.

Figure 25: VPP Platform



The VPP platform grabs all available packets from RX rings to form a vector of packets. A packet-processing graph is applied, node by node (including plugins) to the entire packet vector. Graph nodes are small and modular, and loosely coupled which makes it easy to include new graph nodes and rewire existing graph nodes.

A plugin can introduce new graph nodes or rearrange the packet-processing graph. You can also build a plugin independent from the VPP source and consider it as an independent component. A plugin can be installed by adding it to a plugin directory.


VTF uses remote plugin that binds into VPP using VPFA (VPF agent). The VPFA interacts with VPP application using low-level API. The VPFA exposes netconf or yang based API for remote devices to program the VTF through the VPFA.

VPP + VHOSTUSER

Vhost is a solution that allows the user space process to share a number of virtqueues directly with a Kernel driver. The transport mechanism in this case is the ability of the kernel side to access the user space application memory, and a number of ioeventfds and irqfds to serve as the kick mechanism. A QEMU guest uses an emulated PCI device, as the control plane to handle the QEMU. Once a virtqueue has been set up, the QEMU guest uses the Vhost API to pass direct control of a virtqueue to a Kernel driver.

In this model, a vhost_net driver directly passes the guest network traffic to a TUN device directly from the Kernel side, improving performance significantly.

Figure 26: VTF Vhost



In the above implementation, the guest NFV application directly writes packets into the TX rings, which are shared through a common vhost socket as the RX ring on the VPP. The VPP grabs these packets from the RX ring buffer and forwards the packets using the vector graphs it maintains.

Virtual Topology System High Availability

The Virtual Topology System solution is designed to support redundancy, with two solution instances running on separate hosts in an active-standby configuration.

During the initial setup, each instance is configured with an underlay IP address and a virtual IP address. Virtual Router Redundancy Protocol (VRRP) is used between the instances to determine the active instance.

The data from the active-instance is synchronized with the standby instance after each transaction to ensure consistency of the Control Plane information to accelerate failover after a failure. BGP peering is established from both VTS instances for the distribution of tenant-specific routes. During the switchover, you must perform a Nonstop Forwarding (NSF) and a graceful restart to ensure that services are not disrupted.

For more information on setting up high availability, refer to the *Installing VTS in the High Availability Mode* section of the *Cisco VTS 2.6 Installation Guide*.



CHAPTER 12

Managing Backup and Restore Operations

The following topics describe Cisco NFVI management node backup and restore operations.

- [Managing Backup and Restore Operations, on page 351](#)
- [Backing Up VIM UM, on page 353](#)
- [Restoring the Management Node, on page 357](#)
- [Management Node Autobackup, on page 359](#)
- [Managing Cisco VIM Software Hub, on page 360](#)

Managing Backup and Restore Operations

The management node hosts critical services such as Cisco VIM REST API, Cobbler for PXE, ELK for Logging/Kibana dashboard, and VMTP for the cloud validation in Cisco VIM.

The management node is not redundant during the initial Cisco VIM offering, hence it is recommended to take backup of the management node. Using the saved management node information, you can restore the management node if you are facing any issues with the platform.

Backing Up the Management Node

An administrator must maintain the number of backup snapshots on the management node. The backup of the management node is possible only after complete deployment of at least one Cisco VIM. Two copies of backup folders are maintained at the management node itself and the older copy will be overwritten when a next backup is performed.


During the backup operation, activities such as pod management, software update or upgrade, and addition or deletion or replacement of nodes cannot be performed.

The REST API and ELK services are stopped during the backup operation, the OpenStack Logs are cached on the control, compute, and storage nodes until the restoration of the management node is completed.

As part of the backup operation, two files are created: `.backup_files` and `.backup_hash`. `.backup_files` is a list of files that are backed up, while the second one is the hash. These two files are placed under the backup folder `/var/cisco/backup_<tag>_<date-time>` at the management node and also at the `/var/cisco/` folder of all three controllers. These two files are used during the restore validation. When you attempt to restore from a particular backup, these two files within this backup are compared to the files that are kept in the controllers. If there is any discrepancy, the restore validation fails and you are prompted to either terminate the restore operation or continue despite the validation failure. Only one copy of the `.backup_files` and `.backup_hash` are

kept at the controllers, that is every time a new backup is created, these two files are overwritten with the most recent ones. Hence the restore validation passes only when the latest backup is used for restore.

Figure 27: Cisco NFVI Management Node Backup Operation



Before you begin

- Save the management node information (for example, IP address of the management node) for use during the restore operation.
- Ensure that you have the br_mgmt and br_api IP addresses and respective network information.

Step 1 Launch a SSH session to the Cisco NFVI management node.

Step 2 Navigate to the <installer-ws>/tools/mgmt/ directory.

Step 3 Execute `mgmt_node_backup.py`.

What to do next

The backup operation takes approximately 30 minutes and creates the backup_<tag>_<date-time> directory in the /var/cisco/ path.

Copy the directory to a remote server to recover the management node using rsync.

For example, to copy the backup directory to the remote server 20.0.0.5 /var/cisco/directory , execute the following command sequence:

```
rsync -e ssh -go -rtvpX --numeric-ids /var/cisco/
```



Note On the remote server, protect the backup directory for any unauthorized access as the backup files may contain sensitive information. To preserve the file ownership and Linux markings, run as **root** to sync the remote server. The remote server must run RHEL or CentOS 7.x, so that no permission or markings are lost.

At the remote server, change directory to where the backup directory is copied to; in this example /var/cisco/backup_<tag>_<date-time>/.

To verify if the backup is not corrupted or modified, execute `./check_integrity`.

Check_integrity depends on the following packages, the packages are installed on the server where check_integrity is executed.

```
python-prettytable
python-jinja2
python-babel
python-markupsafe
python-setuptools
pytz
```

Backup with Forwarding ELK Logs to External Syslog Server

When the feature Forwarding ELK Logs to External Syslog Server is enabled, during the backup process, in both the autobackup and manual backup, the ELK Logs are not collected. For manual backups, you can override by appending the `-a` or `--add-elk` option to the backup command. The `-s` or `--skip-elk` option is to skip the ELK Logs collection regardless of the forwarding feature is enabled or not.

```
# cd installer/tools/mgmt
# ./mgmt_node_backup.py --help
Usage: ./mgmt_node_backup.py [options]
Options:
  -h, --help            show this help message and exit
  -s, --skip-elk        do not collect ELK logs during backup
  -a, --add-elk         force to also collect ELK logs on backup
```

Backing Up VIM UM

Administrator maintains the backup for Unified Management on the management node. The backup of the Unified Management is done only after the complete deployment of the Unified Management bootstrap. Only two copies of backup directory are maintained at the management node. The older copy is overwritten when a next Unified Management backup or autobackup takes place.

Unified Management backup is stored at the default backup location `/var/cisco/insight_backup/insight_backup_<release_tag>_<date>_<time>`. If you want to take a backup of Unified Management at a different location use `-backupdir/-b` option from `bootstrap_insight`; details of which are provided later in this section.

Unified Management UI triggers an autobackup whenever it detects an operation relating to MySQL database entry to preserve the latest state of Unified Management.



Note Unified Management backup is not allowed after an update. Update is an intermediate stage between rollback and commit. Any change that is made relating to MySQL database entry after an update from UM UI is not backed up.

Autobackup Unified Management

If there is a change, Unified Management Installation automatically run a daemon process to take the autobackup.

Live status of the process is determined by checking the log located at `/var/log/insight/insight_autobackup/insight_autobackup.logs` or `systemctl status insight-autobackup`.



Note Max of 10-log files of size 1024*1024 are maintained in the directory.

Following are the scenarios where autobackup is initiated:

Unified Management Operation	Auto-backup Performed
Adding or Deleting POD	Yes
Changing POD REST Password and Certificate	Yes
Add/Edit/Delete all types of users	Yes
Add/Edit/Delete Roles	Yes
Modify User and Role association	Yes
Revoking or Adding user permission	Yes
Log in or Logout	No
Context Switching	No
Change User Password	Yes

Step 1 To check the status of the Unified Management perform the following steps:

```
systemctl status insight-autobackup
insight-autobackup.service - Insight Autobackup Service
  Loaded: loaded (/usr/lib/systemd/system/insight-autobackup.service; enabled; vendor preset:
disabled)
  Active: active (running) since Wed 2017-08-30 01:17:18 PDT; 19s ago
  Main PID: 19949 (python)
  Memory: 12.4M
  CGroup: /system.slice/insight-autobackup.service
          └─19949 /usr/bin/python /root/<installer-tag>/insight/playbooks/../../insight_autobackup.py
```

Step 2 To stop Unified Management autobackup do the following:

```
systemctl stop insight-autobackup
insight-autobackup.service - Insight Autobackup Service
  Loaded: loaded (/usr/lib/systemd/system/insight-autobackup.service; enabled; vendor preset:
disabled)
  Active: inactive (dead) since Mon 2017-09-04 00:43:43 PDT; 5s ago
  Process: 19993 ExecStop=/bin/kill ${MAINPID} (code=exited, status=0/SUCCESS)
  Main PID: 19984
  Memory: 56.0K
  CGroup: /system.slice/insight-autobackup.service
```

Step 3 The following are the steps to start Unified Management autobackup:

```
systemctl start insight-autobackup
insight-autobackup.service - Insight Autobackup Service
  Loaded: loaded (/usr/lib/systemd/system/insight-autobackup.service; enabled; vendor preset:
disabled)
  Active: active (running) since Wed 2017-08-30 01:17:18 PDT; 19s ago
  Main PID: 19949 (python)
  Memory: 12.4M
```

```
CGroup: /system.slice/insight-autobackup.service
└─19949 /usr/bin/python /root/<installer-tag>/insight/playbooks/./insight_autobackup.py
```

Step 4 The way Unified Management works is as follows:

1. Install

- As soon as galera db and Unified Management containers are up the script will be invoked.
- Log dir : tailf /var/log/insight/insight_autobackup_logs/insight_autobackup.log.
- It has a 10-seconds pulse which tells if the service is up or not.
 - [2017-09-04 00:49:01,504] INFO [Insight Autobackup] Insight Autobackup Service Running.
 - [2017-09-04 00:49:11,514] INFO [Insight Autobackup] Insight Autobackup Service Running.
 - [2017-09-04 00:49:21,525] INFO [Insight Autobackup] Insight Autobackup Service Running.
- If there is any change it takes a backup (time to check Sql diff is 30 seconds).
- It creates "rbac_latest.sql" and "insight_latest.tar.gz" and dump in the latest backup dir.
- During restore the bootstrap script checks if "rbac_latest.sql" or "insight_latest.tar.gz" is present in the backup dir.

2. Update

- During update bootstrap insight does not support backup.
- Autobackup service would be terminated and no backup would be maintained in the intermediate state.

3. Rollback

- Script are invoked again from the previous workspace.

4. Commit

- Script are invoked again from the new workspace.

5. Uninstall

- Service files are deleted.
- Log directory remains as the same.

Back Up Unified Management at Default Back Up Location

Step 1 Launch an SSH session to Cisco Unified Management management node and follow steps:

```
# cd <insight-ws>
#./bootstrap_insight.py -help

usage: bootstrap_insight.py [-h] --action ACTION
                             [--regenerate_secrets] [--setpassword]
                             [--file INSIGHTSETUPDATA] [--keep] [--verbose]
```

```

                                [--backupdir BACKUPDIR] [-y]

Insight install setup helper.
optional arguments:
  -h, --help                show this help message and exit
  --action ACTION, -a ACTION
                            install - Install Insight UI
                            install-status - Display Insight Install Status
reconfigure - Reconfigure Insight DB password or TLS                Certificate
                            update - Update Insight UI
                            update-status - Display Insight Update Status
                            rollback - Rollback Insight UI update
                            commit - Commit Insight UI update
                            backup - Backup Insight UI
                            uninstall - Uninstall Insight UI
  --regenerate_secrets, -r
                            System generated INSIGHT_DB_PASSWORD
  --setpassword, -s         User supplied INSIGHT_DB_PASSWORD,
  --file INSIGHTSETUPDATA, -f INSIGHTSETUPDATA
                            Location of insight_setup_data.yaml
  --keep, -k                Preserve Insight artifacts during uninstall
  --verbose, -v             Verbose on/off
  --backupdir BACKUPDIR, -b BACKUPDIR
                            Path to backup Insight
  -y, --yes                 Option to skip reconfigure or uninstall steps without prompt

```

Step 2 Run the bootstrap command to view the Cisco VIM Unified Management backup details:

```

# ./bootstrap_insight.py -a backup
VIM Insight backup logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log

Cisco VIM Insight backup Info!
+-----+-----+-----+-----+
| Description          | Status| Details
+-----+-----+-----+-----+
| Insight backup Status| PASS  | Backup done @
|                      |       | /var/cisco/insight_backup/insight_backup_<release_tag>_<date_time>|
+-----+-----+-----+-----+
Done with VIM Insight backup!

```

Backup Unified Management at user defined backup location

Step 1 Launch a SSH session to Cisco Unified Management management node and follow the below steps:

```

# cd <insight-ws>
# ./bootstrap_insight.py -help
usage: bootstrap_insight.py [-h] --action ACTION
                             [--regenerate_secrets] [--setpassword]
                             [--file INSIGHTSETUPDATA] [--keep] [--verbose]
                             [--backupdir BACKUPDIR] [-y]

Insight install setup helper.
optional arguments:
  -h, --help                show this help message and exit
  --action ACTION, -a ACTION

```

```

        install - Install Insight UI
        install-status - Display Insight Install Status
reconfigure - Reconfigure Insight DB password or TLS                                Certificate
        update - Update Insight UI
        update-status - Display Insight Update Status
        rollback - Rollback Insight UI update
        commit - Commit Insight UI update
        backup - Backup Insight UI
        uninstall - Uninstall Insight UI
--regenerate_secrets, -r
        System generated INSIGHT_DB_PASSWORD
--setpassword, -s
        User supplied INSIGHT_DB_PASSWORD,
--file INSIGHTSETUPDATA, -f INSIGHTSETUPDATA
        Location of insight_setup_data.yaml
--keep, -k
        Preserve Insight artifacts during uninstall
--verbose, -v
        Verbose on/off
--backupdir BACKUPDIR, -b BACKUPDIR
        Path to backup Insight
-y, --yes
        Option to skip reconfigure or uninstall steps without prompt

```

Step 2 Run the following command to view the Cisco VIM Unified Management backup details:

```

# ./bootstrap_insight.py -a backup --backupdir <user_defined_path>
VIM Insight backup logs are at: /var/log/insight/<bootstrap_insight_<date>_<time>.log

```

```

Cisco VIM Insight backup Info!
-----+-----+-----+
| Description          | Status | Details          |
+-----+-----+-----+
| Insight backup Status | PASS   | Backup done @ <user_defined_path> |
+-----+-----+-----+
Done with VIM Insight backup!

```

What to do next

Copy the backup directory to a remote server using rsync to recover the Insight later. Cisco recommends you to copy backup directory using rsync as it preserves the permissions of the files.

For example, to copy the backup directory to the remote server 20.0.0.5 /var/cisco/insight_backup/directory, execute the following command sequence: .

```

rsync -e ssh -go -rtvpX --numeric-ids
/var/cisco/insight_backup/insight_backup_2.1.5_2017-01-09_14-04-38
root@20.0.0.5:/var/cisco/insight_backup/

```

On the remote server, protect the backup directory for any unauthorized access, as the backup files may contain sensitive information

Restoring the Management Node

As an administrator, you have to reimage the management node with the same ISO version when the backup is performed, before initiating the restore operation. Restore fails when there is a version mismatch.




Note Version checking is available only for offline installation.

As part of the restore operation, system checks for the management node's IP address information to match the prior configuration. Logs are cached on the control, compute, and storage nodes from the moment of the management node fails until its restoration.

If you are using Cisco VIM Unified Management (in Tech Preview), in the same management node, you have to rebootstrap it for installation. During installation, RBAC and Pod registration information is lost, hence it is advised to make a note of the RBAC and Pod information.

Figure 28: Cisco NFVI Management Node Restore Operation



Before you begin

Ensure that you have the `br_mgmt` and `br_api` IP addresses of the failed management node.

- Step 1** Reimage the management node with the ISO version with which you want to restore the node, and with the same IP address that is used before the failure of the node.
- Step 2** Navigate to `/var/cisco/directory` at the remote server where the backup folder is copied during the backup operation. Execute `./check_integrity` to verify if the backup is not corrupted or modified.
- Step 3** Copy the backup file to the `/var/cisco/directory` of the reimaged management node.
- For example, to copy the backup folder from the remote host `20.0.0.5` to the management node `/var/cisco/directory`, execute the following command sequence:
- ```
rsync -e ssh -go -rtvpX --numeric-ids root@20.0.0.5:/var/cisco/backup_2017-01-09_14-04-38 /var/cisco/
```
- Step 4** Navigate to the backup folder and execute the following command to verify if the backup is not corrupted or modified.
- ```
# cd /var/cisco/backup_<date-time>
# ./check-integrity
```
- Step 5** In `/var/cisco/backup_<date-time>` folder, execute the following command:
- ```
/var/cisco/backup_<date-time> # ./restore
```
- The restore operation takes around 45 minutes.
- Step 6** Before restoration, the restore script performs validation of the backup folder. If validation fails, restore operation is halted and an error message is displayed. The script also verifies the last performed backup folder in the Management Node, and if any defects are detected, the you does confirm to proceed with restore operation.

```

...
2017-02-02 21:25:23 INFO Starting Cisco VIM restore...
2017-02-02 21:25:23 INFO Cisco VIM restore: estimated run time is approx. 45 mins...
2017-02-02 21:25:23 INFO Please see progress log for restore at
/var/log/mercury/installer/restore_2017-02-02_21:25:23.log
2017-02-02 21:25:27 ERROR Error: Backup id is not the one expected
Error: Found hashID file only in controller(s): j10-controller-2, j10-controller-3
Management backup files are ok (as per j10-controller-2)
Management backup files are ok (as per j10-controller-3)
The management node changed after the last backup was stored. Do you still want to proceed restoring
this management node? [Y/n] y
2017-02-02 22:17:55 INFO Workspace restored to /root/installer-6518
2017-02-02 22:17:55 INFO Cisco VIM restore: Executing restore playbook ...
2017-02-02 22:18:47 INFO Cisco VIM restore: Executing bootstrap playbook ...

```

**Note** The default behavior is to continue by keying **Return** or **Y**. Keying **N** terminates the restore operation.

```

...
2017-02-02 21:25:23 INFO Starting Cisco VIM restore...
2017-02-02 21:25:23 INFO Cisco VIM restore: estimated run time is approx. 45 mins...
2017-02-02 21:25:23 INFO Please see progress log for restore at
/var/log/mercury/installer/restore_2017-02-02_21:25:23.log
2017-02-02 21:25:27 ERROR Error: Backup id is not the one expected
Error: Found hashID file only in controller(s): j10-controller-2, j10-controller-3
Management backup files are ok (as per j10-controller-2)
Management backup files are ok (as per j10-controller-3)
The management node changed after the last backup was stored. Do you still want to proceed restoring
this management node? [Y/n] n
Aborting the restore operation as per user request

```

Once, restore operation ends, several health check points are automatically executed and the summary of results for that particular cloud availability is displayed.

**Step 7** Run the following checks manually to verify the status of the restore:

- Check the status of the REST API server:

```

cd installer-<tagid>/tools
./restapi.py -a status
Status of the REST API Server: active (running) since Thu 2016-08-18 09:15:39 UTC; 9h ago
REST API launch directory: /root/installer-<tagid>/

```

- Check the setup\_data and runtime consistency of the management node:

```

cd installer-<tagid>/; ciscovim run --perform 1,3 -y

```

- Execute the cloud sanity command:

```

cd installer-<tagid>/tools
./cloud_sanity.py -c all

```

## Management Node Autobackup

After the successful completion of certain Pod management operations, a backup of the management node is performed automatically. Only one copy of the autobackup folder is kept at /var/cisco/ at any given time. Directory format for the autobackup\_<tag>\_<timestamp>.

Following are the list of operations:

- Fresh install of Cisco VIM
- Commit an update
- Replace controller
- Add or Remove compute nodes
- Add or Remove the storage node
- Reconfigure
- NFVIMON

Enabling or disabling the variable `autobackup`, is defined in the `setup_data.yaml` file. It is enabled by default. Add the following `setup-data.yaml` file snippet:

```
#####
AutoBackup configuration
#####
#Default is True
#autobackup: True or False
```

The following tables shows when an auto-backup is performed during update or rollback or commit.

| POD operation                  | Autobackup performed |
|--------------------------------|----------------------|
| Update                         | No                   |
| Rollback                       | No                   |
| Commit                         | Yes                  |
| Update fail with auto rollback | No                   |

After creating a successful autobackup folder, you can copy it to an external server for later restoration as mentioned in [Restoring the Management Node, on page 357](#).

During the autobackup, if **Forwarding ELK Logs to the External Syslog server** option is enabled, the ElasticSearch database will not be maintained and the ELK Logs will not be recovered after restoring the management node.

## Managing Cisco VIM Software Hub

Cisco VIM Software Hub helps mitigate the need to ship USBs across different pods during installing or updating Cisco VIM. To ensure the long-term viability of Cisco VIM Software Hub, it is designed to handle the following Day 2 scenarios:

- [Updating Cisco VIM Software Hub TLS Certificate and Registry Credentials, on page 361](#)
- [Cisco VIM Software Hub Server Backup and Restore, on page 361](#)
- [Resolving Low Disk Space, on page 363](#)
- [Manually Updating Packages, on page 364](#)

## Updating Cisco VIM Software Hub TLS Certificate and Registry Credentials

Before installing the release artifacts from the Cisco VIM Software Hub server, you must provide a valid TLS certificate and Cisco VIM Software Hub registry credentials in the `sds_setup_data.yaml` file. Taking into account the security policies of an organization, Cisco VIM Software Hub allows you to update the TLS certificate and registry credentials on the Cisco VIM Software Hub server as required.

**Step 1** Navigate to the last installed release workspace using the `ls -lrt` command.

**Step 2** Replace the TLS certificate in the `openstack-configs` directory.

**Step 3** Modify the credentials in the `sds_setup_data.yaml` file.

**Step 4** Run the following command for the changes to take effect:

```
cd /root/cvim_sds-<last-tag> # directory of last installed release and execute the following command.
./sds_runner/runner.py
```

This operation validates the changes in the `sds_setup_data.yaml` file and the new TLS certificate. It reconfigures the Cisco VIM Software Hub server components with this new information.

**Note** The Cisco VIM Software Hub registry credentials of the pods that rely on Cisco VIM Software Hub are also reconfigured.

## Cisco VIM Software Hub Server Backup and Restore

Cisco VIM Software Hub triggers an autobackup operation when a new Cisco VIM release is installed on the Cisco VIM Software Hub server. It takes a backup of the relevant files from the Cisco VIM Software Hub server, and saves it in the following location on the Cisco VIM Software Hub server:

```
directory /var/cisco/autobackup_<tag>_<date-time>
```

Only the latest two backup directories are maintained on Cisco VIM Software Hub. The older copy is overwritten when the next autobackup operation is triggered. If you want to use an older backup directory for a restore operation later, you need to save it to another location before it is overwritten. You can use the `rsync` or `scp` commands to save it to an RHEL7/CentOS based system, which is outside the Cisco VIM Software Hub server.

### Checking Integrity of Autobackup Files

You can use the script provided in the autobackup directory to check the integrity of the autobackup files after using the `rsync` or `scp` commands.

#### Before you begin

Ensure that the following packages are installed on the backup server using `yum`:

- `python-prettytable`
- `python-jinja2`
- `python-babel`
- `python-markupsafe`

- python-setuptools
- pytz

- 
- Step 1** Navigate to the autobackup directory.
- Step 2** Execute the following command to run the script:

```
./check_integrity
```

---

## Restoring Cisco VIM Software Hub from Backup

An Cisco VIM Software Hub restore operation is usually performed when the original Cisco VIM Software Hub server is being replaced by a new one.

---

- Step 1** Re-image the Cisco VIM Software Hub server with the ISO version with which you want to restore the node, and with the same IP address that is used before the failure of the node.
- Step 2** Navigate to the location where the backup directory is copied during the backup operation.
- Step 3** Verify the integrity of the backup files as described in [Checking Integrity of Autobackup Files, on page 361](#).
- Step 4** Copy the backup file to the directory of the re-imaged Cisco VIM Software Hub node.

For example, you can copy the backup directory from the remote host 20.0.0.5 to the Cisco VIM Software Hub node directory `/var/cisco/` as follows:

```
rsync -e ssh -go -rtvpX --numeric-ids root@20.0.0.5:/var/cisco/autobackup_2017-01-09_14-04-38 /var/cisco/
```

- Step 5** Navigate to the backup directory and execute the following command to verify if the backup is not corrupted or modified.

```
cd /var/cisco/autobackup_<tag>_<date-time>
./check-integrity
```

- Step 6** In the `/var/cisco/autobackup_<tag>_<date-time>` directory, execute the following commands:

```
cd /var/cisco/backup_<date-time>
./restore
```

It may take about 45 minutes for the restore operation to complete.

**Note** Before restoring a backup directory, the restore script validates the backup directory. If the validation fails, the restore operation is interrupted and an error message is displayed. The restore script also verifies the latest backup directory in the Cisco VIM Software Hub Node. If defects are detected, you need to confirm whether you want to proceed with the restore operation.

For example:

```
2017-02-02 21:25:23 INFO Starting Cisco VIM restore...
2017-02-02 21:25:23 INFO Cisco VIM restore: estimated run time is approx. 45 mins...
2017-02-02 21:25:23 INFO Please see progress log for restore at
/var/log/mercury/installer/restore_2017-02-02_21:25:23.log
2017-02-02 21:25:27 ERROR Error: Backup id is not the one expected
Error: Found hashID file only in controller(s): j10-controller-2, j10-controller-3 Management backup
files are ok (as per j10controller-2)
Management backup files are ok (as per j10-controller-3)
The management node changed after the last backup was stored. Do you still want to proceed restoring
this management node? [Y/n] y
```

```
2017-02-02 22:17:55 INFO Workspace restored to /root/installer-6518
2017-02-02 22:17:55 INFO Cisco VIM restore: Executing restore playbook ...
2017-02-02 22:18:47 INFO Cisco VIM restore: Executing bootstrap playbook ...
```

**Note** To continue the restore operation, you can press the **Enter** key or the **Y** key. If you want to abort the restore operation, you need to press the **N** key.

```
2017-02-02 21:25:23 INFO Starting Cisco VIM restore...
2017-02-02 21:25:23 INFO Cisco VIM restore: estimated run time is approx. 45 mins...
2017-02-02 21:25:23 INFO Please see progress log for restore at
/var/log/mercury/installer/restore_2017-02-02_21:25:23.log
2017-02-02 21:25:27 ERROR Error: Backup id is not the one expected
Error: Found hashID file only in controller(s): j10-controller-2, j10-controller-3 Management backup
files are ok (as per j10controller-2)
Management backup files are ok (as per j10-controller-3)
The management node changed after the last backup was stored. Do you still want to proceed restoring
this management node? [
Y/n] n
Aborting the restore operation as per user request
```

## Resolving Low Disk Space

Installing releases on Cisco VIM Software Hub server is not allowed if the free disk space is less than 20%. Hence, a utility to remove docker images from the container registry running on the Cisco VIM Software Hub server is provided. You can find the cleanup script at the following location:

```
/root/cvim_sds-<last-tag>/sds/registry_cleanup.py
```

Example of running the cleanup script:

```
./registry_cleanup.py -h
usage: registry_cleanup.py [-h] (--list | --delete DELETE | --unused_tags)
 [-u USERNAME] [-p PASSWORD] [-r REGISTRY]
```

List/Delete image tags in the registry

optional arguments:

```
-h, --help Show this help message and exit
--list List Image Tags in Registry
--delete DELETE Delete Images of provided tags from registry
--unused_tags List unused Tags in SDS registry
-u USERNAME, --username USERNAME
 Registry Username
-p PASSWORD, --password PASSWORD
 Registry Password
-r REGISTRY, --registry REGISTRY
 Registry URL
```

The cleanup script requires three mandatory parameters, namely, Registry URL, Registry username, and Registry password. The script supports the following three options:

- **List Image Tags**—The option lists all the images and corresponding tags present in the docker registry.
- **Unused Tags**—This option lists all the releases present on the Cisco VIM Software Hub server but are not used by any of the Cisco VIM pods. By default, the pods are registered with the Cisco VIM Software Hub server. When a pod is installed, updated, roll backed, or upgraded, the release information is sent to Cisco VIM Software Hub. You can use this command to identify the releases that can be safely removed from the Cisco VIM Software Hub server.

- **Delete Tags**—You can specify the releases that you want to remove from the docker registry. The script removes these images and frees the disk space.

## Manually Updating Packages

Cisco VIM Software Hub installs repositories inside docker containers so that all the packages to be installed are obtained from those repositories. These repositories are updated when you install a later version of Cisco VIM release on the Cisco VIM Software Hub server. Once the repositories are updated, all the packages, except httpd package and its dependencies are updated. Updating httpd is deferred because when httpd is updated, all downstream connections are disrupted thereby requiring you to restart the Cisco VIM pod install.

To update httpd and its dependent packages, you can use the update script found in the tools directory. Ensure that you run this script during the maintenance phase so that non of the Cisco VIM pods are currently attempting to get artifacts from the Cisco VIM Software Hub server.

Run the following command to execute the update script:

```
cd /root/cvim_sds-<last-tag> # directory of last installed release and execute the following
command.
./update_httpd.sh
```



# CHAPTER 13

## Troubleshooting

The following topics describe various Cisco NFVI troubleshooting operations:

- [Displaying Cisco NFVI Node Names and IP Addresses, on page 365](#)
- [Verifying Cisco NFVI Node Interface Configurations, on page 366](#)
- [Displaying Cisco NFVI Node Network Configuration Files, on page 367](#)
- [Viewing Cisco NFVI Node Interface Bond Configuration Files, on page 368](#)
- [Viewing Cisco NFVI Node Route Information, on page 368](#)
- [Viewing Linux Network Namespace Route Information, on page 369](#)
- [Prior to Remove Storage Operation, on page 369](#)
- [Troubleshooting Cisco NFVI, on page 371](#)
- [Management Node Recovery Scenarios, on page 376](#)
- [Recovering Compute Node Scenario, on page 385](#)
- [Running the Cisco VIM Technical Support Tool, on page 387](#)
- [Tech-Support Configuration File, on page 388](#)
- [Tech-Support When Servers Are Offline, on page 391](#)
- [Disk-Maintenance Tool to Manage Physical Drives, on page 391](#)
- [OSD-Maintenance Tool, on page 394](#)
- [Utility to Resolve Cisco VIM Hardware Validation Failures, on page 397](#)
- [Cisco VIM Client Debug Option, on page 399](#)

## Displaying Cisco NFVI Node Names and IP Addresses

Complete the following steps to display the Cisco NFVI node names and IP addresses.

**Step 1** Log into the Cisco NFVI build node.

**Step 2** The `openstack-configs/mercury_servers_info` file displays the node name and the address as follows.

```
more openstack-configs/mercury_servers_info Total nodes: 5
Controller nodes: 3
+-----+-----+-----+-----+-----+-----+
| Server | CIMC | Management | Provision | Tenant | Storage |
+-----+-----+-----+-----+-----+-----+
test-c-control-1	10.10.223.13	10.11.223.22	10.11.223.22	169.254.133.102	None
test-c-control-3	10.10.223.9	10.11.223.23	10.11.223.23	169.254.133.103	None
```

```

test-c-control-2	10.10.223.10	10.11.223.24	10.11.223.24	169.254.133.104	None
+-----+-----+-----+-----+-----+-----+-----+					
Compute nodes: 2					
+-----+-----+-----+-----+-----+-----+-----+					
Server	CIMC	Management	Provision	Tenant	Storage
+-----+-----+-----+-----+-----+-----+-----+					
test-c-compute-1	10.10.223.11	10.11.223.25	10.11.223.25	169.254.133.105	None
test-c-compute-2	10.10.223.12	10.11.223.26	10.11.223.26	169.254.133.106	None
+

```

**Note** During the Cisco NFVI deployment, SSH public keys for each node are added to `.../.ssh/authorized_keys`, so you should be able to log in from the build node into each of the Cisco NFVI nodes without passwords. If, for some reason you do need account information, see the `openstack-configs/secrets.yaml` file on the build node.

## Verifying Cisco NFVI Node Interface Configurations

Complete the following steps to verify the interface configurations of Cisco NFVI nodes:

**Step 1** SSH into the target node, for example, one of the Cisco VIM controllers:

```

[root@mgmt-node~]# ssh root@control-server-1
[root@control-server-1 ~]#

```

**Step 2** Enter the `ip a` command to get a list of all interfaces on the node:

```

[root@control-server-1 ~]# ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN link/loopback 00:00:00:00:00:00
 brd 00:00:00:00:00:00
 inet 127.0.0.1/8 scope host lo
 valid_lft forever preferred_lft forever
2: enp8s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP qlen 1000 link/ether
 54:a2:74:7d:42:1d brd ff:ff:ff:ff:ff:ff
3: enp9s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc mq state UP qlen 1000 link/ether
 54:a2:74:7d:42:1e brd ff:ff:ff:ff:ff:ff
4: mx0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master mx state UP qlen 1000
 link/ether 54:a2:74:7d:42:21 brd ff:ff:ff:ff:ff:ff
5: mx1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master mx state UP qlen 1000
 link/ether 54:a2:74:7d:42:21 brd ff:ff:ff:ff:ff:ff
6: t0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master t state UP qlen 1000 link/ether
 54:a2:74:7d:42:23 brd ff:ff:ff:ff:ff:ff
7: t1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master t state UP qlen 1000 link/ether
 54:a2:74:7d:42:23 brd ff:ff:ff:ff:ff:ff
8: e0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master e state UP qlen 1000 link/ether
 54:a2:74:7d:42:25 brd ff:ff:ff:ff:ff:ff
9: e1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master e state UP qlen 1000 link/ether
 54:a2:74:7d:42:25 brd ff:ff:ff:ff:ff:ff
10: p0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master p state UP qlen 1000 link/ether
 54:a2:74:7d:42:27 brd ff:ff:ff:ff:ff:ff
11: p1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master p state UP qlen 1000 link/ether

```

```

54:a2:74:7d:42:27 brd ff:ff:ff:ff:ff:ff
12: a0: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master a state UP qlen 1000 link/ether
54:a2:74:7d:42:29 brd ff:ff:ff:ff:ff:ff
13: a1: <BROADCAST,MULTICAST,SLAVE,UP,LOWER_UP> mtu 1500 qdisc mq master a state UP qlen 1000

link/ether 54:a2:74:7d:42:29 brd ff:ff:ff:ff:ff:ff
14: bond0: <BROADCAST,MULTICAST,MASTER> mtu 1500 qdisc noop state DOWN link/ether 4a:2e:2a:9e:01:d1
brd ff:ff:ff:ff:ff:ff
15: a: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue master br_api state UP link/ether
54:a2:74:7d:42:29 brd ff:ff:ff:ff:ff:ff
16: br_api: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP link/ether
54:a2:74:7d:42:29 brd ff:ff:ff:ff:ff:ff
17: e: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP link/ether
54:a2:74:7d:42:25 brd ff:ff:ff:ff:ff:ff
18: mx: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue master br_mgmt state UP
link/ether 54:a2:74:7d:42:21 brd ff:ff:ff:ff:ff:ff
19: br_mgmt: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP link/ether
54:a2:74:7d:42:21 brd ff:ff:ff:ff:ff:ff
inet 10.23.221.41/28 brd 10.23.221.47 scope global br_mgmt valid_lft forever preferred_lft forever
20: p: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP link/ether
54:a2:74:7d:42:27 brd ff:ff:ff:ff:ff:ff
21: t: <BROADCAST,MULTICAST,MASTER,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP link/ether
54:a2:74:7d:42:23 brd ff:ff:ff:ff:ff:ff
inet 17.16.3.8/24 brd 17.16.3.255 scope global t valid_lft forever preferred_lft forever
22: docker0: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc noqueue state DOWN link/ether
02:42:70:f6:8b:da brd ff:ff:ff:ff:ff:ff
inet 172.17.42.1/16 scope global docker0 valid_lft forever preferred_lft forever
24: mgmt-out@if23: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast master br_mgmt state
UP qlen 1000
link/ether 5a:73:51:af:e5:e7 brd ff:ff:ff:ff:ff:ff link-netnsid 0
26: api-out@if25: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast master br_api state UP
qlen 1000
link/ether 6a:a6:fd:70:01:f9 brd ff:ff:ff:ff:ff:ff link-netnsid 0

```

## Displaying Cisco NFVI Node Network Configuration Files

Complete the following steps to view a Cisco NFVI node network configuration files:

**Step 1** SSH into the target node, for example, one of the Cisco VIM controllers:

```

[root@mgmt-node~]# ssh root@control-server-1
[root@control-server-1 ~]#

```

**Step 2** List all of the network configuration files in the /etc/sysconfig/network-scripts directory, for example:

```

[root@control-server-1 ~]# ls /etc/sysconfig/network-scripts/
ifcfg-a ifcfg-enp15s0 ifcfg-mx0 ifdown-ib ifup ifup-ppp
ifcfg-a0 ifcfg-enp16s0 ifcfg-mx1 ifdown-ippv6 ifup-aliases ifup-routes
ifcfg-a1 ifcfg-enp17s0 ifcfg-p ifdown-ipv6 ifup-bnep ifup-sit
ifcfg-br_api ifcfg-enp18s0 ifcfg-p0 ifdown-isdn ifup-eth ifup-Team
ifcfg-br_mgmt ifcfg-enp19s0 ifcfg-p1 ifdown-post ifup-ib ifup-TeamPort
ifcfg-e ifcfg-enp20s0 ifcfg-t ifdown-ppp ifup-ippv6 ifup-tunnel
ifcfg-e0 ifcfg-enp21s0 ifcfg-t0 ifdown-routes ifup-ipv6 ifup-wireless
ifcfg-e1 ifcfg-enp8s0 ifcfg-t1 ifdown-sit ifup-isdn init.ipv6-global
ifcfg-enp12s0 ifcfg-enp9s0 ifdown ifdown-Team ifup-plip network-functions

```

```
ifcfg-enp13s0 ifcfg-lo ifdown-bnep ifdown-TeamPort ifup-plusb network-functions-ipv6
ifcfg-enp14s0 ifcfg-mx ifdown-eth ifdown-tunnel ifup-post
```

## Viewing Cisco NFVI Node Interface Bond Configuration Files

Complete the following steps to view the Cisco NFVI node interface bond configuration files:

**Step 1** SSH into the target node, for example, one of the Cisco VIM controllers:

```
[root@mgmt-node~]# ssh root@control-server-1
[root@control-server-1 ~]#
```

**Step 2** List all of the network bond configuration files in the `/proc/net/bonding/` directory:

```
[root@control-server-1 ~]# ls /proc/net/bonding/
a bond0 e mx p t
```

**Step 3** To view more information about a particular bond configuration, enter:

```
[root@control-server-1 ~]# more /proc/net/bonding/a
Ethernet Channel Bonding Driver: v3.7.1 (April 27, 2011)
```

```
Bonding Mode: load balancing (xor)
Transmit Hash Policy: layer3+4 (1)
MII Status: up
MII Polling Interval (ms): 100
Up Delay (ms): 0
Down Delay (ms): 0
```

```
Slave Interface: a0
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 1
Permanent HW addr: 54:a2:74:7d:42:29
Slave queue ID: 0
```

```
Slave Interface: a1
MII Status: up
Speed: 10000 Mbps
Duplex: full
Link Failure Count: 2
Permanent HW addr: 54:a2:74:7d:42:2a
Slave queue ID: 0
```

## Viewing Cisco NFVI Node Route Information

Complete the following steps to view Cisco NFVI node route information. Note that this is not the HAProxy container running on the controller. The default gateway should point to the gateway on the management network using the `br_mgmt` bridge.

**Step 1** SSH into the target node, for example, one of the Cisco VIM controllers:

```
[root@mgmt-node~]# ssh root@control-server-1
[root@control-server-1 ~]#
```

**Step 2** View the routing table (verify the default gateway) of the Cisco NFVI node:

```
[root@control-server-1 ~]# route -n
Kernel IP routing table
Destination Gateway Genmask Flags Metric Ref Use Iface
0.0.0.0 10.23.221.33 0.0.0.0 UG 0 0 0 br_mgmt
10.23.221.32 0.0.0.0 255.255.255.240 U 0 0 0 br_mgmt
17.16.3.0 0.0.0.0 255.255.255.0 U 0 0 0 t
169.254.0.0 0.0.0.0 255.255.0.0 U 1016 0 0 br_api
169.254.0.0 0.0.0.0 255.255.0.0 U 1017 0 0 e
169.254.0.0 0.0.0.0 255.255.0.0 U 1019 0 0 br_mgmt
169.254.0.0 0.0.0.0 255.255.0.0 U 1020 0 0 p
169.254.0.0 0.0.0.0 255.255.0.0 U 1021 0 0 t
172.17.0.0 0.0.0.0 255.255.0.0 U 0 0 0 docker0
```

## Viewing Linux Network Namespace Route Information

Complete the following steps to view the route information of the Linux network namespace that the HAProxy container uses on a Cisco NFVI controller node. The default gateway must point to the gateway on the API network using the API interface in the Linux network namespace.

**Step 1** SSH into the target node. For example, one of the Cisco VIM controllers:

```
[root@mgmt-node~]# ssh root@control-server-1
[root@control-server-1 ~]#
```

**Step 2** Enter the `ip netns` command to find the name of the network namespace:

```
[root@control-server-2 ~]# ip netns 17550 (id: 0)
```

**Step 3** Enter the `ip netns exec` command to view the routing table (verify the default gateway) of the Linux network namespace:

```
[root@control-server-2 ~]# ip netns exec 17550 route -n
Kernel IP routing table
Destination Gateway Genmask Flags Metric Ref Use Iface
0.0.0.0 172.29.86.1 0.0.0.0 UG 0 0 0 api
10.23.221.32 0.0.0.0 255.255.255.240 U 0 0 0 mgmt
172.29.86.0 0.0.0.0 255.255.255.0 U 0 0 0 api
```

## Prior to Remove Storage Operation

Upon completion of the pod management operations such as add-storage, the operator has to ensure that any subsequent operation such as remove-storage on the same storage node is done after accounting for all of the

devices and their corresponding OSDs have been marked in the persistent crush map as shown in the output of the ceph osd crush tree.

Execute the following command on the storage node where a remove-storage pod operation is performed, to get a list of all the devices configured for ceph osds:

```
[root@storage-3 ~]$ df | grep -oh ceph-[0-9]*
[root@storage-3 ~]$ df | grep -oh ceph-[0-9]*
ceph-1
ceph-5
ceph-7
ceph-10
```

Login to any of the controller nodes and run the following commands within the ceph mon container:

```
$ cephmon
$ ceph osd crush tree
```

From the json output, locate the storage node to be removed and ensure all of the devices listed for ceph osds have corresponding osd entries for them by running the following commands:

```
{
 "id": -3,
 "name": "storage-3",
 "type": "host",
 "type_id": 1,
 "items": [
 {
 "id": 1,
 "name": "osd.1",
 "type": "osd",
 "type_id": 0,
 "crush_weight": 1.091095,
 "depth": 2
 },
 {
 "id": 5,
 "name": "osd.5",
 "type": "osd",
 "type_id": 0,
 "crush_weight": 1.091095,
 "depth": 2
 },
 {
 "id": 7,
 "name": "osd.7",
 "type": "osd",
 "type_id": 0,
 "crush_weight": 1.091095,
 "depth": 2
 },
 {
 "id": 10,
 "name": "osd.10",
 "type": "osd",
 "type_id": 0,
 "crush_weight": 1.091095,
 "depth": 2
 }
]
},
```

# Troubleshooting Cisco NFVI

The following topics provide Cisco NFVI general troubleshooting procedures.

## Managing CIMC and ISO Installation

When you are remote it is good to map the ISO through the CIMC Mapped vMedia.

To add new mapping:

**Step 1** Click **Server > Remote Presence > Virtual Media > Add New Mapping**.

The screenshot shows a web-based dialog titled "Cisco IMC-Mapped vMedia" with a sub-header "Add New Map". The dialog contains the following fields and controls:

- Volume:** Text input field containing "f".
- Mount Type:** Dropdown menu set to "WWW(HTTP/HTTP)".
- Remote Share:** Text input field containing "http://172.29.172.152/downloads/".
- Remote File:** Text input field containing "buildnode-internal-13130.iso" and a "Browse..." button to the right.
- Mount Options:** Text input field containing "noauto".
- User Name:** Empty text input field.
- Password:** Empty text input field.
- Buttons:** "Save" and "Close" buttons located at the bottom right of the dialog.


**Step 2** Enter the field values such as the Volume, Mount Type, Remote Share, Remote File, User name, and Password.

**Step 3** Click **Save**. The CIMC pulls the ISO directly from the HTTP server.

## Management Node Installation Fails

Management node installation fails if the CIMC is configured for cisco card mode.

Choose the dedicated mode in the following screen:




The selected method that is shown in the preceding screen is the incorrect mode.

## Configuring Boot Order

Management node does not come up post reboot. It must boot from hard drive to check for the actual boot order.

Choose **Server > BIOS > Configure Boot Order > Boot Order**.




## PXE Failure Issue During Baremetal Step

Perform the following steps in case of PXE boot failure:

- Step 1** Check log file `/var/log/mercury/mercury_baremetal_install.log` and connect to failing node CIMC KVM console to find out more on PXE boot failure reason.
- Step 2** Ensure all validations (step 1) and hardware validations (step 3) pass.
- Step 3** Check log file `/var/log/mercury/<UUID>/mercury_baremetal_install.log`.
- Step 4** Connect to KVM console of failing node(s) to find out more on PXE boot failure.
- Step 5** Check L2/L3 network connectivity between failing node(s) and management node.
- Step 6** Check for VPC configuration and port-channel status of failing node(s) and ensure `no lacp suspend-individual` is configured on the port-channel.
- Step 7** Check the actual PXE boot order must not differ from the boot-order configured.
- Step 8** Perform `tcpdump` on the management node interface `br_mgmt` to watch for UDP port 67 (dhcp) or UDP port 69 (tftp) `tcpdump -I br_mgmt port 67 or port 69 #` on the management node.
- Step 9** Perform `tcpdump` on the management node management interface `br_mgmt` on TCP 80 `tcpdump -I br_mgmt port 80 #` on the management node.
- Step 10** Check the apache log to watch the management IP address of failing node (if static allocated) `tail -f /var/log/cobblerhttpd/access_log #` on the management node.
- Step 11** For Authorization Required error messages during bare metal (Step 4) with CIMC operations such as hardware validations or cleaning up vNIC, check whether the maximum allowed simultaneous connection (4) are in use. All four connections are run when the 3rd party application monitoring CIMC does not properly close CIMC. This makes CiscoVIM installer not to log in using `xmlapi` with valid username and password. Check Cisco IMC logs on CIMC (Server > Faults and Logs > Cisco IMC Logs) for the reason why user was denied the access (maximum session, incorrect credentials.). The workaround is to disable 3rd party monitoring, wait at least 10 minutes and then perform CiscoVIM operations.
- Step 12** In case none of the nodes are getting DHCP address; DHCP requests arrive at the management node but no response goes out, then check CIMC VIC adapter settings. Server > Inventory > Cisco VIC Adapters > vNICs | VLAN & VLAN Mode. Ensure the VLAN (both id and mode) configured does not match with that of N9K switch

| Option | Description      |
|--------|------------------|
| CIMC   | Trunk:None       |
| Switch | Access:vlan_mgmt |



The following topics provide Cisco NFVI general troubleshooting procedures.

### Container Download Problems

1. Check installer logs log file `/var/log/mercury/mercury_buildorchestration.log` for any build node orchestration failures including stuck "registry-Populate local registry". Downloading the Docker container from your management node can be slow.
2. Check the network connectivity between the management node and the remote registry in `defaults.yaml` on the management node (`grep "^registry:" openstack-configs/defaults.yaml`).
3. Verify valid remote registry credentials are defined in `setup_data.yaml` file.
4. A proxy server is required to pull the container images from remote registry. If a proxy is required, exclude all IP addresses for your setup including management node.

### Cisco IMC Connection Problems during Bare Metal Installation

The cause may be Cisco IMC has too many connections, so the installer cannot connect to it. Clear the connections by logging into your Cisco IMC, going into the Admin->Sessions tab and clearing the connections.

### API VIP Connection Problems

Verify the active HAProxy container is running in one of the controller nodes. On that controller within the HAProxy container namespace verify the IP address is assigned to the API interface. Also, verify that your ToR and the network infrastructure connecting your ToR is provisioned with API network segment VLAN.

### HAProxy Services Downtime after Initial Installation or HA Failover

The HAProxy web interface can be accessed on TCP port 1936

```
http://<external_lb_vip_address>:1936/
Username: haproxy
Password: <HAPROXY_PASSWORD> from secrets.yaml file
```

After initial installation, the HAProxy web interface can report to several OpenStack services with downtime depending upon when that OpenStack service was installed after HAProxy install. The counters are not synchronized between HAProxy active and standby. After HA proxy failover, the downtime timers can change based on the uptime of new active HAproxy container.

## Management Node Problems

### Service Commands

To identify all the services that are running, enter:

```
$ systemctl -a | grep docker | grep service
 On controller ignore status of:
docker-neutronlb
 On compute ignore status of:
docker-neutronlb, docker-keystone
```

To start a service on a host, enter:

```
$ systemctl start <service_name>
```

To stop a service on a host, enter:

```
$ systemctl stop <service_name>
```

To restart a service on a host, enter:

```
$ systemctl restart <service_name>
```

To check service status on a host, enter:

```
$ systemctl status <service_name>
```

---

## Connecting to Docker Container

---

To connect to the docket container do the following:

```
generally, aliases are created for all containers
use alias to identify those
alias | grep in_container
checking specific alias by name
alias cobbler

check docker containers
alias created by CVIM
dp
list docker containers
docker ps -a
list docker images
docker images

connecting to container
docker exec -it my_cobbler_<tag_id> /bin/bash

connecting to docker container as privileged user
docker exec -it -u root my_cobbler_<tag_id> /bin/bash

systemctl files
systemctl -a | egrep "docker-.*.service"

check specific service
systemctl status mercury-restapi -l
systemctl status docker-vmtmp
```

```
restart specific service
systemctl restart docker-vmtp
```

---


## Management Node Recovery Scenarios

The Cisco NFVI management node hosts the Cisco VIM Rest API service, Cobbler for PXE services, ELK for Logging to Kibana dashboard services and VMTP for the cloud validation. As the maintenance node does not have redundancy, understanding its points of failure and recovery scenarios is important. Managing Node recovery scenarios are described in the following steps.

The management node architecture includes a Cisco UCS C240 M4 server with dual CPU socket. It has a 1-Gbps on-board (LOM) NIC and a 10-Gbps Cisco VIC mLOM. HDDs are used in 8,16, or 24 disk configurations.

The following figure shows the high-level maintenance node of the hardware and software architecture.

Figure 29: Cisco NFVI Management Node Architecture



Different management node hardware or software failures can cause Cisco NFVI service disruptions and outages. Some failed services can be recovered through manual intervention. In cases if the system is operational during a failure, double faults cannot be recoverable.

The following table lists the management node failure scenarios and their recovery options.

Table 18: Management Node Failure Scenarios

| Scenario # | Failure or Trigger                                          | Recoverable? | Operational Impact |
|------------|-------------------------------------------------------------|--------------|--------------------|
| 1          | Failure of 1 or 2 active HDD                                | Yes          | No                 |
| 2          | Simultaneous failure of more than 2 active HDD              | No           | Yes                |
| 3          | Spare HDD failure: 4 spare for 24 HDD; or 2 spare for 8 HDD | Yes          | No                 |

| Scenario # | Failure or Trigger                                            | Recoverable? | Operational Impact                            |
|------------|---------------------------------------------------------------|--------------|-----------------------------------------------|
| 4          | Power outage/hard reboot                                      | Yes          | Yes                                           |
| 5          | Graceful reboot                                               | Yes          | Yes                                           |
| 6          | Docker daemon start failure                                   | Yes          | Yes                                           |
| 7          | Service container (Cobbler, ELK) start failure                | Yes          | Yes                                           |
| 8          | One link failure on bond interface                            | Yes          | No                                            |
| 9          | Two link failures on bond interface                           | Yes          | Yes                                           |
| 10         | REST API service failure                                      | Yes          | No                                            |
| 11         | Graceful reboot with Cisco VIM Unified Management             | Yes          | Yes; CLI alternatives exist during reboot.    |
| 12         | Power outage or hard reboot with Cisco VIM Unified Management | Yes          | Yes                                           |
| 13         | VIM Unified Management Container reinstallation               | Yes          | Yes; CLI alternatives exist during reinstall. |
| 14         | Cisco VIM Unified Management Container reboot                 | Yes          | Yes; CLI alternatives exist during reboot.    |
| 15         | Intel 1350 1Gbps LOM failure                                  | Yes          | Yes                                           |
| 16         | Cisco VIC 1227 10-Gbps mLOM failure                           | Yes          | Yes                                           |
| 17         | DIMM memory failure                                           | Yes          | No                                            |
| 18         | One CPU failure                                               | Yes          | No                                            |

**Scenario 1: Failure of one or two active HDDs**

The management node has either 8,16, or 24-HDDs. The HDDs are configured with RAID 6, which helps to enable data redundancy and storage performance and overcomes any unforeseen HDD failures.

- When 8 HDDs are installed, 7 are active disks and one is spare disk.
- When 16 HDDs are installed, 14 are active disks and two are spare disks.
- When 24 HDDs are installed, 20 are active disks and four are spare disks.

With RAID 6 up, two simultaneous active HDD failures can occur. When an HDD fails, the system begins automatic recovery by moving the spare disk to active state and begins recovering and rebuilding the new active HDD. It takes approximately 4 hours to rebuild the new disk and move to synchronized state. During this operation, the system is fully functional and no impacts are seen. However, you must monitor the system to ensure that more failures do not occur to enter into a double fault situation.

You can use the **storcli** commands to check the disk and RAID state as shown in the following commands:



**Note** Make sure that the node is running with hardware RAID by checking the storcli output and comparing to the one preceding.

```
[root@mgmt-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show
<...snip...>
TOPOLOGY:
=====

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID6 Optl N 4.087 TB dflt N N dflt N N
0 0 - - - RAID6 Optl N 4.087 TB dflt N N dflt N N <== RAID
6 in optimal state
0 0 0 252:1 1 DRIVE Onln N 837.258 GB dflt N N dflt - N
0 0 1 252:2 2 DRIVE Onln N 837.258 GB dflt N N dflt - N
0 0 2 252:3 3 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 3 252:4 4 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 4 252:5 5 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 5 252:6 6 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 6 252:7 7 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 - - 252:8 8 DRIVE DHS - 930.390 GB - - - - N
```

```
<...snip...>
PD LIST:
=====

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:1 1 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U <== all disks
functioning
252:2 2 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U
252:3 3 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:4 4 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:5 5 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:6 6 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:7 7 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:8 8 DHS 0 930.390 GB SAS HDD N N 512B ST91000640SS D
```

```
[root@mgmt-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show
<...snip...>
TOPOLOGY :
=====

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID6 Pdgd N 4.087 TB dflt N N dflt N N <== RAID 6
in degraded state
0 0 - - - RAID6 Dgrd N 4.087 TB dflt N N dflt N N
0 0 0 252:8 8 DRIVE Rbld Y 930.390 GB dflt N N dflt - N
0 0 1 252:2 2 DRIVE Onln N 837.258 GB dflt N N dflt - N
0 0 2 252:3 3 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 3 252:4 4 DRIVE Onln N 930.390 GB dflt N N dflt - N
```

```

0 0 4 252:5 5 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 5 252:6 6 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 6 252:7 7 DRIVE Onln N 930.390 GB dflt N N dflt - N

```

<...snip...>

PD LIST :

=====

```

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:1 1 UGood - 837.258 GB SAS HDD N N 512B ST900MM0006 U <== active disk
in slot 1 disconnected from drive group 0
252:2 2 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U
252:3 3 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:4 4 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:5 5 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:6 6 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:7 7 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:8 8 Rbld 0 930.390 GB SAS HDD N N 512B ST91000640SS U <== spare disk
in slot 8 joined drive group 0 and in rebuilding state

```

```

[root@mgmt-node ~]# /opt/MegaRAID/storcli/storcli64 /c0/e252/s8 show rebuild
Controller = 0
Status = Success
Description = Show Drive Rebuild Status Succeeded.

```

```

Drive-ID Progress% Status Estimated Time Left

/c0/e252/s8 20 In progress 2 Hours 28 Minutes <== spare disk in slot 8 rebuild
status

```

To replace the failed disk and add it back as a spare:

```

[root@mgmt-node ~]# /opt/MegaRAID/storcli/storcli64 /c0/e252/s1 add hotsparedrive dg=0
Controller = 0
Status = Success
Description = Add Hot Spare Succeeded.

```

```

[root@mgmt-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show

```

<...snip...>

TOPOLOGY :

=====

```

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID6 Pdgd N 4.087 TB dflt N N dflt N N
0 0 - - - RAID6 Dgrd N 4.087 TB dflt N N dflt N N
0 0 0 252:8 8 DRIVE Rbld Y 930.390 GB dflt N N dflt - N
0 0 1 252:2 2 DRIVE Onln N 837.258 GB dflt N N dflt - N
0 0 2 252:3 3 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 3 252:4 4 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 4 252:5 5 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 0 5 252:6 6 DRIVE Onln N 930.390 GB dflt N N dflt - N

```

```

0 0 6 252:7 7 DRIVE Onln N 930.390 GB dflt N N dflt - N
0 - - 252:1 1 DRIVE DHS - 837.258 GB - - - - N

```

<...snip...>

PD LIST :  
=====

```

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:1 1 DHS 0 837.258 GB SAS HDD N N 512B ST900MM0006 U <== replacement
 disk added back as spare
252:2 2 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U
252:3 3 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:4 4 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:5 5 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:6 6 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:7 7 Onln 0 930.390 GB SAS HDD N N 512B ST91000640SS U
252:8 8 Rbld 0 930.390 GB SAS HDD N N 512B ST91000640SS U

```

**Scenario 2: Simultaneous failure of more than two active HDDs**

If more than two HDD failures occur at the same time, the management node goes into an unrecoverable failure state because RAID 6 allows for recovery of up to two simultaneous HDD failures. To recover the management node, reinstall the operating system.

**Scenario 3: Spare HDD failure**

When the management node has 24 HDDs, four are designated as spares. Failure of any of the disks does not impact the RAID or system functionality. Cisco recommends replacing these disks when they fail (see the steps in Scenario 1) to serve as standby disks and so when an active disk fails, an auto-rebuild is triggered.

**Scenario 4: Power outage or reboot**

If a power outage or hard system reboot occurs, the system boots up, and come back to operational state. Services running on the management node during down time gets disrupted. See the steps in Scenario 9 for the list of commands to check the services status after recovery.

**Scenario 5: System reboot**

If a graceful system reboot occurs, the system boots up and come back to operational state. Services running on the management node during down time gets disrupted. See the steps in Scenario 9 for the list of commands to check the services status after recovery.

**Scenario 6: Docker daemon start failure**

The management node runs the services using Docker containers. If the Docker daemon fails to come up, it causes services such as ELK, Cobbler, and VMTP to go into down state. You can use the **systemctl** command to check the status of the Docker daemon, for example:

```

systemctl status docker
docker.service - Docker Application Container Engine
Loaded: loaded (/usr/lib/systemd/system/docker.service; enabled; vendor preset: disabled)
Active: active (running) since Mon 2016-08-22 00:33:43 CEST; 21h ago
Docs: http://docs.docker.com
Main PID: 16728 (docker)

```

If the Docker daemon is in down state, use the **systemctl restart docker** command to restart the Docker service. Run the commands that are listed in Scenario 9 to verify that all the Docker services are active.

**Scenario 7: Service container (Cobbler, ELK) start failure**

As described in Scenario 8, all the services run as Docker containers on the management node. To find all services running as containers, use the **docker ps -a** command. If any services are in Exit state, use the **systemctl** command and **grep** for Docker to find the exact service name, for example:

```
systemctl | grep docker- | awk '{print $1}'
docker-cobbler-tftp.service
docker-cobbler-web.service
docker-cobbler.service
docker-container-registry.service
docker-elasticsearch.service
docker-kibana.service
docker-logstash.service
docker-vmtp.service
```

If any services need restarting, use the **systemctl** command. For example, to restart a Kibana service:

```
systemctl restart docker-kibana.service
```

### Scenario 8: One link failure on the bond Interface

management node is set up with two different networks: **br\_api** and **br\_mgmt**. The **br\_api** interface is the external. It is used for accessing outside services such as the Cisco VIM REST API, Kibana, and Cobbler. The **br\_mgmt** interface is internal. It is used for provisioning and to provide management connectivity to all OpenStack nodes (control, compute and storage). Each network has two ports that are bonded to provide redundancy. If one port fails, the system remains completely functional through the other port. If a port fails, check for physical network connectivity, and remote switch configuration to debug the underlying cause of the link failure.

### Scenario 9: Two link failures on the bond Interface

As described in Scenario 10, each network is configured with two ports. If both ports are down, the system is not reachable and management node services could be disrupted. After the ports are back up, the system is fully operational. Check the physical network connectivity and the remote switch configuration to debug the underlying link failure cause.

### Scenario 10: REST API service failure

The management node runs the REST API service for Cisco VIM clients to reach the server. If the REST service is down, Cisco VIM clients cannot reach the server to trigger any server operations. However, with the exception of the REST service, other management node services remain operational.

To verify the management node REST services are fully operational, use the following command to check that the **httpd** and **mercury-restapi** services are in active and running state:

```
systemctl status httpd
httpd.service - The Apache HTTP Server
 Loaded: loaded (/usr/lib/systemd/system/httpd.service; enabled; vendor preset: disabled)
 Active: active (running) since Mon 2016-08-22 00:22:10 CEST; 22h ago

systemctl status mercury-restapi.service
mercury-restapi.service - Mercury Restapi
 Loaded: loaded (/usr/lib/systemd/system/mercury-restapi.service; enabled; vendor preset: disabled)
 Active: active (running) since Mon 2016-08-22 00:20:18 CEST; 22h ago
```

A tool is also provided so that you can check the REST API server status and the location of the folder it is running from. To execute run the following command:

```
cd installer-<tagid>/tools
./restapi.py -a status
Status of the REST API Server: active (running) since Thu 2016-08-18 09:15:39 UTC; 9h
```

```
ago
 REST API launch directory: /root/installer-<tagid>/
```

Confirm the server status is active and check that the restapi launch folder matches the folder where the installation was launched. The restapi tool also provides the options to launch, tear down, and reset password for the restapi server as shown in the following command:

```
./restapi.py -h

usage: restapi.py [-h] --action ACTION [--yes] [--verbose]

REST API setup helper

optional arguments:
 -h, --help show this help message and exit
 --action ACTION, -a ACTION
 setup - Install and Start the REST API server.
 teardown - Stop and Uninstall the REST API
 server.
 restart - Restart the REST API server.
 regenerate-password - Regenerate the password for
 REST API server.
 reset-password - Reset the REST API password with
 user given password.
 status - Check the status of the REST API server
 --yes, -y Skip the dialog. Yes to the action.
 --verbose, -v Perform the action in verbose mode.
```

If the REST API server is not running, execute **ciscovim** to show the following error message:

```
cd installer-<tagid>/
ciscovim -setupfile ~/Save/<setup_data.yaml> run
```

If the installer directory or the REST API state is not correct or points to an incorrect REST API launch directory, go to the installer-<tagid>/tools directory and execute:

```
./restapi.py -action setup
```

To confirm that the REST API server state and launch directory is correct run the following command:

```
./restapi.py -action status
```

### Scenario 11: Graceful reboot with Cisco VIM Unified Management

Cisco VIM Unified Management runs as a container on the management node. After a graceful reboot of the management node, the VIM Unified Management and its associated database containers comes up. So there is no impact on recovery.

### Scenario 12: Power outage or hard reboot with VIM Unified Management

The Cisco VIM Unified Management container comes up automatically following a power outage or hard reset of the management node.

### Scenario 13: Cisco VIM Unified Management reinstallation

If the management node which is running the Cisco VIM Unified Management fails and cannot come up, you must uninstall and reinstall the Cisco VIM UM. After the VM Unified Management container comes up, add the relevant bootstrap steps as listed in the install guide to register the pod. VIM Unified Management then automatically detects the installer status and reflects the present status appropriately.

To clean up and reinstall Cisco VIM UM run the following command:

```
cd /root/installer-<tagid>/insight/
./bootstrap_insight.py -a uninstall -o standalone -f </root/insight_setup_data.yaml>
```

**Scenario 14: VIM Unified Management Container reboot**

On Reboot of the VIM Unified Management container, services continue to work as it is.

**Scenario 15: Intel (I350) 1Gbps LOM failure**

The management node is set up with an Intel (I350) 1-Gbps LOM for API connectivity. Two 1-Gbps ports are bonded to provide connectivity redundancy. No operational impact occurs if one of these ports goes down. However, if both ports fail, or the LOM network adapter fails, the system cannot be reached through the API IP address. If this occurs you must replace the server because the LOM is connected to the system motherboard. To recover the management node with a new server, complete the following steps. Make sure the new management node hardware profile, matches the existing server and the Cisco IMC IP address is assigned.

1. Shut down the existing management node.
2. Unplug the power from the existing and new management nodes.
3. Remove all HDDs from existing management node and install them in the same slots of the new management node.
4. Plug in the power to the new management node, but do not boot the node.
5. Verify the configured boot order is set to boot from local HDD.
6. Verify the Cisco NFVI management VLAN is configured on the Cisco VIC interfaces.
7. Boot the management node for the operating system to begin.

After the management node is up, the management node bond interface is down due to the incorrect MAC address. It points to old node network card MAC address.

8. Update the MAC address under `/etc/sysconfig/network-scripts`.
9. Reboot the management node.  
It is fully operational. All interfaces has to be in an up state and be reachable.
10. Verify that Kibana and Cobbler dashboards are accessible.
11. Verify the Rest API services are up. See Scenario 15 for any recovery steps.

**Scenario 16: Cisco VIC 1227 10Gbps mLOM failure**

The management node is configured with a Cisco VIC 1227 dual port 10-Gbps mLOM adapter for connectivity to the other Cisco NFVI nodes. Two 10 Gbps ports are bonded to provide connectivity redundancy. If one of the 10-Gbps ports goes down, no operational impact occurs. However, if both Cisco VIC 10 Gbps ports fail, the system goes into an unreachable state on the management network. If this occurs, you must replace the VIC network adapters. Otherwise pod management and the Fluentd forwarding service is disrupted. If you replace a Cisco VIC, update the management and provisioning VLAN for the VIC interfaces using Cisco IMC and update the MAC address in the interfaces under `/etc/sysconfig/network-scripts` interface configuration file.

**Scenario 17: DIMM memory failure**

The management node is set up with multiple DIMM memory across different slots. Failure of one or memory modules could cause the system to go into unstable state, depending on how many DIMM memory failures occur. DIMM memory failures are standard system failures like any other Linux system server. If a DIMM memory fails, replace the memory module(s) as soon as possible to keep the system in stable state.

**Scenario 18: One CPU failure**

Cisco NFVI management nodes have dual core Intel CPUs (CPU1 and CPU2). If one CPU fails, the system remains operational. However, always replace failed CPU modules immediately. CPU failures are standard system failures such as any other Linux system server. If a CPU fails, replace it immediately to keep the system in stable state.

## Recovering Compute Node Scenario

The Cisco NFVI Compute node hosts the OpenStack services to provide processing, network, and storage resources to run instances. The node architecture includes a Cisco UCS C220 M4 server with dual CPU socket, 10-Gbps Cisco VIC mLOM, and two HDDs in RAID 1 configuration.

### Failure of one active HDD

With RAID 1, data are shown and allows up to one active HDD failure. When an HDD fails, the node is still functional with no impacts. However, the data are no longer illustrated and losing another HDD results in unrecoverable and operational downtime. The failed disk has to be replaced soon as it takes approximately 2 hours to rebuild the new disk and move to synchronized state.

To check the disk and RAID state, run the storcli commands as follows:



**Note** Make sure that the node is running with hardware RAID by checking the storcli output and comparing to the one that is shown in the following command.

```
[root@compute-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show

<...snip...>

TOPOLOGY :
=====

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID1 Opt1 N 837.258 GB dflt N N dflt N N <== RAID 1 in
optimal state
0 0 - - - RAID1 Opt1 N 837.258 GB dflt N N dflt N N
0 0 0 252:2 9 DRIVE Onln N 837.258 GB dflt N N dflt - N
0 0 1 252:3 11 DRIVE Onln N 837.258 GB dflt N N dflt - N

<...snip...>

Physical Drives = 2

PD LIST :
=====

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:2 9 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U <== all disks
functioning
252:3 11 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U

[root@compute-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show
```

```
<...snip...>

TOPOLOGY :
=====

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID1 Dgrd N 837.258 GB dflt N N dflt N N <== RAID 1 in
degraded state.
0 0 - - - RAID1 Dgrd N 837.258 GB dflt N N dflt N N
0 0 0 - - DRIVE Msgng - 837.258 GB - - - - - N
0 0 1 252:3 11 DRIVE Onln N 837.258 GB dflt N N dflt - N

```

```
<...snip...>

PD LIST :
=====

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:2 9 UGood - 837.258 GB SAS HDD N N 512B ST900MM0006 U <== active disk
in slot 2 disconnected from drive group 0
252:3 11 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U

```

To replace the failed disk and add it back as a spare run the following command:

```
[root@compute-node ~]# /opt/MegaRAID/storcli/storcli64 /c0/e252/s2 add hotsparedrive dg=0
Controller = 0
Status = Success
Description = Add Hot Spare Succeeded.
```

```
[root@compute-node ~]# /opt/MegaRAID/storcli/storcli64 /c0 show
```

```
<...snip...>

TOPOLOGY :
=====

DG Arr Row EID:Slot DID Type State BT Size PDC PI SED DS3 FSpace TR

0 - - - - RAID1 Dgrd N 837.258 GB dflt N N dflt N N
0 0 - - - RAID1 Dgrd N 837.258 GB dflt N N dflt N N
0 0 0 252:2 9 DRIVE Rbld Y 837.258 GB dflt N N dflt - N
0 0 1 252:3 11 DRIVE Onln N 837.258 GB dflt N N dflt - N

```

```
<...snip...>

PD LIST :
=====

EID:SlT DID State DG Size Intf Med SED PI SeSz Model Sp

252:2 9 Rbld 0 837.258 GB SAS HDD N N 512B ST900MM0006 U <== replacement
disk in slot 2 joined device group 0 and in rebuilding state
252:3 11 Onln 0 837.258 GB SAS HDD N N 512B ST900MM0006 U

```

```
[root@compute-node ~]# /opt/MegaRAID/storcli/storcli64 /c0/e252/s2 show rebuild
Controller = 0
```

```
Status = Success
Description = Show Drive Rebuild Status Succeeded.
```

```

Drive-ID Progress% Status Estimated Time Left

/c0/e252/s2 10 In progress 1 Hours 9 Minutes <== replacement disk in slot 2 rebuild
status

```

## Running the Cisco VIM Technical Support Tool

Cisco VIM includes a tech-support tool that you can use to gather Cisco VIM information to help solve issues working with Cisco Technical Support. The tech-support tool can be extended to execute custom scripts. It can be called after runner is executed at least once. The tech-support tool uses a configuration file that specifies what information to collect. The configuration file is located in the following location:  
/root/openstack-configs/tech-support/tech\_support\_cfg.yaml.

The tech-support tool checks the point where the Cisco VIM installer has executed and collects the output of files or commands that is indicated by the configuration file. For example, if the installer fails at Step 3 (VALIDATION), the tech-support provides information that is listed in the configuration file up to Step 3 (included). You can override this default behavior by adding the --stage option to the command.

The tech-support script is located at the management node /root/installer-{tag-id}/tech-support directory. To run it after the runner execution, enter the following command:

```
./tech-support/tech_support.py
```

The command creates a compressed tar file containing all the information that is gathered. The file location is displayed in the console at the end of the execution. You need not have to execute the command with any options. However, if you want to override any default behavior, you can use the following options:

```
/tech_support.py --help
Usage: tech_support.py [options]
```

Tech-support collects information about your cloud

Options:

```
-h, --help show this help message and exit
--stage=STAGE specify the stage where installer left off
--config-file=CFG_FILE specify alternate configuration file name
--tmp-dir=TMP_DIR specify alternate temporary directory name
--file-size=TAIL_SIZE specify max size (in KB) of each file collected
--host-list=HOST_LIST List (comma separated) of the hostnames of the servers
 to collect info from
--ip-list=IP_LIST List (comma separated) of the IPv4 of the hosts to
 collect info from
--exclude-mgmt-node specify if mgmt node info needs to be excluded
--include-cimc specify if cimc techsupport needs to be included
```

Where:

- stage—tells at which state the installer left off. The possible values are: INPUT\_VALIDATION, BUILDNODE\_ORCHESTRATION, VALIDATION, BAREMETAL\_INSTALL, COMMON\_SETUP, CEPH, ORCHESTRATION or VMTP

- **config-file**—Provides the path for a specific configuration file. Make sure that your syntax is correct. Look at the default `/root/tech-support/openstack-configs/tech_support_cfg.yaml` file as an example on how to create a new `config-file` or modify the default file.
- **tmp-dir**—Provides the path to a temp directory `tech-support` can use to create the compressed tar file. The `tech-support` tool provides the infrastructure to execute standard Linux commands from packages that are included in the Cisco VIM installation. This infrastructure is extensible and you can add commands, files, or custom bash or Python scripts into the configuration file pane for the tool to collect the output of those commands or scripts. (See the README pane for more details.)
- **file-size**—Is an integer that specifies (in KB) the maximum file size that `tech-support` captures and tail the file if needed. By default, this value is set to 10 MB. For example, if no `file-size` option is provided and the `tech-support` has to collect `/var/log/mercury/data.log` and the `data.log` is more than 10 MB, `tech-support` gets the last 10 MB from `/var/log/mercury/data.log`.
- **host-list**—Provides the list of hosts one wants to collect from the `tech-support` through hostname, defaults to all hosts.
- **ip-list**—Provides the list of hosts one wants to collect the `tech-support` through management IP, defaults to all hosts.
- **exclude-mgmt-node**—It is an option not to collect `tech-support` from the management node.
- **include-cimc**—This option allows to specify the list of hosts to get the CIMC `tech-support`. You can use this option along with the `-host-list` and `-ip-list` options.



---

**Note** When using the `ip-list` option, provide the list of the management IP addresses (the `tech-support` will figure out the CIMC IP address from the `setup_data.yaml` file).

---

## Tech-Support Configuration File

Cisco VIM `tech-support` is a utility tool is designed to collect the VIM pod logs which help users to debug the issues offline. The administrator uses the `tech-support` configuration files to provide the list of commands or configuration files. The `tech support` tool of the Cisco VIM gathers list of commands or configuration files for the offline diagnostic or debugging purposes.

By default the `tech-support` configuration file is located at the `/root/openstack-configs/tech-support/tech_support_cfg.yaml` file. Alternatively, you can use a different one by specifying the `-config-file` option. The syntax of this configuration file must be as follows:

The `tech-support` configuration file section is divided into eight sections which corresponds to each of the installer stages:

- `INPUT_VALIDATION`
- `BUILDNODE_ORCHESTRATION`
- `VALIDATION`
- `BAREMETAL_INSTALL`

- COMMON\_SETUP
- CEPH
- ORCHESTRATION
- VMTP

Inside each of these eight sections, there are tags divided on hierarchical levels. At the first level, the tag indicates the host(s) or path on which the command(s) run and from where the file(s) can be collected. The possible tags are as follows:

- - HOSTS\_MANAGEMENT: Run in the Management node only
- - HOSTS\_CONTROL: Run in all the Control nodes
- - HOSTS\_COMPUTE: Run in all the Compute nodes
- - HOSTS\_STORAGE: Run in all the Storage nodes
- - HOSTS\_COMMON: Run in all the Compute and Control nodes
- - HOSTS\_ALL: Run in all the Compute, Control and Storage nodes



---

**Note** In any of these eight sections, if HOSTS tag is not specified then no information is collected for that stage.

---

For each of the hosts mentioned above there is a second level tag which specifies where to run the command. The possible values of those tags are as follows:

- - SERVER\_FILES: Path(s) to the file(s) that tech-support has to collect.
- - SERVER\_COMMANDS: Command(s) or script name(s) which has to be executed directly on the server. The command(s) has to be included before in the \$PATH. For the scripts, refer to the Custom Scripts paragraph below.
- - CONTAINERS: Indicates the tech-support tool that the command(s) has to be executed and the files to be gathered from inside a container. See the following steps for more specific information of what can be added in this section.

In the CONTAINERS section, indicate the path in which container the commands are executed or gathered from. This is done with a <container\_name> tag. The following are the shown to get the string for the <container\_name> tag):

- all\_containers: Execute inside all containers (regardless of the state).
- <container\_name>: Container Name must be the name of a container and it indicates in which container to run the command or gather the information. It runs commands inside the container only if the mentioned container is up (as we cannot run commands on dead containers). Examples of how to get the container name:
  - Execute **docker ps** and get the name (without any numbers) of the last column of output **docker ps -a**.

For example:

```

CONTAINER ID IMAGE COMMAND <snip> NAMES
81bc4e54cbfb <registry>/vmtp:4263 /bin/bash" vmtp_4263

```

The tech-support runs the linux commands on the server (from packages that is included in RHEL7.3). Add the name of the commands under the SERVER\_COMMANDS section of the configuration file to run the commands.

However, if the administrator wants to add a custom bash or python script to be executed in some set of servers in the cloud. In such case you need to add the script into the custom-scripts directory on the current directory path (/root/openstack-configs/tech-support/) and add the script name into the corresponding SERVER\_COMMANDS section.

The tech-support tool will scp the script(s) included in the custom-scripts directory into the appropriate cloud nodes where it will be executed (as# indicated in this config file) and capture the output (stdout and stderr) and add it to the collection of files collected by the tech-support tool. It is assumed that the scripts are self-standing and independent and needs no external input.

Following is an example of a custom tech-support configuration file. This is just an example of what information the tech-support tool will gather if given the following configuration file:

```

COMMON_SETUP:
 HOSTS_ALL: # All compute, control and storage hosts
 SERVER_FILES:
 - /usr/lib/docker-storage-setup
 SERVER_COMMANDS:
 - docker info
 - my_script.sh
 CONTAINERS:
 all_containers: #execute in all containers (even if they are in down state)
 CONTAINER_COMMANDS:
 - docker inspect
 - docker logs
 logstash:
 CONTAINER_FILES:
 - /var/log/
 CONTAINER_COMMANDS:
 - ls -l

```

Given this example of configuration, and assuming that the installer ended in at least the COMMON\_SETUP state, the tech-support tool will run under all OpenStack nodes (Compute, Control and Storage) and it will:

- Gather (if exists) the contents of /usr/lib/docker-storage-setup file.
- Run **docker info** command and collect the output.
- Run **my\_script.sh** and collect the output. The **my\_script.sh** is an example of a bash script which the user previously added to the /root/openstack-configs/tech-support/custom-scripts directory.
- Collect the output of docker inspect and docker logs for all containers.
- Collect the files in /var/log inside the logstash container (if there is container with that name). This is equivalent to running the following command (where /tmp indicates a temporary location where the tech-support tool gathers all the information): **docker cp logstash\_{tag}:/var/log/ /tmp**.
- Collect the output of the command **docker exec logstash\_{{tag}}: ls -l**.

## Tech-Support When Servers Are Offline

It is difficult to collect the information from the servers if one or more cloud nodes are not reachable. In this case, you can connect through the KVM console into those servers and run the local tech-support tool.

---

**Step 1** To run the local tech-support tool run the following command:

```
/root/tech_support_offline
```

**Step 2** Cisco VIM tech\_support\_offline collects the Logs and other troubleshooting output from the server and place it in the location of the other server:

```
/root/tech_support
```

**Note** After the server is reachable, you can use the Cisco VIM tech-support tool which collects all the files under the /root/tech-support/ directory which can be used to debug any issue which are offline.

---

## Disk-Maintenance Tool to Manage Physical Drives

In VIM you can use the disk-maintenance tool to check the status of all physical drives that are present in running and operational nodes in the following roles -

- Management
- Control (all or specific nodes)
- Compute (all or specific nodes) (Expect for third party)

This provides the information about the present status of the physical drives - if they are in Online, Offline, Rebuilding, Unconfigured Good or JBOD states if all disks are ok. If not, the disks that have gone bad are displayed with the slot number and server information, that has to be replaced. When multiple disks have to be replaced, we recommend you to execute remove or add of the node.

- Physically remove and insert a new disk before attempting to replace.
- For smooth operation, wipe out disk before attempting replace operations.
- Call Cisco TAC if you face any issue. Do not reattempt.



---

**Note** Make sure that each node is running with hardware RAID, the steps for which can be found in the section titled Recovering Compute Node Scenario. Refer to step 15 of the section "Upgrading Cisco VIM Software Using a USB" on how to move the pod from hardware RAID to software RAID.

---

To check the status of the Diskmgmt log in to the management node and run the ciscovim command with the diskmgmt option. The design of the diskmgmt user interface follows a test job create, list, show, and delete the workflow.

Diskmgmt user workflow:

A database of disk operation results is maintained so that you can keep the results of multiple disk check or replace and view them at any time.

**Step 1** Run the Help command to see all available command line options:

```
ciscovim help diskmgmt
usage: ciscovim diskmgmt [--server <node1,node2,...>] [--id <id>]
 [--locator {on,off}] [--json-display] [-y]
 create|delete|list|show check-disks|replace-disks
 all|management|control|compute

HDD maintenance helper

Positional arguments:
 create|delete|list|show The control command to perform
 check-disks|replace-disks The identity of the task/action
 all|management|control|compute The role of the target host(s)

Optional arguments:
 --server <node1,node2,...> List of specific control/compute host names
 within the target role.
 --id <id> ID used to identify specific item to
 show/delete.
 --locator {on,off} Turn on/off locator LED for server with bad
 disks and for the physical drives.
 --json-display Shows output in JSON format.
 -y, --yes Yes option to perform the action
```

**Step 2** Check disk operation creates check-disks operation for all control nodes in the POD. The system responds with a message indicating the Time, ID and when it was created. Run the following check-disk operation command:

```
ciscovim diskmgmt create check-disks control
+-----+
| Field | Value |
+-----+-----+
action	check-disks
command	create
created_at	2018-03-07T21:12:20.684648+00:00
id	0c6d27c8-bdac-493b-817e-1ea8640dae57
locator	False
result	
role	control
servers	None
status	not_run
updated_at	None
+-----+-----+
```

**Step 3** The cisco vim diskmgmt list command is used to monitor a currently running task, and the completed tasks. The list command can filter based on the role. Using ‘all’ command lists all the tests that are in the database.

```
ciscovim diskmgmt list check-disks control
+-----+-----+-----+-----+-----+
| ID | Action | Role | Status | Created |
+-----+-----+-----+-----+-----+
| 861d4d73-ffee-40bf-9348-13afc697ee3d | check-disks | control | Complete | 2018-03-05 14:44:47+00:00 |
| 0c6d27c8-bdac-493b-817e-1ea8640dae57 | check-disks | control | Running | 2018-03-07 21:12:20+00:00 |
+-----+-----+-----+-----+-----+
```

```

+-----+
[root@F24-Michigan ~]# ciscovim diskmgmt list check-disks compute
+-----+
| ID | Action | Role | Status | Created |
+-----+
| 0be7a55a-37fe-43a1-a975-cbf93ac78893 | check-disks | compute | Complete | 2018-03-05 14:45:45+00:00 |
+-----+
[root@F24-Michigan ~]# ciscovim diskmgmt list check-disks all
+-----+
| ID | Action | Role | Status | Created |
+-----+
cdfd18c1-6346-47a2-b0f5-661305b5d160	check-disks	all	Complete	2018-03-05 14:43:50+00:00
861d4d73-ffee-40bf-9348-13afc697ee3d	check-disks	control	Complete	2018-03-05 14:44:47+00:00
0be7a55a-37fe-43a1-a975-cbf93ac78893	check-disks	compute	Complete	2018-03-05 14:45:45+00:00
0c6d27c8-bdac-493b-817e-1ea8640dae57	check-disks	control	Complete	2018-03-07 21:12:20+00:00
+-----+

```

**Step 4** Run the following command to show the detailed results of a diskmgmt check-disks operation:

```

ciscovim diskmgmt show check-disks control --id 0c6d27c8-bdac-493b-817e-1ea8640dae57
+-----+
| Message | Host | Role | Server | State |
+-----+
Raid Health Status	f24-michigan-micro-1	block_storage control compute	7.7.7.7	Optimal
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	Optimal
	f24-michigan-micro-3	block_storage control compute	7.7.7.5	Optimal
VD Health Status	f24-michigan-micro-1	block_storage control compute	7.7.7.7	Optimal
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	Optimal
	f24-michigan-micro-3	block_storage control compute	7.7.7.5	Optimal
RAID Level and Type	f24-michigan-micro-1	block_storage control compute	7.7.7.7	Type - HW; Level - RAID1
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	Type - HW; Level - RAID1
	f24-michigan-micro-3	block_storage control compute	7.7.7.5	Type - HW; Level - RAID1
Number of Physical Disks	f24-michigan-micro-1	block_storage control compute	7.7.7.7	8
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	8
	f24-michigan-micro-3	block_storage control compute	7.7.7.5	8

```

```

| Number of Virtual Disks | f24-michigan-micro-1 | block_storage control compute | 7.7.7.7 | 1
| | f24-michigan-micro-2 | block_storage control compute | 7.7.7.6 | 1
| | f24-michigan-micro-3 | block_storage control compute | 7.7.7.5 | 1
| | | | |
| Boot Drive Disk Media-Type | f24-michigan-micro-1 | block_storage control compute | 7.7.7.7 | HDD
| | f24-michigan-micro-2 | block_storage control compute | 7.7.7.6 | HDD
| | f24-michigan-micro-3 | block_storage control compute | 7.7.7.5 | SSD

```

---

State Keys:

DHS-Dedicated Hot Spare|UGood-Unconfigured Good|GHS-Global Hotspare  
 UBad-Unconfigured Bad|Onln-Online|Offln-Offline  
 Rbld-Rebuilding|JBOD-Just a Bunch Of Disks

**Step 5** Run the following command to delete the diskmgmt check-disks:

Delete a diskmgmt check-disks result:

**Note** Cisco recommends you to delete the tests which are not in use.

---

## OSD-Maintenance Tool

You can use the osd-maintenance tool to check the status of all OSDs that are present in running and operational block storage nodes. OSD maintenance tool gives you the detailed information about the status of the OSDs - if they are Up or Down, in addition to what HDD corresponds to which OSD, including the slot number and server hostname.

- If it is down OSD is discovered after check\_osds is performed, run the cluster recovery and recheck.
- If still down, wait 30 minutes before attempting replace - time for ceph-mon to sync.
- Physically remove and insert a new disk before attempting replace.
- For smooth operation, wipe out disk before attempting replace operations.
- Need a dedicated journal SSD for each storage server where osdmgmt is attempted.
- Only allowed to replace one OSD at a time. Space out each replace OSD by 30 minutes - time for ceph-mon to sync.
- Call TAC if any issue is hit. Do not reattempt.

To check the status of the osdmgmt tool log in the management node and run the ciscovim command with the osdmgmt option. The osdmgmt user interface allows you to create, list, show, and delete a workflow.

- Use ‘ciscovim osdmgmt create ...’ command to initiate a check and replace OSD operation
- Use ‘ciscovim osdmgmt list ...’ command to view summary and status of current OSD operations
- Use ‘ciscovim osdmgmt show ... --id <ID>’ command to view detail OSD operation results

- Use 'ciscovim osdmgmt delete ... --id <ID>' command to delete the results.

Examples of usage of this tool:

**Step 1** Run the Help command to see all the option:

```
ciscovim help osdmgmt
usage: ciscovim osdmgmt [--server <node1,node2,...>] [--detail] [--id <id>]
 [--osd <osd_name>] [--locator {on,off}]
 [--json-display] [-y]
 create|delete|list|show check-osds|replace-osd

OSD maintenance helper

Positional arguments:
 create|delete|list|show The control command to perform
 check-osds|replace-osd The identity of the task/action

Optional arguments:
 --server <node1,node2,...> List of specific block_storage hostnames
 --detail Display full OSD details
 --id <id> ID used to identify specific item to
 show/delete.
 --osd <osd_name> Name of down OSD to replace. Eg. 'osd.xx'
 --locator {on,off} Turn on|off locator LED for server with bad OSDs
 and for the physical drives.
 --json-display Show output will be in JSON format.
 -y, --yes Yes option to perform the action

-----+
```

**Step 2** To check the osds run the following command:

```
ciscovim osdmgmt create check-osds
-----+
| Field | Value |
-----+-----+
action	check-osds
command	create
created_at	2018-03-08T21:11:13.611786+00:00
id	5fd4f9b5-786a-4a21-a70f-bffac70a3f3f
locator	False
osd	None
result	
servers	None
status	not_run
updated_at	None
-----+
```

**Step 3** Monitor the osdmgmt check operations using the list command. Cisco Vim Osd mgmt list commands are used to monitor the currently running test. It also helps you to view the tests that are run/ completed.

```
ciscovim osdmgmt list check-osds
-----+-----+-----+-----+
| ID | Action | Status | Created |
-----+-----+-----+-----+
| 5fd4f9b5-786a-4a21-a70f-bffac70a3f3f | check-osds | Complete | 2018-03-08 21:11:13+00:00 |
| 4efd0be8-a76c-4bc3-89ce-142de458d844 | check-osds | Complete | 2018-03-08 21:31:01+00:00 |
-----+-----+-----+-----+
```

**Step 4** To show the detailed results of `osdmgmt check-osds` operation, run the following command:

```
ciscovim osdmgmt show check-osds --id 5fd4f9b5-786a-4a21-a70f-bffac70a3f3f
+-----+-----+-----+-----+-----+-----+
| Message | Host | Role | Server | State |
+-----+-----+-----+-----+-----+-----+
Overall OSD Status	f24-michigan-micro-3	block_storage control compute	7.7.7.5	Optimal
	f24-michigan-micro-1	block_storage control compute	7.7.7.7	Optimal
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	Optimal
Number of OSDs	f24-michigan-micro-3	block_storage control compute	7.7.7.5	5
	f24-michigan-micro-1	block_storage control compute	7.7.7.7	5
	f24-michigan-micro-2	block_storage control compute	7.7.7.6	5
+-----+-----+-----+-----+-----+-----+				
Host	OSDs	Status	ID	HDD Slot
+-----+-----+-----+-----+-----+-----+				
Journal				
+-----+-----+-----+-----+-----+-----+				
f24-michigan-micro-3	osd.0	up	0	4 (JBOD)
/dev/sdf1				
	osd.1	up	1	5 (JBOD)
/dev/sdf2				
	osd.3	up	3	7 (JBOD)
/dev/sdf3				
	osd.5	up	5	8 (JBOD)
/dev/sdf4				
	osd.6	up	6	6 (JBOD)
/dev/sdf5				
f24-michigan-micro-1	osd.2	up	2	5 (JBOD)
/dev/sdf1				
	osd.7	up	7	7 (JBOD)
/dev/sdf2				
	osd.9	up	9	8 (JBOD)
/dev/sdf3				
	osd.11	up	11	6 (JBOD)
/dev/sdf4				
	osd.13	up	13	4 (JBOD)
/dev/sdf5				
f24-michigan-micro-2	osd.4	up	4	8 (JBOD)
/dev/sdf1				
	osd.8	up	8	5 (JBOD)
/dev/sdf2				
	osd.10	up	10	4 (JBOD)
/dev/sdf3				
	osd.12	up	12	6 (JBOD)
/dev/sdf4				
	osd.14	up	14	7 (JBOD)
/dev/sdf5				
+-----+-----+-----+-----+-----+-----+
```

**Step 5** To delete the check-disk osds, run the following command:

```
ciscovim osdmgmt delete check-osds --id 5fd4f9b5-786a-4a21-a70f-bffac70a3f3f

Perform the action. Continue (Y/N)Y
Delete of UUID 5fd4f9b5-786a-4a21-a70f-bffac70a3f3f Successful

[root@F24-Michigan ~]# ciscovim osdmgmt list check-osds
+-----+-----+-----+-----+-----+-----+
| ID | Action | Status | Created |
+-----+-----+-----+-----+-----+-----+
```

```
-----+-----+-----+-----+
| 4efd0be8-a76c-4bc3-89ce-142de458d844 | check-osds | Complete | 2018-03-08 21:31:01+00:00 |
-----+-----+-----+-----+
```

**Note** OSD maintenance is supported only on standalone OSD drives (based on HDD), but not when they are co-located with journaling.

## Utility to Resolve Cisco VIM Hardware Validation Failures

The Cisco VIM Hardware Validation utility tool is used to perform hardware validation during the installation of UCS C-series servers. It captures the user and environmental hardware validation errors that occur during the installation process. The tool enables you to fix these errors that are based on the inputs you provide at the Command Line Interface (CLI). It validates the updated configurations to verify if the changes are applied properly. After the error is resolved, you can resume the installation from the point of failure.

The `ciscovim hardware-mgmt` user interface allows you to test the job `validate orresolve-failures(create)`, `list`, `show`, and `delete` workflow

Hardware-mgmt user workflow:

1. Use “`ciscovim hardware-mgmt validate ...`” command to initiate a validation.
2. Use “`ciscovim hardware-mgmt list ...`” command to view summary/status of current test jobs.
3. Use “`ciscovim hardware-mgmt show ... --id <ID>`” command to view detail test results
4. Use “`ciscovim hardware-mgmt delete ... --id <ID>`” to delete test results.

A database of results is maintained so that the user can keep the results of multiple hardware-mgmt operations and view them at any time.



**Note** You cannot use the utility for the following tasks:

- Configuring BIOS settings for the B-series pods.
- Upgrading or changing the firmware version.
- Resolving hardware failures other than `lom`, `hba`, `flexflash`, `pcie_slot`, `power`, and `vnuc_pxe_boot`.

## Command Usage

To capture the list of failures that can be resolved by using the utility, go to the `install` directory and execute the `help` command:

```
cd <installer-id>/clouddeploy
python hw_validations.py -help .
```

The following shows the output of the `help` command.

```
usage: hw_validations.py [-h] [--resolve-failures RESOLVE_FAILURES]
[--validate VALIDATE_OF] [-y] [--host HOSTS]
[--file SETUP_FILE_LOCATION]
UCS Hardware Validations
optional arguments:
-h, --help show this help message and exit
--resolve-failures RESOLVE_FAILURES, -rf RESOLVE_FAILURES
 all - Fix all the failures.
 lom - Fix LOM port(s) status failures.
 hba - Fix HBA port status failures.
 flexflash - Fix Flexflash failures.
 pcie_slot - Fix PCIe slot status failures.
 power - Fix Power failures.
 vnic_pxe_boot - Fix Vnic PXE_Boot statusfailures
-y, -yes
--host HOSTS Comma separated list of hostnames
--file SETUP_FILE_LOCATION, -f SETUP_FILE_LOCATION
 Provide a valid 'setup_data.yaml' file
```

### Command Syntax

**hw\_validations.py [-h] [--resolve-failures RESOLVE\_FAILURES] [--validate VALIDATE\_OF] [-y] [--host HOSTS] [--file SETUP\_FILE\_LOCATION]**

The following table provides the description of the parameters of the command.

| Optional                                                    | Description                                                                                                                                                                                                                                                                                                                                                                         |
|-------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| [-h], --help                                                | Provides detailed information about the command.                                                                                                                                                                                                                                                                                                                                    |
| [--resolve-failures RESOLVE_FAILURES], -rf RESOLVE_FAILURES | Enables you to specify the failure that you want to resolve. The optional arguments are as follows:                                                                                                                                                                                                                                                                                 |
| [-y]                                                        | Yes                                                                                                                                                                                                                                                                                                                                                                                 |
| [--host HOSTS]                                              | Enables you to specify the hostname of the server for which you want to resolve failures. You cannot specify the IP address or CIMC IP address of servers as arguments. You can specify a list of hostnames as comma-separated arguments.<br><br>If the -host option is not specified, the failures of all the servers that are specified in the setup_data.yaml file are resolved. |
| [--file SETUP_FILE_LOCATION]<br>[-f SETUP_FILE_LOCATION]    | Enables you to specify the name of a setup_data.yaml file.                                                                                                                                                                                                                                                                                                                          |

## Examples of Command Usage

The following table provides the commonly used commands along with their examples.

| Purpose                  | Syntax                                                | Example                                               |
|--------------------------|-------------------------------------------------------|-------------------------------------------------------|
| To resolve all failures. | python hw_validations.py<br>--resolve-failures all -y | python hw_validations.py<br>--resolve-failures all -y |

| Purpose                                                                                                          | Syntax                                                                                                                     | Example                                                                                                                                                                                         |
|------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| To simultaneously resolve one or more failures.                                                                  | python hw_validations.py<br>--resolve-failures<br><failure-1>,<failure-2> -y                                               | To resolve the lom and hba status failures: python hw_validations.py --resolve-failures lom,hba -y                                                                                              |
| To resolve the errors by using the setup_data.yaml file.                                                         | python hw_validations.py<br>--resolve-failures<br><failure-1>,<failure-2> -y --file<br><location-of-yaml file>             | To resolve the LOM status failures by using ~/save/setup_data.yaml file:<br><br>python hw_validations.py --resolve-failures lom,hba -y --file ~/save/setup_data.yaml                            |
| To resolve failures on a particular server as specified in the setup_data.yaml file by using the -- host option. | python hw_validations.py<br>--resolve-failures <failure-1> -y<br>--host<br><name-of-host-server-1>,<name-of-host-server-2> | To resolve the PCIe slot failures on hiccup-controller-1 server as specified in the setup_data.yaml:<br><br>python hw_validations.py --resolve-failures pcie_slot -y --host hiccup-controller-1 |

## Cisco VIM Client Debug Option

The --debug option enables you to get verbose logging on the ciscovim client console. You can use verbose logging to troubleshoot issues with the ciscovim client.

The debug option has the following parts:

- Curl Command: Curl command can be used for debugging. It can be executed standalone. Curl Command also displays the REST API Endpoint and the Request Payload.
- Response of REST API

### Examples of Using debug Option to get list of passwords

```
ciscovim --debug list-password-keys
2018-05-28 22:13:21,945 DEBUG [ciscovimclient.common.httpClient][MainThread] curl -i -X GET
-H 'Content-Type: application/json' -H 'Authorization: ****' -H 'Accept: application/json'
-H 'User-Agent: python-ciscovimclient' --cacert /var/www/mercury/mercury-ca.crt
https://172.31.231.17:8445/secrets
2018-05-28 22:13:21,972 DEBUG [ciscovimclient.common.httpClient][MainThread]
HTTP/1.1 200 OK
content-length: 1284
x-xss-protection: 1
x-content-type-options: nosniff
strict-transport-security: max-age=31536000
server: WSGIServer/0.1 Python/2.7.5
cache-control: no-cache, no-store, must-revalidate, max-age=0
date: Tue, 29 May 2018 05:13:21 GMT
x-frame-options: SAMEORIGIN
content-type: application/json; charset=UTF-8

{u'HEAT_KEYSTONE_PASSWORD': '****', u'CINDER_KEYSTONE_PASSWORD': '****',
u'METADATA_PROXY_SHARED_SECRET': '****', u'WSREP_PASSWORD': '****', u'ETCD_ROOT_PASSWORD':
'****', u'HEAT_DB_PASSWORD': '****', u'CINDER_DB_PASSWORD': '****', u'KEYSTONE_DB_PASSWORD':
'****', u'NOVA_DB_PASSWORD': '****', u'GLANCE_KEYSTONE_PASSWORD': '****',
```

```
u'CLOUDPULSE_KEYSTONE_PASSWORD': '****', u'VPP_ETCD_PASSWORD': '****', u'COBBLER_PASSWORD':
 '****', u'DB_ROOT_PASSWORD': '****', u'NEUTRON_KEYSTONE_PASSWORD': '****',
u'HEAT_STACK_DOMAIN_ADMIN_PASSWORD': '****', u'KIBANA_PASSWORD': '****',
u'IRONIC_KEYSTONE_PASSWORD': '****', u'ADMIN_USER_PASSWORD': '****', u'HAPROXY_PASSWORD':
 '****', u'NEUTRON_DB_PASSWORD': '****', u'IRONIC_DB_PASSWORD': '****', u'GLANCE_DB_PASSWORD':
 '****', u'RABBITMQ_ERLANG_COOKIE': '****', u'NOVA_KEYSTONE_PASSWORD': '****',
u'CPULSE_DB_PASSWORD': '****', u'HORIZON_SECRET_KEY': '****', u'RABBITMQ_PASSWORD': '****'}
```

```
+-----+
| Password Keys |
+-----+
| ADMIN_USER_PASSWORD |
| CINDER_DB_PASSWORD |
| CINDER_KEYSTONE_PASSWORD |
| CLOUDPULSE_KEYSTONE_PASSWORD |
| COBBLER_PASSWORD |
| CPULSE_DB_PASSWORD |
| DB_ROOT_PASSWORD |
| ETCD_ROOT_PASSWORD |
| GLANCE_DB_PASSWORD |
| GLANCE_KEYSTONE_PASSWORD |
| HAPROXY_PASSWORD |
| HEAT_DB_PASSWORD |
| HEAT_KEYSTONE_PASSWORD |
| HEAT_STACK_DOMAIN_ADMIN_PASSWORD |
| HORIZON_SECRET_KEY |
| IRONIC_DB_PASSWORD |
| IRONIC_KEYSTONE_PASSWORD |
| KEYSTONE_DB_PASSWORD |
| KIBANA_PASSWORD |
| METADATA_PROXY_SHARED_SECRET |
| NEUTRON_DB_PASSWORD |
| NEUTRON_KEYSTONE_PASSWORD |
| NOVA_DB_PASSWORD |
| NOVA_KEYSTONE_PASSWORD |
| RABBITMQ_ERLANG_COOKIE |
| RABBITMQ_PASSWORD |
| VPP_ETCD_PASSWORD |
| WSREP_PASSWORD |
+-----+
```

**Examples of Using debug option to get list of nodes**

```
ciscovim --debug list-nodes
2018-05-28 22:13:31,572 DEBUG [ciscovimclient.common.httpclient][MainThread] curl -i -X GET
-H 'Content-Type: application/json' -H 'Authorization: ****' -H 'Accept: application/json'
-H 'User-Agent: python-ciscovimclient' --cacert /var/www/mercury/mercury-ca.crt
https://172.31.231.17:8445/nodes
2018-05-28 22:13:31,599 DEBUG [ciscovimclient.common.httpclient][MainThread]
HTTP/1.1 200 OK
content-length: 2339
x-xss-protection: 1
x-content-type-options: nosniff
strict-transport-security: max-age=31536000
server: WSGIServer/0.1 Python/2.7.5
cache-control: no-cache, no-store, must-revalidate, max-age=0
date: Tue, 29 May 2018 05:13:31 GMT
x-frame-options: SAMEORIGIN
content-type: application/json; charset=UTF-8

{'nodes': {'status': 'Active', 'uuid': '6b1ea6ee-b15b-41ca-9d79-3bb9ec0002bc',
'setupdata': 'fe78b5f9-5a46-447c-9317-2bf7362c1e81', 'node_data': {'rack_info':
{'rack_id': 'RackD'}, 'cimc_info': {'cimc_ip': '172.29.172.81'}, 'management_ip':
'21.0.0.10'}, 'updated_at': '2018-05-25T11:14:46+00:00', 'reboot_required': 'No',
'mtype': 'control', 'install': '372aa3c1-1ab0-4dd0-a8a8-1853a085133c', 'power_status':
```

```
u'PowerOnSuccess', u'install_logs':
u'https://172.31.231.17:8008//edd3975c-8b7c-4d3c-93de-a033ae10a6b6', u'created_at':
u'2018-05-21T13:25:50+00:00', u'name': u'gg34-2'}}
```

```
+-----+-----+-----+-----+
| Node Name | Status | Type | Management IP |
+-----+-----+-----+-----+
gg34-1	Active	control	21.0.0.12
gg34-2	Active	control	21.0.0.10
gg34-3	Active	control	21.0.0.11
gg34-4	Active	compute	21.0.0.13
+-----+-----+-----+-----+
```

### Example of Getting Response from REST API using Curl Commands

Get the REST API Password.

```
cat /opt/cisco/ui_config.json
{
"Kibana-Url": "http://172.31.231.17:5601",
"RestAPI-Url": "https://172.31.231.17:8445",
"RestAPI-Username": "admin",
"RestAPI-Password": "*****",
"RestDB-Password": "*****",
"BuildNodeIP": "172.31.231.17"
}
```

Form the Curl Command.

```
curl -k -u <RestAPI-Username>:<RestAPI-Password> <RestAPI-Url>/<Endpoint>
E.g. To get Nodes Info of Cloud
curl -k -u admin:**** http://172.31.231.17:5601/v1/nodes
```

### Examples of Response of REST APIs

API "/"

```
curl -k -u admin:**** https://172.31.231.17:8445/

{"default_version": {"id": "v1", "links": [{"href": "http://127.0.0.1:8083/v1/", "rel":
"self"}]}, "versions": [{"id": "v1", "links": [{"href": "http://127.0.0.1:8083/v1/", "rel":
"self"}]}], "name": "Virtualized Infrastructure Manager Rest API", "description":
"Virtualized Infrastructure Manager Rest API is used to invoke installer from API."}
```

API "/v1/setupdata/"

```
curl -k -u admin:**** https://172.31.231.17:8445/v1/setupdata/

{"setupdatas": [. . .]}
```

API "/v1/nodes"

```
curl -k -u admin:**** https://172.31.231.17:8445/v1/nodes

{"nodes": [{"status": "Active", "uuid": "0adabc97-f284-425b-ac63-2d336819fbaf", "setupdata":
"fe78b5f9-5a46-447c-9317-2bf7362c1e81", "node_data": {"rack_info": {"rack_id":
\RackC\}, \cimc_info": {"cimc_ip": "172.29.172.75"}, \management_ip":
"21.0.0.13"}}, {"updated_at": "2018-05-21T15:11:05+00:00", "reboot_required": "No", "mtype":
"compute", "install": "372aa3c1-1ab0-4dd0-a8a8-1853a085133c", "power_status":
"PowerOnSuccess", "install_logs":
"https://172.31.231.17:8008//edd3975c-8b7c-4d3c-93de-a033ae10a6b6", "created_at":
"2018-05-21T13:25:50+00:00", "name": "gg34-4"}, . . .]}
```

```

API "/v1/secrets"

curl -k -u admin:**** https://172.31.231.17:8445/v1/secrets

{"HEAT_KEYSTONE_PASSWORD": "5oNff4jWsvAwnWk1", "CINDER_KEYSTONE_PASSWORD": "Hq4i6S5CnfQe7Z2W",
 "RABBITMQ_ERLANG_COOKIE": "XRMHBQHTLVJSVWDFKJUX", "METADATA_PROXY_SHARED_SECRET":
 "XNzrhosqW4rwiz7c", "WSREP_PASSWORD": "z1oQqhKd1fXDxJTV", "ETCD_ROOT_PASSWORD":
 "LMLC8gvilIA3KiIc", "HEAT_DB_PASSWORD": "J8zt8ldMvdtJxAtG", "CINDER_DB_PASSWORD":
 "BVX3y2280DSx2JkY", "KEYSTONE_DB_PASSWORD": "55fVNzxR1VxCNodh", "NOVA_DB_PASSWORD":
 "RklMK1OIJgsjGZal", "IRONIC_KEYSTONE_PASSWORD": "9tYZgIw6SZERZ1dZ", "ADMIN_USER_PASSWORD":
 "DjdQrk4QT7pgHy94", "GLANCE_KEYSTONE_PASSWORD": "w4REb8uhrHquCfRm", "HAPROXY_PASSWORD":
 "oB0v7VJoo2IfB80W", "CLOUDPULSE_KEYSTONE_PASSWORD": "q6QVvxBQhrqv6Zhx", "NEUTRON_DB_PASSWORD":
 "FZVMWgApcZR4us5q", "IRONIC_DB_PASSWORD": "dq3Udmu95DWyX1jy", "GLANCE_DB_PASSWORD":
 "O7vQ2emuPDrrvD4x", "KIBANA_PASSWORD": "azHHhP4ewxpZVwcg", "VPP_ETCD_PASSWORD":
 "NlyIAvECMW2qI7Bp", "NOVA_KEYSTONE_PASSWORD": "JUfMNGz0BZG7JwXV", "NEUTRON_KEYSTONE_PASSWORD":
 "QQ01o8Q87BjFoAYQ", "CPULSE_DB_PASSWORD": "DaFthNtpX2RvwTSS", "COBBLER_PASSWORD":
 "XoIJ9mbWcmVyzvvN", "HORIZON_SECRET_KEY":
 "NHkA0qwHIWUSwhPZowJ8Ge3RyRd6oM8XjOT8PHnZdckxgm3kbb1mS1tsw0TAQJnx", "DB_ROOT_PASSWORD":
 "seqh5DRIKP6ZsKJ8", "HEAT_STACK_DOMAIN_ADMIN_PASSWORD": "Vu6LexEadAxscsvY",
 "RABBITMQ_PASSWORD": "LBoYoxuvGsMsl1TX"}

API "/v1/nodes/mgmt._node"

curl -k -u admin:**** https://172.31.231.17:8445/v1/nodes/mgmt_node

{"api_ip": "172.31.231.17", "mgmt_ip": "21.0.0.2"}

```