



# APPENDIX **A**

## CLI Commands and Scripts

Cisco Prime Collaboration Manager supports the following CLI commands and scripts:

Command/Script Name	CLI User Login	Description
<code>show application status emsam</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the status of the Prime CM application.
<code>show version</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the version details of the Prime CM application.
<code>show application</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the details of the installed application.
<code>application start emsam</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Starts Prime CM application. For example: <code>admin# application start emsam</code>
<code>application stop emsam</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Stops Prime CM application. <code>admin# application stop emsam</code>
<code>show timezones</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays all supported time zones
<code>show timezone</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the configured time zone.
<code>application reset-config emsam</code>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Resets application configuration to factory defaults. You can use this command to reset the password for <i>cmuser</i> and the Prime CM web client <i>admin</i> .  The web client <i>admin</i> password will be reset to <i>admin</i> . You can enter the new password for the <i>cmuser</i> .  For example: <code>admin# application reset-config emsam</code>

Command/Script Name	CLI User Login	Description
<b>username</b> <i>username</i> <b>password</b> <i>plain</i> <i>password</i> <b>role</b> <i>admin</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Change the password for the Prime CM server administrator. This administrator user is configured while deploying the OVA. By default, the administrator user is <i>admin</i> .  You must run this command in the configuration mode (config t).  For example:  admin# <b>config t</b> admin(config)# <b>username</b> <i>cmadmin</i> <b>password</b> <i>plain</i> <b>Emsam!23</b> <b>role</b> <i>admin</i>  We recommend that you note down this password because you cannot recover it.
<b>repository</b> <i>RepositoryName</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Creates a repository.  You must run this command in the configuration mode (config t).  See <a href="#">Performing Backup and Restore</a> for details on how to create repository on a disk and FTP, TFTP, or SFTP server.
<b>backup</b> <i>Backupfilename</i> <b>repository</b> <i>RepositoryName</i> <b>application</b> <i>emsam</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Backs up Prime CM data.  See <a href="#">Performing Backup and Restore</a> for details on how to back up files and how to restore the backed up data.
<b>show repository</b> <i>RepositoryName</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the content of the repository.
<b>show backup history</b>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Displays the backup history.
<b>restore</b> <i>Backupfilename</i> <b>repository</b> <i>RepositoryName</i> <b>application</b> <i>emsam</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Restores the backed up data.  See <a href="#">Performing Backup and Restore</a> for details on how to restore the backed up data.
<b>patch install</b> <i>Patchfilename</i> <i>RepositoryName</i>	The user that you created during OVA configuration. By default, this username is <i>admin</i> .	Installs the Prime CM updates.
<b>resetuserpwd</b>	cmuser	Resets the Prime CM client <i>admin</i> password.  See <a href="#">Resetting the Password for the Cisco Prime CM Web Client admin</a> for details on the script usage.