



Cisco Prime IP Express 8.3 Administration Guide

First Published: 2014-03-04

Last Modified: 2015-12-16

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <http://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

© 2015 Cisco Systems, Inc. All rights reserved.



CONTENTS

PART I

Getting Started 1

CHAPTER 1

Introduction to Cisco Prime IP Express 3

Target Users 3

Regional and Local Clusters 3

Deployment Scenarios 4

Related Topics 5

Small-to-Medium-Size LANs 5

Large Enterprise Networks 5

Configuration and Performance Guidelines 7

Related Topics 7

General Configuration Guidelines 7

Special Configuration Cases 8

Interoperability with Earlier Releases 8

CHAPTER 2

Cisco Prime IP Express User Interfaces 11

Management Components 11

Introduction to the Web-Based User Interfaces 12

Related Topics 12

Supported Web Browsers 13

Access Security 13

Logging In to the Web UIs 13

Multiple Users 14

Changing Passwords 14

Navigating the Web UIs 15

Waiting for Page Resolution Before Proceeding 15

Committing Changes in the Web UIs 15

Role and Attribute Visibility Settings 15

Displaying and Modifying Attributes	16
Grouping and Sorting Attributes	16
Modifying Attributes	16
Displaying Attribute Help	16
Left Navigation Pane and Quick View Icon	17
Help Pages	17
Logging Out	17
Local Cluster Web UI	17
Related Topics	18
Local Basic Main Menu Page	18
Local Advanced Main Menu Page	19
Setting Local User Preferences	20
Configuring Clusters in the Local Web UI	20
Regional Cluster Web UI	20
Related Topics	21
Command Line Interface	21
Global Search in PrimeIP Express	22

CHAPTER 3

Server Status Dashboard 25

Opening the Dashboard	25
Display Types	25
General Status Indicators	26
Graphic Indicators for Levels of Alert	26
Magnifying and Converting Charts	27
Legends	27
Tables	27
Line Charts	27
Stacked Area Charts	29
Other Chart Types	30
Getting Help for the Dashboard Elements	31
Customizing the Display	31
Refreshing Displays	31
Setting the Polling Interval	32
Displaying Charts as Tables	32
Exporting to CSV Format	32

Displaying or Hiding Chart Legends	33
Selecting Dashboard Elements to Include	33
Configuring Server Chart Types	33
Host Metrics	35
System Metrics	35
How to Interpret the Data	35
Troubleshooting Based on the Results	36

PART II

Local and Regional Administrator 37

CHAPTER 4

Managing Administrators 39

Administrators, Groups and Roles	39
Related Topics	39
How Administrators Relate to Groups and Roles	40
Administrator Types	40
Roles, Subroles, and Constraints	41
Groups	44
External Authentication Servers	45
Configuring an RADIUS External Authentication Server	45
Adding an RADIUS External Configuration Server	46
CLI Commands	46
Deleting an RADIUS External Authentication Server	46
Configuring an AD External Authentication Server	46
Configuring Kerbero's Realm and KDC	47
Adding an AD External Configuration Server	47
CLI Commands	48
Deleting an AD External Authentication Server	48
Managing Administrators	48
Adding Administrators	49
Local and Regional Web UI	49
Editing Administrators	49
Deleting Administrators	49
Managing Passwords	49
Managing Groups	50
Adding Groups	50

Local Advanced and Regional Web UI	50
Editing Groups	50
Deleting Groups	50
Managing Roles	51
Adding Roles	51
Local Advanced Web UI	51
Regional Advanced Web UI	51
Editing Roles	51
Deleting Roles	52
CLI Commands	52
Granular Administration	52
Local Advanced and Regional Web UI	52
Related Topics	52
Scope-Level Constraints	53
Local Advanced Web UI	54
Prefix-Level Constraints	54
Local Advanced and Regional Web UI	55
Local Advanced and Regional Web UI	55
Link-Level Constraints	55
Local Advanced and Regional Web UI	56
Centrally Managing Administrators	56
Related Topics	56
Pushing and Pulling Administrators	57
Related Topics	57
Pushing Administrators to Local Clusters	57
Regional Basic and Advanced Web UI	57
Pushing Administrators Automatically to Local Clusters	57
Regional Basic and Advanced Web UI	58
Connecting to CLI in Regional Mode	58
Pulling Administrators from the Replica Database	58
Regional Basic and Advanced Web UI	58
Pushing and Pulling External Authentication Servers	59
Pushing RADIUS External Authentication Servers	59
Pulling RADIUS External Authentication Servers	59
Pushing AD External Authentication Servers	60

Pulling AD External Authentication Servers	60
Pushing and Pulling Groups	61
Related Topics	61
Pushing Groups to Local Clusters	61
Regional Basic and Advanced Web UI	61
Pulling Groups from the Replica Database	62
Regional Basic and Advanced Web UI	62
Pushing and Pulling Roles	62
Related Topics	63
Pushing Roles to Local Clusters	63
Regional Advanced Web UI	63
Pulling Roles from the Replica Database	63
Regional Advanced Web UI	64

CHAPTER 5

Managing Owners and Regions 65

Managing Owners	65
Local Advanced and Regional Advanced Web UI	65
CLI Commands	65
Managing Regions	66
Local Advanced and Regional Advanced Web UI	66
CLI Commands	66
Centrally Managing Owners and Regions	66
Related Topics	67
Pushing and Pulling Owners or Regions	67
Related Topics	67
Pushing Owners or Regions to Local Clusters	67
Regional Web UI	67
Pulling Owners and Regions from the Replica Database	67
Regional Web UI	68

CHAPTER 6

Managing the Central Configuration 69

Central Configuration Tasks	69
Default Ports for Cisco Prime IP Express Services	70
Firewall Considerations	71
Licensing	71

Regional Web UI	72
CLI Commands	72
Adding License	72
Registering a Local Cluster that is Behind a NAT	73
CLI Commands	74
License History	74
Regional Web UI	74
CLI Command	74
Configuring Server Clusters	74
Related Topics	75
Adding Local Clusters	75
Regional Web UI	75
Local Web UI	76
CLI Commands	76
Editing Local Clusters	76
Regional Web UI	76
Local Web UI	76
CLI Commands	76
Listing Related Servers for DHCP, DNS, and TCP Listener Servers	77
Regional Web UI	77
CLI Commands	86
Connecting to Local Clusters	86
Synchronizing with Local Clusters	86
Replicating Local Cluster Data	86
Viewing Replica Data	87
Regional Web UI	87
Purging Replica Data	87
Deactivating, Reactivating, and Recovering Data for Clusters	87
Regional Web UI	88
Central Configuration Management Server	88
Managing CCM Server	89
Editing CCM Server Properties	89
Local Basic or Advanced Web UI	89
Simple Network Management	89
Related Topics	90

Setting Up the SNMP Server	90
Local Basic or Advanced and Regional Web UI	91
CLI Commands	91
How Notification Works	92
Handling SNMP Notification Events	93
DHCP v4 Notification	93
DHCP v6 Notification	94
Handling Deactivated Scopes or Prefixes	94
Local Basic or Advanced Web UI	94
To edit a trap configuration, do the following:	95
Deleting Trap Configuration	95
Regional Basic or Advanced Web UI	95
Server Up/Down Traps	95
CLI Commands	96
Handling SNMP Queries	96
Integrating Cisco PrimeIP Express SNMP into System SNMP	97
Bring Your Own Device Web Server	97
Managing BYOD Web Server	97
Editing BYOD Web Server Properties	97
Setting Up BYOD Theme and Content	98
Adding and Previewing BYOD Themes	98
Adding and Previewing BYOD Content	99
Polling Process	99
Polling Lease History Data	100
Related Topics	100
Adjusting the Polling Intervals	100
Enabling Lease History Collection	101
Managing DHCP Scope Templates	101
Related Topics	101
Pushing Scope Templates to Local Clusters	101
Regional Web UI	102
Pulling Scope Templates from Replica Data	102
Regional Web UI	102
Managing DHCP Policies	103
Related Topics	103

Pushing Policies to Local Clusters	103
Regional Web UI	103
Pulling Policies from Replica Data	103
Regional Web UI	104
Managing DHCP Client-Classes	104
Related Topics	104
Pushing Client-Classes to Local Clusters	104
Regional Web UI	105
Pulling Client-Classes from Replica Data	105
Regional Web UI	105
Managing Virtual Private Networks	105
Related Topics	106
Pushing VPNs to Local Clusters	106
Regional Web UI	106
Pulling VPNs from Replica Data	106
Managing DHCP Failover Pairs	107
Regional Web UI	107
Managing Lease Reservations	107
Related Topics	108
DHCPv4 Reservations	108
DHCPv6 Reservations	108
Regional Web UI	108
Monitoring Resource Limit Alarms	109
Configuring Resource Limit Alarm Thresholds	110
CLI Commands	110
Setting Resource Limit Alarms Polling Interval	111
Viewing Resource Limit Alarms	111
Resetting Resource Limit Alarms Peak Value	111
CLI Commands	111
Export Resource Limit Alarms Data	112
Local Cluster Management Tutorial	112
Related Topics	112
Administrator Responsibilities and Tasks	112
Create the Administrators	113
Local Basic Web UI	113

Create the Address Infrastructure	114
Local Advanced Web UI	114
Create the Zone Infrastructure	114
Related Topics	114
Create the Forward Zones	115
Local Basic Web UI	115
Create the Reverse Zones	115
Local Basic Web UI	115
Create the Initial Hosts	116
Local Advanced Web UI	116
Create a Host Administrator Role with Constraints	116
Local Advanced Web UI	116
Create a Group to Assign to the Host Administrator	118
Local Advanced Web UI	118
Test the Host Address Range	119
Local Advanced Web UI	119
Regional Cluster Management Tutorial	119
Related Topics	120
Administrator Responsibilities and Tasks	120
Create the Regional Cluster Administrator	120
Regional Web UI	121
Create the Central Configuration Administrator	121
Regional Web UI	121
Create the Local Clusters	121
Regional Web UI	122
Add Zone Management to the Configuration Administrator	122
Regional Web UI	123
Create a Zone for the Local Cluster	123
Regional Web UI	123
Pull Zone Data and Create a Zone Distribution	123
Regional Web UI	124
Create a Subnet and Pull Address Space	124
Regional Web UI	124
Push a DHCP Policy	125
Regional Web UI	125

Create a Scope Template	125
Regional Web UI	126
Create and Synchronize the Failover Pair	126
Regional Web UI	126

CHAPTER 7
Maintaining Servers and Databases 129

Managing Servers	129
Local Basic or Advanced and Regional Web UI	130
CLI Commands	131
Scheduling Recurring Tasks	131
Local Basic or Advanced Web UI	132
Logs	133
Log Files	133
CLI Commands	134
Logging Server Events	134
Local Basic or Advanced and Regional Web UI	134
Related Topics	135
Logging Format and Settings	135
Local Basic or Advanced and Regional Web UI	135
CLI Commands	135
Searching the Logs	135
View Change Log	136
Local Basic and Advanced Web UI	136
Dynamic Update on Server Log Settings	136
Local Basic or Advanced Web UI	137
Local Basic or Advanced Web UI	137
CLI Commands	137
Running Data Consistency Rules	137
Local Basic or Advanced and Regional Web UI	138
CLI Tool	138
Monitoring and Reporting Server Status	140
Related Topics	141
Server States	141
Displaying Health	141
Server Health Status	142

Local Basic or Advanced and Regional Web UI	143
CLI Commands	143
Displaying Statistics	143
Local Basic or Advanced and Regional Web UI	143
CLI Commands	144
DNS Statistics	144
CDNS Statistics	146
DHCP Statistics	150
Displaying IP Address Usage	152
Local Advanced and Regional Web UI	152
CLI Commands	152
Displaying Related Servers	153
Related Topics	153
Monitoring Remote Servers Using Persistent Events	153
DNS Zone Distribution Servers	154
Local Basic or Advanced Web UI	154
Regional Web UI	154
CLI Commands	155
DHCP Failover Servers	155
Local Basic or Advanced Web UI	155
CLI Commands	155
Displaying Leases	155
Local Basic or Advanced Web UI	155
Regional Web UI	155
Troubleshooting DHCP and DNS Servers	156
Related Topics	156
Immediate Troubleshooting Actions	156
Modifying the cnr.conf File	156
Modifying the cnr.conf File for Syslog Support	157
Troubleshooting Server Failures	158
Linux Troubleshooting Tools	159
Using the TAC Tool	160

CHAPTER 8
Backup and Recovery 161

Backing Up Databases	161
----------------------	-----

Related Topics	161
Syntax and Location	162
Backup Strategy	162
Manual Backup (Using <code>cnr_shadow_backup</code> utility)	162
Related Topics	163
Setting Automatic Backup Time	163
Performing Manual Backups	163
Using Third-Party Backup Programs with <code>cnr_shadow_backup</code>	164
Backing Up CNRDB Data	164
Backing Up All CNRDBs Using tar or Similar Tools	165
Database Recovery Strategy	165
Recovering CNRDB Data from Backups	167
Recovering All CNRDBs Using tar or Similar Tools	167
Recovering Single CNRDB from tar or Similar Tools	168
Virus Scanning While Running Cisco Prime IP Express	168
Troubleshooting Databases	168
Related Topics	169
Using the <code>cnr_exim</code> Data Import and Export Tool	169
Using the <code>cnrdb_recover</code> Utility	171
Using the <code>cnrdb_verify</code> Utility	172
Using the <code>cnrdb_checkpoint</code> Utility	173
Using the <code>cnrdb_util</code> Utility	173
Restoring DHCP Data from a Failover Server	175
On Windows	175
On Linux	175

CHAPTER 9

Managing Reports 177

ARIN Reports and Allocation Reports	177
Managing ARIN Reports	178
Related Topics	178
Managing Point of Contact and Organization Reports	178
Related Topics	179
Creating a Point of Contact Report	179
Regional Web UI	179
Registering a Point of Contact	179

Regional Web UI 179

Editing a Point of Contact Report 180

Regional Web UI 180

Creating an Organization Report 180

Regional Web UI 180

Registering an Organization 181

Regional Web UI 181

Editing an Organization Report 181

Regional Web UI 181

Managing IPv4 Address Space Utilization Reports 181

Regional Web UI 182

Managing Shared WHOIS Project Allocation and Assignment Reports 182

Managing BYOD Reports 183

Registered Devices 183

Registered Devices Report 183

Scopes/Prefix 183

Scope/Prefix Report 183

PART III

Virtual Appliance 185

CHAPTER 10

Introduction to Cisco Prime IP Express Virtual Appliance 187

How the Cisco Prime IP Express Virtual Appliance Works 187

How to Download the Cisco Prime IP Express Virtual Appliance 188

Invoking Cisco Prime IP Express on the Virtual Appliance 188

Monitoring Disk Space Availability 188

Monitoring Disk Space Availability (Using the Console) 189

Increasing the Size of Disk 189

Troubleshooting 190

Glossary 191



PART **I**

Getting Started

- [Introduction to Cisco Prime IP Express, page 3](#)
- [Cisco Prime IP Express User Interfaces, page 11](#)
- [Server Status Dashboard, page 25](#)



CHAPTER

1

Introduction to Cisco Prime IP Express

Cisco Prime IP Express is a full featured, scalable Domain Name System (DNS) and Dynamic Host Configuration Protocol (DHCP) implementation for medium to large IP networks. It provides the key benefits of stabilizing the IP infrastructure and automating networking services, such as configuring clients and provisioning cable modems. This provides a foundation for policy-based networking.

Enterprise users can better manage their networks to integrate with other network infrastructure software and business applications.

- [Target Users, page 3](#)
- [Regional and Local Clusters, page 3](#)
- [Deployment Scenarios, page 4](#)
- [Configuration and Performance Guidelines, page 7](#)

Target Users

Cisco Prime IP Express is designed for these users:


- **Enterprises**—Helps meet the needs of single- and multisite enterprises (small-to-large businesses) to administer and control network functions. Cisco Prime IP Express automates the tasks of assigning IP addresses and configuring the Transport Control Protocol/Internet Protocol (TCP/IP) software for individual network devices. Forward-looking enterprise users can benefit from class-of-service and other features that help integrate with new or existing network management applications, such as user registration.

Regional and Local Clusters

The regional cluster acts as an aggregate management system for up to a hundred local clusters. Address and server administrators interact at the regional and local clusters through the regional and local web-based user interfaces (web UIs), and local cluster administrators can continue to use the command line interface (CLI) at the local cluster. The regional cluster consists of a Central Configuration Management (CCM) server, Tomcat web server, servlet engine, and server agent (see [Management Components, on page 11](#)). The license management is now done at the regional cluster and hence the local server has to be registered to a regional

server to avail the necessary services. See the "Overview" chapter in *Cisco Prime IP Express Installation Guide* for more details.

Figure 1: Cisco Prime IP Express User Interfaces and Server Clusters



A typical deployment is one regional cluster at a customer network operation center (NOC), the central point of network operations for an organization. Each division of the organization includes a local address management server cluster responsible for managing a part of the network. The System Configuration Protocol (SCP) communicates the configuration changes between the servers.

Deployment Scenarios

The Cisco Prime IP Express regional cluster web UI provides a single point to manage any number of local clusters hosting DNS, CDNS or DHCP servers. The regional and local clusters also provide administrator management so that you can assign administrative roles to users logged in to the application.

This section describes two basic administrative scenarios and the hardware and software deployments for two different types of installations—a small-to-medium local area network (LAN), and a large-enterprise or service-provider network with three geographic locations.

Related Topics

[Small-to-Medium-Size LANs, on page 5](#)

[Large Enterprise Networks, on page 5](#)

Small-to-Medium-Size LANs


In this scenario, low-end Windows or Linux servers are acceptable. You can also use systems with EIDE disks, although we recommend you use Ultra-SCSI disks for dynamic DNS update. The image below shows a configuration that would be adequate for this network.



Note

Regional server is MUST in deployment for small and medium sized LANs.

Figure 2: Small-to-Medium LAN Configuration




Large Enterprise Networks

In a large enterprise network serving over 500,000 DHCP clients use mid-range Windows or Linux servers. Put DNS and DHCP servers on different systems. The image below shows the hardware that would be adequate for this network.

When supporting geographically dispersed clients, locate DHCP servers at remote locations to avoid disrupting local services if wide-area connections fail. Install the Cisco Prime IP Express regional cluster to centrally manage the distributed clusters.

Figure 3: Large Enterprise Network Configuration



36271.2

Configuration and Performance Guidelines

Cisco Prime IP Express is an integrated DHCP and DNS server cluster capable of running on a Windows, or Linux workstation or server.

Because of the wide range of network topologies for which you can deploy Cisco Prime IP Express, you should first consider the following guidelines. These guidelines are very general and cover most cases. Specific or challenging implementations could require additional hardware or servers.

Related Topics

[General Configuration Guidelines, on page 7](#)

[Special Configuration Cases, on page 8](#)

General Configuration Guidelines

The following suggestions apply to most Cisco Prime IP Express deployments:

- Configure a separate DHCP server to run in remote segments of the wide area network (WAN). Ensure that the DHCP client can consistently send a packet to the server in under a second. The DHCP protocol dictates that the client receive a response to a DHCPDISCOVER or DHCPREQUEST packet within four seconds of transmission. Many clients (notably early releases of the Microsoft DHCP stack) actually implement a two-second timeout.
- In large deployments, separate the secondary DHCP server from the primary DNS server used for dynamic DNS updates. Because lease requests and dynamic DNS updates are persisted to disk, server performance is impacted when using a common disk system. So that the DNS server is not adversely affected, run it on a different cluster than the DHCP server.
- Include a time server in your configuration to deal with time differences between the local and regional clusters so that aggregated data at the regional server appears in a consistent way. See the [Polling Lease History Data, on page 100](#).
- Set DHCP lease times in policies to four to ten days. To prevent leases from expiring when the DHCP client is turned off (overnight or over long weekends), set the DHCP lease time longer than the longest period of expected downtime, such as seven days. See *"Managing Leases" section in Cisco Prime IP Express 8.3 DHCP User Guide*.
- Locate backup DNS servers on separate network segments. DNS servers are redundant by nature. However, to minimize client impact during a network failure, ensure that primary and secondary DNS servers are on separate network segments.
- If there are high dynamic DNS update rates in the network, configure separate DNS servers for forward and reverse zones.
- Use NOTIFY/IXFR. Secondary DNS servers can receive their data from the primary DNS server in two ways: through a full zone transfer (AXFR) or an incremental zone transfer (NOTIFY/IXFR, as described in RFCs 1995 and 1996). Use NOTIFY/IXFR in environments where the name space is relatively dynamic. This reduces the number of records transferred from the primary to the secondary server. See the *"Enabling Incremental*

Zone Transfers (IXFR)" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide.

Special Configuration Cases

The following suggestions apply to some special configurations:

- When using dynamic DNS updates for large deployments or very dynamic networks, divide primary and secondary DNS and DHCP servers across multiple clusters.
Dynamic DNS updates generate an additional load on all Cisco Prime IP Express servers as new DHCP lease requests trigger dynamic DNS updates to primary servers that update secondary servers through zone transfers.
- During network reconfiguration, set DHCP lease renewal times to a small value.
Do this several days before making changes in network infrastructure (such as to gateway router and DNS server addresses). A renewal time of eight hours ensures that all DHCP clients receive a changed DHCP option parameter within one working day. See the *"Managing Leases" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*

Interoperability with Earlier Releases

The following table shows the interoperability of Cisco Prime Network Registrar / Cisco Prime IP Express features on the regional CCM server with versions of the local cluster.

Table 1: CCM Regional Feature Interoperability with Server Versions

Feature	Local Cluster Version				8.3 (CPNR/CPIPE)
	7.2 (CPNR)	8.0 (CPNR)	8.1 (CPNR)	8.2 (CPNR/CPIPE)	
Push and pull:	x	x	x	x	x
Address space	x	x	x	x	x
IPv6 address space	x	x	x	x	x
Scope templates, policies, client-classes	x	x	x	x	x
IPv6 prefix and link templates	x	x	x	x	x
Zone data and templates	x	x	x	x	x
Groups, owners, regions	x	x	x	x	x
Resource records (RRs)	x	x	x	x	x
Local cluster restoration	x	x	x	x	x
Host administration	x	x	x	x	x
Extended host administration	x	x	x	x	x
Administrators and roles				x	x
Zone Views					

Feature	Local Cluster Version				8.3 (CPNR/CPIPE)
	7.2 (CPNR)	8.0 (CPNR)	8.1 (CPNR)	8.2 (CPNR/CPIPE)	
Administrator:	x	x	x	x	x
Single sign-on	x	x	x	x	x
Password change					
IP history reporting:	x	x	x	x	x
Lease history	x	x	x	x	x
Detailed lease history					
Utilization reporting:	x	x	x	x	x
Subnet utilization history	x	x	x	x	x
Subnet and scope utilization	x	x	x	x	x
IPv6 prefix utilization					



Cisco Prime IP Express User Interfaces

Cisco Prime IP Express provides a regional and a local web UI and a regional and local CLI to manage the CDNS, DNS, DHCP, and CCM servers:

- **Web UI for the regional cluster to access local cluster servers**—See [Regional Cluster Web UI](#), on page 20.
- **Web UI for the local cluster**—See [Local Cluster Web UI](#), on page 17.
- **CLI for the local clusters**—Open the `CLIContent.html` file in the installation `/docs` directory (see [Command Line Interface](#), on page 21).
- **CCM servers that provide the infrastructure to support these interfaces**— See [Central Configuration Management Server](#), on page 88.

This chapter describes the Cisco Prime IP Express user interfaces and the services that the CCM servers provide. Read this chapter before starting to configure the Cisco Prime IP Express servers so that you become familiar with each user interface capability.

- [Management Components](#), page 11
- [Introduction to the Web-Based User Interfaces](#), page 12
- [Local Cluster Web UI](#), page 17
- [Regional Cluster Web UI](#), page 20
- [Command Line Interface](#), page 21
- [Global Search in PrimeIP Express](#), page 22

Management Components

Cisco Prime IP Express contains two management components:

- Regional component, consisting of:
 - Web UI
 - CLI
 - CCM Server

- Bring your own device (BYOD)
- Local component, consisting of:
 - Web UI
 - CLI
 - CCM server
 - Authoritative Domain Name System (DNS) server
 - Caching / Recursive Domain Name System (CDNS) server
 - Dynamic Host Configuration Protocol (DHCP) server
 - Simple Network Management Protocol (SNMP) server
 - Management of local address space, zones, scopes, DHCPv6 prefixes and links, and users

**Note**

We do not recommend configuring both DNS and Caching DNS services in one server.

License management is done from the regional cluster when Cisco Prime IP Express is installed. You must install the regional server first and load all licenses in the regional server. When you install the local cluster, it registers with regional to obtain its license.

The regional CCM server provides central management of local clusters, with an aggregated view of DHCP address space and DNS zones. It provides management of the distributed address space, zones, scopes, DHCPv6 prefixes and links, and users.

The local CCM server provides management of the local address space, zones, scopes, DHCPv6 prefixes and links, and users.

The remainder of this chapter describes the SNMP protocols. The CCM server, web UIs, and CLI are described in [Cisco Prime IP Express User Interfaces, on page 11](#). The DNS, CDNS and DHCP servers are described in their respective sections.

Introduction to the Web-Based User Interfaces

The web UI provides granular access to configuration data through user roles and constraints. The UI provides quick access to common functions. The web UI granularity is described in the following sections.

Related Topics

[Supported Web Browsers, on page 13](#)

[Access Security, on page 13](#)

[Logging In to the Web UIs, on page 13](#)

[Multiple Users, on page 14](#)

[Changing Passwords, on page 14](#)

[Navigating the Web UIs, on page 15](#)

[Waiting for Page Resolution Before Proceeding, on page 15](#)

[Committing Changes in the Web UIs, on page 15](#)

[Role and Attribute Visibility Settings, on page 15](#)

[Displaying and Modifying Attributes, on page 16](#)

[Help Pages, on page 17](#)

[Logging Out, on page 17](#)

Supported Web Browsers

The web UI has been tested on Microsoft Internet Explorer 9 and Mozilla Firefox 21 and later. Internet Explorer 8 is not supported.

Access Security

At Cisco Prime IP Express installation, you can choose to configure HTTPS to support secure client access to the web UIs. You must specify the HTTPS port number and provide the keystore at that time. With HTTPS security in effect, the web UI Login page indicates that the “Page is [SSL¹ Secure](#).”



Note

Do not use a dollar sign (\$) symbol as part of a keystore password.

Logging In to the Web UIs

You can log into the Cisco Prime IP Express local or regional cluster web UIs either by HTTPS secure or HTTP nonsecure login. After installing Cisco Prime IP Express, open one of the supported web browsers and specify the login location URL in the browser address or netsite field. Login is convenient and provides some memory features to increase login speed.

You can log in using a nonsecure login in two ways:

- On Windows, from the Start menu, choose **Start > All Programs > IP Express 8.3 > IP Express 8.3 {local | regional} Web UI**. This opens the local or regional cluster web UI from your default web browser.



Note

Open the regional Web UI first and add the licenses for the required services.

- Open the web browser and go to the web site. For example, if default ports were used during the installation, the URLs would be **http://hostname:8080** for the local cluster web UI, and **http://hostname:8090** for the regional cluster web UI.

This opens the New Product Installation page if no valid license is added at the time of installation. You have to browse and add the valid license. If the license key is acceptable, the Cisco Prime IP Express login page is displayed.

¹ This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

**Note**

You can add the licenses only in the regional server. The local has to be registered to the regional at the time of installation to run the desired licensed services.

In the local server, confirm the regional server IP address and port number and also the services you want to run at the time of your first login. Click **Register** to confirm registration. If the regional server is configured with the required licenses, you will be displayed the login page.

Enter the superuser username and password created at the time of installation to log into the Web UI. The password is case-sensitive (See [Managing Passwords, on page 49](#)). If you already added the valid license and superuser and configured a password at the time of installation, then you can log into the web UI using that username and password.

**Note**

There is no default username or password for login.

**Note**

To prepare for an HTTPS-secured login, see *Cisco Prime IP Express Installation Guide*.

Depending on how your browser is set up, you might be able to abbreviate the account name or choose it from a drop-down list while setting the username.

To log in, click **Login**.

Multiple Users

The Cisco Prime IP Express user interfaces support multiple, concurrent users. If two users try to access the same object record or data, a **Modified object** error will occur for the second user. If you receive this error while editing user data, do the following:

- **In the web UI**—Cancel the edits and refresh the list. Changes made by the first user will be reflected in the list. Redo the edits, if necessary.
- **In the CLI**—Use the **session cache refresh** command to clear the current edits, before viewing the changes and making further edits. Make changes, if you feel that it is necessary even after the other user's changes.

Changing Passwords

Whenever you edit a password on a web UI page, it is displayed as a string of eight dots. The actual password value is never sent to the web browser. So, if you change the password, the field is automatically cleared. You must enter the new password value completely, exactly as you want it to be.

**Note**

The password should not be more than 255 characters long.

For details on changing administrator passwords at the local and regional cluster, see [Managing Passwords, on page 49](#).

Navigating the Web UIs


The web UI provides a hierarchy of pages based on the functionality you desire and the thread you are following as part of your administration tasks. The page hierarchy prevents you from getting lost easily.




Caution

Do not use the Back button of the browser. Always use the navigation bar menu, or the **Cancel** button on the page to return to a previous page. Using the browser Back button can cause erratic behavior or can cause failures.

A single sign-on feature is available to connect between the regional and local cluster web UIs. The regional

cluster web UI pages include the Connect button () in the List/Add Remote clusters page, which you can click to connect to the local cluster associated with the icon. If you have single sign-on privileges to the local cluster, the connection takes you to the related local server management page (or a related page for related server configurations). If you do not have these privileges, the connection takes you to the login page for the

local cluster. To return to the regional cluster, local cluster pages have the Return button () on the main toolbar.



Note

Navigation bar items can vary based on if you have the role privileges for IPv4 or IPv6. For example, the **Design** menu bar can be **DHCPv4** and **DHCPv6** if you have the ipv6-management subrole of the addrblock-admin role assigned.

Waiting for Page Resolution Before Proceeding

Operations performed in the web UI, such as resynchronizing or replicating data from server clusters, are synchronous in that they do not return control to the browser until the operation is completed. These operations display confirmation messages in blue text. Also, both the Netscape and IE browsers display a wait cursor while the operation is in progress.



Tip


Wait for each operation in the web UI to finish before you begin a new operation. If the browser becomes impaired, close the browser, reopen it, then log in again. Some operations like zone distributions can take significant amount of time, so you may have to wait till the operation completes.

Committing Changes in the Web UIs

You do not actually commit the page entries you make until you click **Save** on the page. You can delete items using the delete icon. To prevent unwanted deletions, a Confirm Delete dialog box appears in many cases so that you have a chance to confirm or cancel the deletion.

Role and Attribute Visibility Settings

Click the *username* drop-down list on the top of the main page to modify user preferences, session settings, user permissions, or debug settings.

- To view the user groups and roles for the administrator, select the **User Preferences** option. Superuser is a special kind of administrator. (For details how to set up these administrator roles, see [Create the Administrators](#), on page 113.)
- Select **Session Settings** to open the Session Settings dialog, select the mode from the **Session Web UI Mode** drop-down list, and click **Modify Session Settings**. You can also click the drop-down arrow of the Mode icon () to view the list of modes. Select the required mode from the list:
 - **Basic**—Basic user mode (the preset choice).
 - **Advanced**—Advanced user mode that exposes the normal attributes.
 - **Expert**—Expert user mode that exposes a set of attributes that are relevant for fine-tuning or troubleshooting the configuration. In most cases, you would accept the default values for these expert attributes and not change them without guidance from the Cisco Technical Assistance Center (TAC). Each Expert mode attribute is marked with a Warning icon on the configuration pages. Each page is clearly marked as being in Expert mode.

Displaying and Modifying Attributes

Many of the web UI pages, such as those for servers, zones, and scopes, include attribute settings that correspond to those you can set using the CLI. (The CLI name equivalents appear under the attribute name.) The attributes are categorized into groups by their function, with the more prominent attributes listed first and the ones less often configured nearer the bottom of the page.

Grouping and Sorting Attributes

On many Advanced mode web UI pages, you can toggle between showing attributes in groups and in alphabetical order. These pages generally open by default in group view so that you can see the attributes in their respective categories. However, in the case of large numbers of attributes, you might want to see the attributes alphabetized. Click **Show A-Z View** to change the page to show the attributes alphabetically. Click **Show Group View** to change the page to show the attributes in groups. You can also expand or collapse the attribute groups in group view by clicking **Expand All** or **Collapse All**. In Expert mode, the Expert mode attributes are alphabetized separately further down the page under the Visibility=3 heading and are all marked with the Warning icon.

Modifying Attributes

You can modify attribute values and unset those for optional attributes. In many cases, these attributes have preset values, which are listed under the Default column on the page. The explicit value overrides the default one, but the default one is always the fallback. If there is no default value, unsetting the explicit value removes all values for that attribute.

Displaying Attribute Help

For contextual help for an attribute, click the name of the attribute to open a separate popup window.

Left Navigation Pane and Quick View Icon

The Web UI also provides a navigation pane on the left of the main pages. This navigation pane provides access to objects that are added as part of the various categories. You can click the object to edit its properties in the main page.

Each object displayed under a category in the pane also has a Quick View icon associated with it, which is activated when you move the mouse pointer over the object. The Quick View icon expands to open a dialog box that displays the main details about the object, and provides links (if any) to perform the main actions associated with the object.

Help Pages

The web UI provides a separate window that displays help text for each page. The Help pages provide:

- A context-sensitive help topic depending on which application page you have open.
- A clickable and hierarchical Contents and Index, and a Favorites setting, as tabs on a left-hand pane that you can show or hide.
- A Search facility that returns a list of topics containing the search string, ordered by frequency of appearance of the search string.
- Forward and backward navigation through the history of Help pages opened.
- A Print function.
- A Glossary.

Logging Out

Log out of the web UI by clicking **Log Out** link. You can find the **Log Out** link between the *username* drop-down list and the **About** link at the top right corner of the application page above the toolbar.

Local Cluster Web UI

The local cluster web UI provides concurrent access to Cisco Prime IP Express user and protocol server administration and configuration. It provides granular administration across servers with permissions you can set on a per element or feature basis. The local cluster web UI is available in three user modes:

- **Basic Mode**— Provides a more simplified configuration for the more frequently configured objects, such as DHCP scopes and DNS zones (see [Local Basic Main Menu Page](#), on page 18).
- **Advanced Mode**— Provides the more advanced configuration method familiar to past users of the Cisco PrimeIP Express web UI, with some enhancements (see [Local Advanced Main Menu Page](#), on page 19).
- **Expert Mode** (marked with the icon)-For details on Expert mode, see [Role and Attribute Visibility Settings](#), on page 15.

Change to Basic, Advanced, or Expert mode by clicking the drop-down arrow of the Mode icon () on the toolbar at the top right of the page (see [Setting Local User Preferences](#), on page 20).

**Note**


If you change the IP address of your local cluster machine, see the Note in [Configuring Clusters in the Local Web UI](#), on page 20.

Related Topics

[Introduction to the Web-Based User Interfaces](#), on page 12

[Regional Cluster Web UI](#), on page 20

Local Basic Main Menu Page

The Basic tab activated on the toolbar at the top right corner of the page implies that you are in Basic user mode. Otherwise, click the drop-down arrow of the Mode icon () to view the list of modes and select **Basic**.

You can see the submenu items under the navigation bar item by placing the cursor on the main menu. To choose a submenu under a navigation bar item, place the cursor over the navigation bar item. For example, place the cursor on **Operate** to choose the **Manage Servers**.


Also, you can select any submenu under the required navigation bar and then navigate to the required submenu page from the left pane. For example, place the cursor on **Operate**, choose **Schedule Tasks**. You can see List/Add Scheduled Tasks page along with a left pane that has links to Manage Servers, Manage Clusters, Schedule Tasks, and View Change Log. Click the **Manage Servers** link to view the Manage Servers page.

The Local Basic main menu page provides functions with which you can:


- **Open the dashboard to monitor system health**—Open **Operate** menu and click **Dashboard**. See the "Server Status Dashboard" chapter.
- **Set up a basic configuration by using the Setup interview pages**—Click the **Setup** icon at the top, and select the different tabs in the Setup page. See *Cisco Prime IP Express Quick Start Guide* for more details.
- **Administer users, encryption keys**—Place the cursor on **Administration** menu (for user access options) or **Design** menu (for Security > Keys option). See [Managing Administrators](#), on page 39.
- **Manage the Cisco PrimeIP Express protocol servers**—Place the cursor on **Operate** menu and select **Manage Servers** or **Schedule Tasks** option. See [Maintaining Servers and Databases](#), on page 129.
- **Manage clusters**—Place the cursor on **Operate** menu and choose **Manage Clusters** option. See [Configuring Server Clusters](#), on page 74.
- **Configure DHCP**—Place the cursor on **Design** menu and select the options under **DHCP Settings**, **DHCPv4** or **DHCPv6**. See the "Configuring Scopes and Networks" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **Configure DNS**—Place the cursor on **Design** menu and select the options under **Cache DNS** and **Auth DNS**. Place the cursor on **Deploy** menu and select the options under **DNS** and **DNS Updates**. See the "Managing Zones" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.
- **Manage hosts in zones**—From the **Design** menu, choose **Hosts** under the **Auth DNS** submenu. See the "Managing Hosts" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.

- **Go to Advanced mode**—Click **Advanced** in the top right corner of the page. See [Local Advanced Main Menu Page](#), on page 19.

Local Advanced Main Menu Page

To switch to Advanced user mode from the Basic user Main Menu page, click the drop-down arrow of the Mode icon () at the top right of the window to view the list of modes and select **Advanced**. Doing so opens another Main Menu page, except that it shows the Advanced user mode functions. To switch back to Basic mode at any time, click next to the Mode icon at the top right of the window and select **Basic**.

The local Advanced mode Main Menu page includes advanced Cisco Prime IP Express functions that are in addition to the ones in Basic mode:

- **Open the dashboard to monitor system health**—Open **Operate** menu and click **Dashboard**. See the "Server Status Dashboard" chapter.
- **Administer users, groups, roles, regions, access control lists (ACLs), and view change logs**—Place the cursor on **Administration** menu (for user access options), **Design** menu (for ACLs) or **Operate** menu (for change logs). See [Managing Administrators](#), on page 39.
- **Manage the Cisco PrimeIP Express protocol servers**—Place the cursor on **Operate** menu and select **Manage Servers** or **Schedule Tasks** option. See [Maintaining Servers and Databases](#), on page 129.
- **Manage clusters**—Place the cursor on **Operate** menu and choose **Manage Clusters** option. See [Configuring Server Clusters](#), on page 74.
- **Configure DHCPv4**—Place the cursor on **Design** and select any option under **DHCPv4**. See the "Configuring Scopes and Networks" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **Configure DHCPv6**—Place the cursor on **Design** and select any option under **DHCPv6**. See the "Managing DHCPv6 addresses" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **Configure DNS**—Place the cursor on **Design** menu and select the options under **Cache DNS** and **Auth DNS**. Place the cursor on **Deploy** menu and select the options under **DNS** and **DNS Updates**. See the "Managing Zones" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.
- **Manage hosts in zones**—From the **Design** menu, choose **Hosts** under the **Auth DNS** submenu. See the "Managing Hosts" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.
- **Manage IPv4 address space**—Place the cursor on **Design** and select any option under **DHCPv4**. See the "Managing Address Space" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **Configure IPv6 address space**—Place the cursor on **Design** and select any option under **DHCPv6**. See the "Managing DHCPv6 Addresses" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **Go to Basic mode**—Click the drop-down arrow of the mode icon () at the top right corner of the page and choose **Basic**. See [Local Basic Main Menu Page](#), on page 18.

The Advanced user mode page provides additional functions:

- **View the user role and group data for the logged-in user**—See [Role and Attribute Visibility Settings](#), on page 15.
- **Set your preferred session settings**—See [Role and Attribute Visibility Settings](#), on page 15.

- **Set server debugging**—You can set debug flags for the protocol servers. Set these values only under diagnostic conditions when communicating with the Cisco Technical Assistance Center (TAC).
- **Change your login administrator password**—See [Managing Passwords, on page 49](#).

Setting Local User Preferences

You can maintain a short list of web UI settings through subsequent user sessions. The only difference between the Basic and Advanced or Expert mode user preference pages is that Advanced and Expert modes have additional columns listing the data types and defaults

You can edit the user preferences by going to **User Preferences** under the **admin** menu(at the top of the main page). The user preference attributes to set are:

- **Username**—Username string, with a preset value of admin. You cannot modify this field.
- **Web UI list page size**—Adjust the page size by the number of displayed lines in a list; the preset value is 10 lines.
- **Web UI mode**—User mode at startup: Basic, Advanced, or Expert (see [Role and Attribute Visibility Settings, on page 15](#)). If unset, the mode defaults to the one set in the CCM server configuration (see [Managing Servers, on page 129](#)).

You can unset the page size and web UI mode values by checking the check box in the *Unset?* column, next to the attribute. After making the user preference settings, click **Modify User Preferences**.

Configuring Clusters in the Local Web UI

You can define other local Cisco Prime IP Express clusters in the local web UI. The local cluster on the current machine is called the **localhost** cluster. To set up other clusters, choose **Manage Clusters** from **Operate** menu to open the List/Add Clusters page. Note that the **localhost** cluster has the IP address and SCP port of the local machine.

Click the **Add Cluster** icon in the left pane to open the Add Cluster page. At a minimum, you must enter the name and ipaddr of the remote local cluster. You should also enter the admin name and password, along with possibly the SCP port (if not 1234), of the remote cluster. Click **Add Cluster**. To edit a cluster, click the cluster name in the Clusters pane on the left to open the Edit Cluster page. If you want to use secure access mode, select use-ssl as disabled, optional, or required (optional is the preset value; you need the security library installed if you choose required). Make the changes, then click **Save**.



Note

If you change the IP address of your local cluster machine, you must modify the **localhost** cluster to change the address in the ipaddr field. Avoid setting the value to the loopback address (127.0.0.1); if you do, you must also set the actual IP addresses of main and backup servers for DHCP failover and High-Availability (HA) DNS configurations.

Regional Cluster Web UI

The regional cluster web UI provides concurrent access to regional and central administration tasks. It provides granular administration across servers with permissions you can set on a per element or feature basis. After

you log into the application, the Home page appears. Regional cluster administration is described in [Managing the Central Configuration](#), on page 69.

Related Topics

[Introduction to the Web-Based User Interfaces](#), on page 12

[Local Cluster Web UI](#), on page 17

Command Line Interface

Using the Cisco Prime IP Express CLI (the **nrcmd** program), you can control your local cluster server operations. You can set all configurable options, as well as start and stop the servers.



Note

The CLI provides concurrent access, by at most 14 simultaneous users and processes per cluster.



Tip

See the **CLIContents.html** file in the **/docs** subdirectory of your installation directory for details.

The **nrcmd** program for the CLI is located on:

- **Windows**—In the *install-path* \bin directory.
- **Linux**—In the *install-path* /usrbin directory.

On a local cluster, once you are in the appropriate directory, use the following command at the prompt:

```
nrcmd [-C cluster[:port]] [-N user] [-P password] [-h] [-r] [-v] [-b < script | command]
```

- **-C**—Cluster name, preset value **localhost**. Specify the port number with the cluster name while invoking **nrcmd** to connect to another cluster. See the preceding example.
The port number is optional if the cluster uses the default SCP port—1234 for local and 1244 for regional. Ensure that you include the port number if the port used is not the default one.
- **-N**—Username. You have to enter the username that you created when first logged into the Web UI.
- **-P**—User password. You have to enter the password that you created for the username.
- The local cluster (**-L**) is implied; use **-R** to open the regional cluster CLI.
- **-b < script** Process script file of **nrcmd** commands.
- **-h** Print this help text.
- **-r** Login as a read-only user.
- **-R** Connect to regional.
- **-v** Report the program version and exit.



Note

Cluster defaults to localhost if not specified.

**Tip**

For additional command options, see the **CLIGuide.html** file in /docs.

**Note**

If you change the IP address of your local cluster machine, you must modify the **localhost** cluster to change the address in the *ipaddress* attribute. Do not set the value to 127.0.0.1.

You can also send the output to a file using:

```
nrcmd> session log filename
```

For example:

To send the leases on the DHCP server to a file (leases.txt), use the following commands:

```
nrcmd> session log leases.txt
nrcmd> lease list
```

**Note**

To close a previously opened file, use session log (no filename). This stops writing the output to any file.

To disconnect from the cluster, use **exit**:

```
nrcmd> exit
```

**Tip**

The CLI operates on a coordinated basis with multiple user logins. If you receive a cluster lock message, determine who has the lock and discuss the issue with that person. (See [Multiple Users](#), on page 14.)

Global Search in PrimeIP Express

The Local and Regional Web UI in PrimeIP Express also provides a global search functionality for the IP addresses or DNS names available in the local clusters. The search interface element is available at the top right corner of the main page.

**Note**

To view the search interface element and run the search for IP addresses and DNS names, Cisco PrimeIP Express must be licensed with DHCP or DNS, and the DHCP or DNS services must be enabled for the local cluster (in the List/Add Remote Clusters page in Regional Web UI).

The following table shows the typical search results under different scenarios.

Table 2: Typical Search Results

You search for...	With active licenses and services for...	Search Results
An IPv4 address	Only DHCP	The closest matching scope, scope lease or scope reservation

You search for...	With active licenses and services for...	Search Results
An IPv4 address or a DNS FQDN	Only DNS	The related Zone or Resource Record
An IPv6 address	Only DHCP	The closest matching prefix, prefix lease or prefix reservation
An IPv6 address or a DNS FQDN	Only DNS	The related Zone or Resource Record
An IPv4 address, an IPv6 address or a DNS FQDN	Both DHCP and DNS	All of the above, based on the type of address



Server Status Dashboard

The Cisco Prime IP Express server status dashboard in the web user interface (web UI) presents a graphical view of the system status, using graphs, charts, and tables, to help in tracking and diagnosis. These dashboard elements are designed to convey system information in an organized and consolidated way, and include:

- Significant protocol server and other metrics
- Alarms and alerts
- Database inventories
- Server health trends

The dashboard is best used in a troubleshooting desk context, where the system displaying the dashboard is dedicated for that purpose and might be distinct from the systems running the protocol servers. The dashboard system should point its browser to the system running the protocol servers.

You should interpret dashboard indicators in terms of deviations from your expected normal usage pattern. If you notice unusual spikes or drops in activity, there could be communication failures or power outages on the network that you need to investigate.

- [Opening the Dashboard, page 25](#)
- [Display Types, page 25](#)
- [Customizing the Display, page 31](#)
- [Selecting Dashboard Elements to Include, page 33](#)
- [Host Metrics, page 35](#)

Opening the Dashboard

To open the dashboard in local web UI, from the **Operate** menu, choose **Dashboard**.

Display Types

Provided you have DHCP and DNS privileges through administrator roles assigned to you, the preset display of the dashboard consists of the following tables (See the table below for an example):

- **System Metrics**—See [System Metrics](#), on page 35.
- **DHCP General Indicators**—See the "DHCP General Indicators" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.
- **DNS General Indicators**—See the "DNS General Indicators" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.

**Tip**

These are just the preset selections. See [Selecting Dashboard Elements to Include](#), on page 33 for other dashboard elements you can select. The dashboard retains your selections from session to session.

Figure 4: Preset Dashboard Elements



Each dashboard element initially appears as a table or a specific chart type, depending on the element:

- **Table**—See [Tables](#), on page 27.
- **Line chart**—See [Line Charts](#), on page 27.
- **Stacked area chart**—See [Stacked Area Charts](#), on page 29.

General Status Indicators

Note the green box next to each dashboard element name in the above image. This box indicates that the server sourcing the information is functioning normally. A yellow box indicates that server operation is less than optimum. A red box indicates that the server is down. These indicators are the same as for the server health on the Manage Servers page in the regular web UI.

Graphic Indicators for Levels of Alert

Graphed lines and stacked areas in the charts follow a standard color and visual coding so that you can immediately determine key diagnostic indicators at a glance. The charts use the following color and textural indicators:

- **High alerts or warnings**—Lines or areas in red, with a hatched texture.

- **All other indicators**—Lines or areas in various other colors distinguish the data elements. The charts do not use green or yellow.

Magnifying and Converting Charts

If Magnified Chart is the selected Chart Link (see [Figure 8: Specifying Chart Conversion to Table Format, on page 32](#)), you can magnify a chart in a separate window by clicking the chart. In magnified chart view, you can choose an alternative chart type from the one that comes up initially (see [Other Chart Types, on page 30](#)).



Note

Automatic refresh is turned off for magnified charts (see [Setting the Polling Interval, on page 32](#)). To get the most recent data, click the **Refresh** icon next to the word Dashboard at the top left of the page.

To convert a chart to a table, see [Displaying Charts as Tables, on page 32](#). You cannot convert tables to a graphic chart format.

Legends

Each chart initially includes a color-coded legend. To turn off the legend display on the main dashboard page, see [Displaying or Hiding Chart Legends, on page 33](#). Removing the legend renders the graphic chart size relatively larger, which can be helpful if you have many charts displayed. You cannot remove legends in magnified views.

Tables

Dashboard elements rendered as tables have data displayed in rows and columns. The following dashboard elements are preset to consist of (or include) tables:

- System Metrics
- DHCP DNS Updates
- DHCP Address Current Utilization
- DHCP General Indicators
- DNS General Indicators
- Caching DNS General Indicators



Note

If you view a table in Expert mode, additional data might appear.

Line Charts

Dashboard elements rendered as line charts can include one or more lines plotted against the x and y axes. The three types of line charts are described in the following table.


Table 3: Line Chart Types

Type of Line Chart	Description	Dashboard Elements Rendered
Raw data line chart	Lines plotted against raw data.	<ul style="list-style-type: none"> • Java Virtual Machine (JVM) Memory Utilization (Expert mode only) • DHCP Buffer Capacity • DHCP Failover Status (two charts) • DNS Network Errors • DNS Related Servers Errors
Delta line chart	Lines plotted against the difference between two sequential raw data.	<ul style="list-style-type: none"> • DNS Inbound Zone Transfers • DNS Outbound Zone Transfers
Rate line chart	Lines plotted against the difference between two sequential raw data divided by the sample time between them.	<ul style="list-style-type: none"> • DHCP Server Request Activity (see the image below) • DHCP Server Response Activity • DHCP Response Latency • DNS Query Responses • DNS Forwarding Errors

**Tip**

To get the raw data for a chart that shows delta or rate data, enter Expert mode, set the Chart Link to Data Table (see [Displaying Charts as Tables](#), on page 32), then click the chart. The Raw Data table is below the Chart Data table.

Figure 5: Line Chart Example




Stacked Area Charts

Dashboard elements rendered as stacked area charts have multiple related metrics plotted as trend charts, but stacked one on top of the other, so that the highest point represents a cumulative value. The values are

independently shaded in contrasting colors. (See the image below for an example of the DHCP Server Request Activity chart shown in [Figure 5: Line Chart Example](#), on page 29 rendered as a stacked area chart.)

Figure 6: Stacked Area Chart Example



They are stacked in the order listed in the legend, the left-most legend item at the bottom of the stack and the right-most legend item at the top of the stack. The dashboard elements that are pre-set to stacked area charts are:

- DHCP Server Request Activity
- DHCP Server Response Activity
- DHCP Response Latency
- DNS Outbound Zone Transfers
- DNS Inbound Zone Transfers

Other Chart Types

The other chart types available for you to choose are:

- **Line**—One of the line charts described in [Table 3: Line Chart Types](#), on page 28.
- **Stacked Area**—Charts described in the [Stacked Area Charts](#), on page 29.
- **Pie**—Shows a single percentage pie chart of the data averaged over the time sampled.
- **Bar**—Multiple related current value metrics plotted side by side as groups of bars that show the actual data sampled.
- **Stacked Bar**—Addition total of the actual samples. This chart shows more distinct data points than the stacked area chart.



Tip

Each chart type shows the data in distinct ways and in different interpretations. You can decide which type best suits your needs.

Getting Help for the Dashboard Elements

You can open a help window for each dashboard element by clicking the title of the element.

Customizing the Display

To customize the dashboard display, you can:

- Refresh the data and set an automatic refresh interval.
- Expand a chart and render it in a different format.
- Convert a graphic chart to a table.
- Download data to comma-separated value (CSV) output.
- Display or hide chart legends.
- Configure server chart types.
- Reset to default display

Each chart supports:

- Resizing
- Drag and drop to new cell position
- Minimizing
- Closing

Each chart has a help icon with a description of the chart and a detailed help if you click the chart title.

**Note**

The changes made to the dashboard/chart will persist only if you click **Save** in the Dashboard window.

Refreshing Displays

Refresh each display so that it picks up the most recent polling by clicking the **Refresh** icon.

Setting the Polling Interval

You can set how often to poll for data. Click the **Dashboard Settings** icon in the upper-right corner of the dashboard display. There are four options to set the polling interval of the cached data, which polls the protocol servers for updates. (See the image below)

Figure 7: Setting the Chart Polling Interval




You can set the cached data polling (hence, automatic refresh) interval to:

- **Disabled**— Does not poll, therefore does not automatically refresh the data.
- **Slow**— Refreshes the data every 30 seconds.
- **Medium**— Refreshes the data every 20 seconds.
- **Fast** (the preset value)— Refreshes the data every 10 seconds.

Displaying Charts as Tables

You can choose to display a graphic chart as a table when you magnify the chart by clicking it. At the middle of the top of the dashboard display are the controls for the chart links (see the image below)

Figure 8: Specifying Chart Conversion to Table Format



Click the **Data Table** radio button. When you click the chart itself, it opens as a table. The preset display format is Magnified Chart.

Exporting to CSV Format

You can dump the chart data to a comma-separated value (CSV) file (such as a spreadsheet) when you magnify the chart by clicking it. In the Chart Link controls at the top of the page (see [Figure 8: Specifying Chart Conversion to Table Format, on page 32](#)), click the **CSV Export** radio button, then click the chart. A Save As window appears, where you can specify the name and location of the CSV file.

Displaying or Hiding Chart Legends

You can include or exclude the color-coded legends for charts on the main dashboard page. You might want to remove the legends as you become more familiar with the data and track it on a slightly larger chart display. In the upper-right of the dashboard display are the controls for the legend display (see the image below). The preset value is Visible.

Figure 9: Displaying or Hiding Chart Legends and Selecting Chart



Selecting Dashboard Elements to Include

You can decide how many dashboard elements you want to display on the page. At times, you might want to focus on one server activity only, such as for the DHCP server, and exclude all other metrics for the other servers. In this way, the dashboard becomes less crowded, the elements are larger and more readable. At other times, you might want an overview of all server activities, with a resulting smaller element display.

You can select the dashboard elements to display from the main Dashboard page by clicking **Chart Selections** in the Dashboard Settings dialog (see [Figure 9: Displaying or Hiding Chart Legends and Selecting Chart, on page 33](#)). Clicking the link opens the Chart Selection page (see [Figure 10: Selecting Dashboard Elements, on page 34](#)).

Configuring Server Chart Types

You can set the default chart types on the main dashboard view. You can customize the server charts in the dashboard to display only the specific chart types as default.

To set up default chart type, check the check box corresponding to the Metrics chart that you want to display and choose a chart type from the **Type** drop-down list. The default chart types are consistent and shared across different user sessions (see the image below).



Note

You can see either the CDNS or DNS Metrics in the **Dashboard Settings > Chart Selection** page based on the service configured on the server.

**Tip**

The order in which the dashboard elements appear in the Chart Selection list does not necessarily determine the order in which the elements will appear on the page. An algorithm that considers the available space determines the order and size in a grid layout. The layout might be different each time you submit the dashboard element selections. To change selections, check the check box next to the dashboard element that you want to display.

Figure 10: Selecting Dashboard Elements

Name	Type	Width	Height	Minimize
System Metrics	Table	500	300	<input type="checkbox"/>
DHCP Metrics				
<input type="checkbox"/> DHCP Server Request Activity	Stacked Area Chart	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Server Response Activity	Stacked Area Chart	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Buffer Capacity	Line Chart	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Response Latency	Stacked Area Chart	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP DNS Updates	Table	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Address Current Utilization	Table	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Failover Status	Line Chart	500	300	<input type="checkbox"/>
<input checked="" type="checkbox"/> DHCP General Indicators	Table	500	300	<input type="checkbox"/>
<input type="checkbox"/> DHCP Server Lease Data	Line Chart	500	300	<input type="checkbox"/>
DNS Metrics				
<input type="checkbox"/> DNS Outbound Zone Transfers	Stacked Area Chart	500	300	<input type="checkbox"/>
<input type="checkbox"/> DNS Inbound Zone Transfers	Stacked Area Chart	500	300	<input type="checkbox"/>

To change selections, check the check box next to the dashboard element that you want to display.

Specific group controls are available in the drop-down list, **Chart Selection**, at the top of the page. To:

- Uncheck all check boxes, choose **None**.
- Revert to the preset selections, choose **Default**. The preset dashboard elements for administrator roles supporting DHCP and DNS are:
 - Host Metrics: System Metrics
 - DHCP Metrics: General Indicators
 - DNS Metrics: General Indicators
- Select the DHCP metrics only, choose **DHCP** (see the "DHCP Metrics" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*).
- Select the DNS metrics only, choose **DNS** (see the "Dashboard and Authoritative DNS Metrics" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*).
- Select the DNS metrics only, choose **CDNS** (see the "Caching DNS Metrics" section in *Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*).

- Select all the dashboard elements, choose **All**.

Click **Save** at the bottom of the page to save your choices, or **Cancel** to cancel the changes.

Host Metrics

Host metrics comprise two charts:

- **System Metrics**—See the [System Metrics](#), on page 35.
- **JVM Memory Utilization** (available in Expert mode only).

System Metrics

The System Metrics dashboard element shows the free space on the disk volumes where the Cisco Prime IP Express logs and database directories are located, the date and time of the last server backup, and CPU and memory usage for the various servers. System metrics are available if you choose **Host Metrics: System Metrics** in the Chart Selection list.

The resulting table shows:

- **Logs Volume**—Current free space out of the total space on the disk drive where the logs directory is located, with the equivalent percentage of free space.
- **Database Volume**—Current free space out of the total space on the disk drive where the data directory is located, with the equivalent percentage of free space.
- **Last Good Backup**—Date and time when the last successful shadow database backup occurred (or Not Done if it did not yet occur) since the server agent was last started.
- **CPU Utilization** (in seconds), **Memory Utilization** (in kilobytes), and (in Expert mode only) the **VM Utilization** (in kilobytes) and Process ID (**PID**) for the:
 - Cisco Prime IP Express server agent
 - CCM server
 - DNS server
 - DHCP server
 - Web server
 - SNMP server
 - DNS caching server

How to Interpret the Data

The System Metrics data shows how full your disk volumes are getting based on the available free space for the Cisco Prime IP Express logs and data volumes. It also shows if you had a last successful backup of the data files and when that occurred. Finally, it shows how much of the available CPU and memory the Cisco Prime IP Express servers are using. The difference in the memory and VM utilization values is:

- **Memory Utilization**—Physical memory that a process uses, or roughly equivalent to the Resident Set Size (RSS) value in UNIX **ps** command output, or to the Task Manager Mem Usage value in Windows: the number of pages the process has in real memory minus administrative usage. This value includes only the pages that count toward text, data, or stack space, but not those demand-loaded in or swapped out.
- **VM Utilization**—Virtual memory that a process uses, or roughly equivalent to the SZ value in UNIX **ps** command output, or to the Task Manager VM Size value in Windows: the in-memory pages plus the page files and demand-zero pages, but not usually the memory-mapped files. This value is useful in diagnosing how large a process is and if it continues to grow.

Troubleshooting Based on the Results

If you notice the free disk space decreasing for the logs or data directory, you might want to consider increasing the disk capacity or look at the programs you are running concurrently with Cisco Prime IP Express.



PART II

Local and Regional Administrator

- [Managing Administrators, page 39](#)
- [Managing Owners and Regions, page 65](#)
- [Managing the Central Configuration, page 69](#)
- [Maintaining Servers and Databases, page 129](#)
- [Backup and Recovery, page 161](#)
- [Managing Reports, page 177](#)



Managing Administrators

This chapter explains how to set up network administrators at the local and regional clusters. The chapter also includes local and regional cluster tutorials for many of the administration features.

- [Administrators, Groups and Roles, page 39](#)
- [External Authentication Servers, page 45](#)
- [Managing Administrators, page 48](#)
- [Managing Passwords, page 49](#)
- [Managing Groups, page 50](#)
- [Managing Roles, page 51](#)
- [Granular Administration, page 52](#)
- [Centrally Managing Administrators, page 56](#)

Administrators, Groups and Roles

The types of functions that network administrators can perform in Cisco Prime IP Express are based on the roles assigned to them. Local and regional administrators can define these roles to provide granularity for the network administration functions. Cisco Prime IP Express predefines a set of base roles that segment the administrative functions. From these base roles you can define further constrained roles that are limited to administering particular addresses, zones, and other network objects.

The mechanism to associate administrators with their roles is to place the administrators in groups that include these roles.

Related Topics

[How Administrators Relate to Groups and Roles, on page 40](#)

[Administrator Types, on page 40](#)

[Roles, Subroles, and Constraints, on page 41](#)

[Groups, on page 44](#)

[Managing Administrators, on page 48](#)

[Managing Passwords, on page 49](#)

[Managing Groups, on page 50](#)

[Managing Roles, on page 51](#)

How Administrators Relate to Groups and Roles

There are three administrator objects in Cisco Prime IP Express—administrator, group, and role:

- **Administrator**—An account that logs in and that, through its association with one or more administrator groups, can perform certain functions based on its assigned role or roles. At the local cluster, these functions are administering the local Central Configuration Management (CCM) server and databases, hosts, zones, address space, and DHCP. At the regional cluster, these functions administer the regional CCM server and databases, central configuration, and regional address space. An administrator must be assigned to at least one group to be effective.
Adding administrators is described in [Managing Administrators, on page 48](#).
- **Group**—A grouping of roles. You must associate one or more groups with an administrator, and a group must be assigned at least one role to be usable. The predefined groups that Cisco Prime IP Express provides map each role to a unique group.
Adding groups is described in [Managing Groups, on page 50](#).
- **Role**—Defines the network objects that an administrator can manage and the functions that an administrator can perform. A set of predefined roles are created at installation, and you can define additional constrained roles. Some of the roles include subroles that provide further functional constraints. Adding roles is described in [Managing Roles, on page 51](#).

Administrator Types

There are two basic types of administrators: superusers and specialized administrators:

- **Superuser**—Administrator with unrestricted access to the web UI, CLI, and all features. This administrator type should be restricted to a few individuals. The superuser privileges of an administrator override all its other roles.



Tip

You have to create the superuser and password at installation, or when you first log into the web UI.

- **Specialized**—Administrator created by name to fulfill specialized functions, for example, to administer a specific DNS forward or reverse zone, based on the administrator assigned role (and subrole, if applicable). Specialized administrators, like the superuser, require a password, but must also be assigned at least one administrator group that defines the relevant roles. The CLI provides the **admin** command. For an example of creating a local zone or host administrator, see [Create the Administrators, on page 113](#).

Roles, Subroles, and Constraints

A license type is associated with each role-subrole combination. A role-subrole is enabled only if that license is available in that cluster.

You can limit an administrator role by applying constraints. For example, you can use the host-admin base role to create a host administrator, named 192.168.50-host-admin, who is constrained to the 192.168.50.0 subnet. The administrator assigned a group that includes this role then logs in with this constraint in effect. Adding roles and subroles is described in [Managing Roles](#), on page 51.

You can further limit the constraints on roles to read-only access. An administrator can be allowed to read any of the data for that role, but not modify it. However, if the constrained data is also associated with a read-write role, the read-write privilege supersedes the read-only constraints.



Tip

An example of adding role constraints is in [Create a Host Administrator Role with Constraints](#), on page 116.

The interplay between DNS and host administrator role assignments is such that you can combine an unconstrained dns-admin role with any host-admin role in a group. For example, combining the dns-admin-readonly role and a host-admin role in a group (and naming the group host-rw-dns-ro) provides full host access and read-only access to zones and RRs. However, if you assign a constrained dns-admin role along with a host-admin role to a group and then to an administrator, the constrained dns-admin role takes precedence, and the administrator privileges at login will preclude any host administration.

Certain roles provide subroles with which you can further limit the role functionality. For example, the local ccm-admin or regional-admin, with just the owner-region subrole applied, can manage only owners and regions. By default, all the possible subroles apply when you create a constrained role.

The predefined roles are described in [Table 4: Local Cluster Administrator Predefined and Base Roles](#), on page 41 (local), and [Table 5: Regional Cluster Administrator Predefined and Base Roles](#), on page 43 (regional).

Table 4: Local Cluster Administrator Predefined and Base Roles

Local Role	Subroles and Active Functionality
addrblock-admin	<p>Core functionality: Manage address block, subnets, and reverse DNS zones (also requires dns-admin); and notify of scope activity.</p> <ul style="list-style-type: none"> • <i>ipv6-management</i> : Manage IPv6 prefixes, links, options, leases, and reservations.
ccm-admin	<p>Core functionality: Manage access control lists (ACLs), and encryption keys.</p> <ul style="list-style-type: none"> • <i>authentication</i> : Manage administrators. • <i>authorization</i> : Manage roles and groups. • <i>owner-region</i> : Manage owners and regions. • <i>database</i> : View database change entries and trim the CCM change sets.

Local Role	Subroles and Active Functionality
cdns-admin	<p>Core functionality: Manage in-memory cache (flush cache and flush cache name).</p> <ul style="list-style-type: none"> • <i>security-management</i> : Manage ACLs and DNSSEC configuration. • <i>server-management</i> : Manage DNSSEC configuration, as well as forwarders, exceptions, DNS64, and scheduled tasks, and stop, start, or reload the server.
cfg-admin	<p>Core functionality: Manage clusters.</p> <ul style="list-style-type: none"> • <i>ccm-management</i> : Manage the CCM server configuration. • <i>dhcp-management</i> : Manage the DHCP server configuration. • <i>dns-management</i> : Manage the DNS server configuration. • <i>cdns-management</i> : Manage Caching DNS server configuration. • <i>snmp-management</i> : Manage the SNMP server configuration.
dhcp-admin	<p>Core functionality: Manage DHCP scopes and templates, policies, clients, client-classes, options, leases, and reservations.</p> <ul style="list-style-type: none"> • <i>server-management</i> : Manage the DHCP server configuration, failover pairs, LDAP servers, extensions, and statistics. • <i>ipv6-management</i> : Manage IPv6 prefixes, links, options, leases, and reservations.
dns-admin	<p>Core functionality: Manage DNS zones and templates, resource records, secondary servers, and hosts.</p> <ul style="list-style-type: none"> • <i>security-management</i> : Manage DNS update policies, ACLs, and encryption keys. • <i>server-management</i> : Manage DNS server configurations and zone distributions, synchronize zones and HA server pairs, and push update maps. • <i>ipv6-management</i> : Manage IPv6 zones and hosts.

Local Role	Subroles and Active Functionality
host-admin	Core functionality: Manage DNS hosts. (Note that if an administrator is also assigned a constrained dns-admin role that overrides the host-admin definition, the administrator is not assigned the host-admin role.)

Table 5: Regional Cluster Administrator Predefined and Base Roles

Regional Role	Subroles and Active Functionality
central-cfg-admin	<p>Core functionality: Manage clusters and view replica data.</p> <ul style="list-style-type: none"> • <i>dhcp-management</i> : Manage DHCP scope templates, policies, client-classes, failover pairs, virtual private networks (VPNs), and options; modify subnets; and replicate data. • <i>ccm-management</i> : Manage CCM Server configuration. • <i>snmp-management</i> : Manage SNMP Server configuration. • <i>ipv6-management</i> : Manage IPv6 prefixes, links, options, leases and reservations. • <i>cdns-management</i> : Manage CDNS Server configuration. • <i>byod-management</i> : Manage BYOD Server configuration.
central-dns-admin	<p>Core functionality: Manage DNS zones and templates, hosts, resource records, and secondary servers; and create subzones and reverse zones.</p> <ul style="list-style-type: none"> • <i>security-management</i> : Manage DNS update policies, ACLs, and encryption keys. • <i>server-management</i> : Synchronize DNS zones and HA server pairs, manage zone distributions, pull replica zone data, and push update maps. • <i>ipv6-management</i> : Manage IPv6 prefixes, links, options, leases and reservations.

Regional Role	Subroles and Active Functionality
central-host-admin	Core functionality: Manage DNS hosts. (Note that if an administrator is also assigned a constrained central-dns-admin role that overrides the central-host-admin definition, the administrator is not assigned the central-host-admin role.)
regional-admin	Core functionality: Manage licenses and encryption keys. <ul style="list-style-type: none"> • <i>authentication</i> : Manage administrators. • <i>authorization</i> : Manage roles and groups. • <i>owner-region</i> : Manage owners and regions. • <i>database</i> : View database change entries and trim the CCM change sets. • <i>security-management</i> : Manage ACLs and DNSSEC configuration.
regional-addr-admin	Core functionality: Manage address blocks, subnets, and address ranges; generate allocation reports; and pull replica address space data. <ul style="list-style-type: none"> • <i>dhcp-management</i> : Push and reclaim subnets; and add subnets to, and remove subnets from, DHCP failover pairs. • <i>lease-history</i> : Query, poll, and trim lease history data. • <i>subnet-utilization</i> : Query, poll, trim, and compact subnet utilization data. • <i>ipv6-management</i> : Manage IPv6 prefixes, links, options, leases and reservations. • <i>byod-management</i> : Manage BYOD Server configuration.

Groups

Administrator groups are the mechanism used to assign roles to administrators. Hence, a group must consist of one or more administrator roles to be usable. When you first install Cisco Prime IP Express, a predefined group is created to correspond to each predefined role.

Roles with the same base role are combined. A group with an unconstrained dhcp-admin role and a constrained dns-admin role, does not change the privileges assigned to the dns-admin role. For example, if one of the roles is assigned unconstrained read-write privileges, the group is assigned unconstrained read-write privileges, even though other roles might be assigned read-only privileges. Therefore, to limit the read-write privileges

of a user while allowing read-only access to all data, create a group that includes the unconstrained read-only role along with a constrained read-write role. (See [Roles, Subroles, and Constraints](#), on page 41 for the implementation of host-admin and dns-admin roles combined in a group.)

External Authentication Servers

Cisco Prime IP Express includes a RADIUS client component and Active Directory (AD) client component, which are integrated with the authentication and authorization modules of the CCM server. To enable external authentication, you must configure a list of external RADIUS or an AD server at local and regional clusters, and ensure all authorized users are appropriately configured on the respective servers.

When external authentication is enabled, the CCM server handles attempts to log in via the web UI, SDK, or CLI, by issuing a RADIUS request to a RADIUS server or a LDAP request to a AD server that is selected from the configured list. If the corresponding server validates the login request, access is granted, and the CCM server creates an authorized session with the group assignments specified by the RADIUS or the AD server.



Note

Any administrators defined in the CCM server's database are ignored when external authentication is enabled. Attempting to log in with these usernames and passwords will fail. To disable external authentication, you must remove or disable all the configured external servers or change the auth-type attribute value to Local.



Tip

If all logins fail because the RADIUS servers are inaccessible or misconfigured, use the local.superusers file to create a temporary username and password. See [Managing Administrators](#), on page 48 for more details.

Configuring an RADIUS External Authentication Server

Cisco Prime IP Express administrators must be assigned to one or more administrator groups to perform management functions. When using a RADIUS server for external authentication, these are set as a vendor specific attribute for each user. Using the Cisco vendor id (9), create the Cisco Prime IP Express groups attribute for each administrator, using the format **cnr:groups=group1 ,group2 ,group3** .

For example, to assign an administrator to the built-in groups **dhcp-admin-group** and **dns-admin-group** , enter:

```
cnr:groups=dhcp-admin-group,dns-admin-group
```

To assign superuser access privileges, the reserved group name **superusers** is used. To provide superuser privileges to an administrator, enter:

```
cnr:groups=superusers
```

The superuser privileges override all other groups



Note

You cannot add, delete, or modify external user names and their passwords or groups using Cisco PrimeIP Express. You must use the RADIUS server to perform this configuration.

Adding an RADIUS External Configuration Server

To add an external configuration server, do the following:

Local Advanced and Regional Web UI

-
- | | |
|---------------|---|
| Step 1 | From the Administration menu, choose RADIUS under the External Authentication submenu. The List/Add RADIUS Server page is displayed. |
| Step 2 | Click the Add RADIUS icon in the RADIUS pane, enter the name, address of the server you want to configure as the external authentication server, and you can set the key attribute which will be used for communicating with this server in the External Authentication dialog box, and click Add External Authentication Server . The CCM server uses the key to set the key-secret attribute which is the secret key shared by client and the server. |
| Step 3 | To enable the external authentication server, check enabled check box of the ext-auth attribute in the Edit Authentication Server page, and then click Save. |
| Step 4 | Change the auth-type attribute to RADIUS in the Manage Server page, click Save and then restart Cisco Prime IP Express. |
-

CLI Commands

To create an external authentication server, use **auth-server name create address [attribute =value ...]** (see the **auth-server** command in the CLIGuide.html file in the /docs directory for syntax and attribute descriptions).

Deleting an RADIUS External Authentication Server

Local Advanced and Regional Web UI

To delete an RADIUS external authentication server, select the server in the RADIUS pane and click the Delete RADIUS icon, then confirm the deletion. You can also cancel the deletion by clicking the Close button.

Configuring an AD External Authentication Server

Cisco Prime IP Express administrators must be assigned to one or more administrator groups to perform management functions. When using an AD server for external authentication, these are set as a vendor specific attribute for each user. Using the Cisco vendor id (9), create the Cisco Prime IP Express groups attribute for each administrator, using the format **cnr:groups=group1 ,group2 ,group3**

For example, to assign an administrator to the built-in groups **dhcp-admin-group** and **dns-admin-group**, enter:

```
cnr:groups=dhcp-admin-group,dns-admin-group
```

To assign superuser access privileges, the reserved group name **superusers** is used. To provide superuser privileges to an administrator, enter:

```
cnr:groups=superusers
```

The superuser privileges override all other groups.

A group needs to be created to access CPIPE and add the users to that group. Select an user attribute and provide the group information in the format **cnr:group1,group2,..**

To configure an Active Directory (AD) external authentication server:

-
- Step 1** In AD server, create a new group, for example **CPIPE**, with the group scope *Domain Local*.
- Step 2** Select a user and click **Add** to a group.
- Step 3** In Enter the Object Names window, select **CPIPE** and click **OK**.
- Step 4** In AD Server Object windows, select **CPIPE** for the *ad-group-name* attribute and **info** for the *ad-user-attr-map* attribute.
- Note** You cannot add, delete, or modify external user names and their passwords or groups using Cisco Prime IP Express. You must use the AD server to perform this configuration.
-

Configuring Kerbero's Realm and KDC

For the Cisco PrimeIP Express to communicate with the AD server, the Kerbero's Realm and KDC servers are required. To configure the Kerbero's Realm and KDC servers in Windows and Linux platforms follow the below examples.

If the Cisco Prime IP Express is running on Windows platform (ksetup), define a KDC entry for a realm by running the following command:

```
ksetup /AddKdc <RealmName> [KdcName]
```

For example, Ksetup /AddKdc ECNR.COM tm-chn-ecnr-ad.ecnr.com

To verify, run the following command:

```
ksetup /dumpstate
```

The result should be similar to the message below:

```
default realm = partnet.cisco.com (NT Domain)
ECNR.COM:
  kdc = tm-chn-ecnr-ad.ecnr.com
  Realm Flags = 0x0No Realm Flags
No user mappings defined.
```

If the Prime IP Express is running on Linux platform, the changes need to be configured in **krb5.conf** (/etc/krb5.conf) file, as shown below:

```
default = FILE:/var/log/krb5libs.log
kdc = FILE:/var/log/krb5kdc.log
admin_server = FILE:/var/log/kadmind.log
[libdefaults]
  ticket_lifetime = 1d
  default_realm = ECNR.COM
  default_tkt_enctypes = rc4-hmac
  default_tgs_enctypes = rc4-hmac
  dns_lookup_realm = false
  dns_lookup_kdc = false
  forwardable = true
[realms]
  ECNR.COM = {
    kdc = <kdc server host name>
    admin_server = <kdc server host name>
  }
[domain_realm]
  .ecnr.com = ECNR.COM
  ecnr.com = ECNR.COM
```

Adding an AD External Configuration Server

To add an external configuration server, do the following:

Local Advanced and Regional Web UI

-
- Step 1** From the **Administration** menu, choose **Active Directory under the External Authentication submenu**. The List/Add Active Directory Server page is displayed.
- Step 2** Click the Add **Active Directory** icon in the Active Directory pane, enter the name, hostname of the server, domain you want to configure as the external authentication server, and you can set the base domain, LDAP user attribute map, AD group name which will be used for communicating with this server in the External Authentication dialog box, and click **Add External Authentication Server**.
- Step 3** Change the auth-type attribute to Active Directory in the Manage Server page, click Save and then restart Cisco Prime IP Express.
-

CLI Commands

To create an external authentication server, use **auth-server name create address [attribute =value]**.

Deleting an AD External Authentication Server

Local Advanced and Regional Web UI

To delete an AD external authentication server, select the server in the AD pane and click the Delete Active Directory icon, then confirm the deletion. You can also cancel the deletion by clicking the Close button.

Managing Administrators

When you first log in, Cisco Prime IP Express will have one administrator—the superuser account. This superuser can exercise all the functions of the web UI and usually adds the other key administrators. However, ccm-admin and regional-admin administrators can also add, edit, and delete administrators. Creating an administrator requires:

- Adding its name.
- Adding a password.
- Specifying if the administrator should have superuser privileges (usually assigned on an extremely limited basis).
- If not creating a superuser, specifying the group or groups to which the administrator should belong. These groups should have the appropriate role (and possibly subrole) assignments, thereby setting the proper constraints.

**Tip**

If you accidentally delete all the roles by which you can log into Cisco Prime IP Express (those having superuser, ccm-admin, or regional-admin privileges), you can recover by creating a username/password pair in the *install-path /conf/priv/local.superusers* file. You must create this file, have write access to it, and include a line in it with the format *username password* . Use this username and password for the next login session. Note, however, that using the local.superusers file causes reduced security. Therefore, use this file only in emergencies such as when temporarily losing all login access. After you log in, create a superuser account in the usual way, then delete the local.superusers file or its contents. You must create a new administrator account for each individual, to track administrative changes.

Adding Administrators

To add a administrator, do the following:

Local and Regional Web UI

- Step 1** From the **Administration** menu, choose **Administrators** under the **User Access** submenu. This opens the List/Add Administrators page (see the [Create the Administrators, on page 113](#) for an example).
- Step 2** Click the **Add Administrator** icon in the **Administrators** pane, enter a name and password in the Add Admin dialog box, then click **Add Admin**.
- Step 3** Choose one or more existing groups from the Groups Available list (or whether the administrator should be a superuser), then click **Save**.

Editing Administrators

To edit an administrator, select the administrator in the Administrators pane, then modifying the name, password, superuser status, or group membership on the Edit Administrator page, then click **Save**. The active group or groups should be in the Selected list.

Deleting Administrators

To delete an administrator, select the administrator in the Administrators pane, click the **Delete** icon, and then confirm or cancel the deletion.

Managing Passwords

Passwords are key to administrator access to the web UI and CLI. In the web UI, you enter the password on the Login page. In the CLI, you enter the password when you first invoke the **nrcmd** program. The local or regional CCM administrator or superuser can change any administrator password.

You can prevent exposing a password on entry. In the web UI, logging in or adding a password never exposes it on the page, except as asterisks. In the CLI, you can prevent exposing the password by creating an administrator, omitting the password, then using **admin name enterPassword**, where the prompt displays

the password as asterisks. You can do this instead of the usual **admin name set password** command that exposes the password as plain text.

Administrators can change their own passwords on clusters. If you want the password change propagated from the regional server to all local clusters, log into the regional cluster. First ensure that your session `admin-edit-mode` is set to `synchronous`, and then update your password.

**Note**

The password should not be more than 255 characters long.

Managing Groups

A superuser, `ccm-admin`, or `regional-admin` can create, edit, and delete administrator groups. Creating an administrator group involves:

- Adding its name.
- Adding an optional description.
- Choosing associated roles.

Adding Groups

To add a group, do the following:

Local Advanced and Regional Web UI

- | | |
|---------------|---|
| Step 1 | From the Administration menu, choose Groups under the User Access submenu. This opens the List/Add Administrator Groups page (see the Create a Group to Assign to the Host Administrator, on page 118 for an example). |
| Step 2 | Click the Add Groups icon in the Groups pane, enter a name and an optional description in the Add Group dialog box, then click Add CCMAdminGroup . |
| Step 3 | Choose one or more existing roles from the Roles Available list and then click Save . |

Editing Groups

To edit a group, click the name of the group that you want to edit in the Groups pane to open the Edit Administrator Group page. You can modify the name, description, or role membership in this page. You can view the active roles in the Selected list.

Deleting Groups

To delete a group, select the group in the Groups pane, click the **Delete** icon, and then confirm the deletion. Click **Cancel** in the confirmation window to cancel the deletion.

Managing Roles

A superuser, ccm-admin, or regional-admin administrator can create, edit, and delete administrator roles. Creating an administrator role involves:

- Adding its name.
- Choosing a base role.
- Possibly specifying if the role should be unconstrained, or read-only.
- Possibly adding constraints.
- Possibly assigning groups.

Adding Roles

To add a role, do the following:

Local Advanced Web UI

-
- | | |
|---------------|--|
| Step 1 | From the Administration menu, choose Roles under the User Access submenu. This opens the List/Add Administrator Roles page. |
| Step 2 | Click the Add Role icon in the Roles pane, enter a name, in the Add Roles dialog box and click Add Role . |
| Step 3 | On the List/Add Administrator Roles page, specify any role constraints, subrole restrictions, or group selections, then click Save . |
-

Regional Advanced Web UI

-
- | | |
|---------------|--|
| Step 1 | From the Administration menu, choose Roles under the User Access submenu. This opens the List/Add Administrator Roles page. |
| Step 2 | Click the Add Role icon in the Roles pane, enter a name, and a base role in the Add Roles dialog box and click Add Role . |
| Step 3 | On the List/Add Administrator Roles page, specify any role constraints, subrole restrictions, or group selections, then click Save . |
-

Editing Roles

To edit a role, select the role in the Roles pane, then modify the name or any constraints, subrole restrictions, or group selections on the Edit Administrator Role page. The active subroles or groups should be in the Selected list. Click **Save**.

Deleting Roles

To delete a role, select the role in the Roles pane, click the **Delete** icon, and then confirm the deletion.



Note

You cannot delete the default roles.

CLI Commands

To add and edit administrator roles, use **role name create base-role** (see the **role** command in the CLIGuide.html file in the /docs directory for syntax and attribute descriptions). The base roles have default groups associated with them. To add other groups, set the *groups* attribute (a comma-separated string value).

Granular Administration

Granular administration prevents unauthorized users from accidentally making a change on zones, address blocks, subnets, and router interfaces. It also ensures that only authorized users view or modify specific scopes, prefixes, and links. Granular administration constraints administrators to specific set of scopes, prefixes, and links. A constrained administrator can view or make changes to authorized scope, prefix, and link objects only. The CCM server uses owner and region constraints to authorize and filter IPv4 address space objects, and DNS zone related objects (CCMZone, CCMReverseZone, CCMSecondaryZone, CCMRRSet, and CCMHost). The zones are constrained by owners and regions. Owner or region attributes on the CCMSubnet control access to scopes. Also, owner or region attributes on the Prefix and Link objects control access to prefixes and links.

Local Advanced and Regional Web UI

-
- Step 1** From the **Administration** menu, choose **Roles** to open the List/Add Administrator Roles page.
 - Step 2** Click the **Add Role** icon in the Roles pane, enter a name for the custom role, for example, my-dhcp, and choose **dhcp-admin** from the Role drop-down list and click **Add Role**.
 - Step 3** Click **True** or **False** radio button as necessary, on the Add DHCP Administrator Role page.
 - Step 4** Choose the required sub roles in the Available field and move them to the Selected field.
 - Step 5** Click **Add Constraint**.
 - a) On the Add Role Constraint page, modify the fields as necessary.
 - b) Click **Add Constraint**. The constraint must have an index number of 1.
 - Step 6** Click **Save**.
The name of the custom role appears on the list of roles in the List/Add Administrator Roles page.
-

Related Topics

[Scope-Level Constraints, on page 53](#)

[Prefix-Level Constraints, on page 54](#)

[Link-Level Constraints, on page 55](#)

Scope-Level Constraints

A dhcp admin user can view or modify a scope if any of the following conditions is met:

- Owner of the subnet for the scope matches the dhcp-admin owner.
- Region of the subnet for the scope matches the region role constraints.
- Owner or region of the parent address block matches the dhcp-admin owner or region role constraints. Note that the most immediate parent address block that has owner or region defined takes precedence.

The following conditions are also valid:

- If the matching owner or region constraint is marked as read-only, you can only view the scope.
- If a scope has a primary network defined, the primary subnet and its parent address block owner or region constraints override secondary subnets.
- If no parent subnet or address block defines owner or region constraints, then you can access the scope.
- If you are an unconstrained dhcp-admin user, you can have access to all scopes.



Note

These hierarchical authorization checks for dhcp-admin owner/region constraints are applicable to scopes, subnets, and parent address blocks. Identical hierarchical authorization checks for addrblock-admin owner/region constraints apply to address blocks and subnets. If you have dhcp-admin and the addrblock-admin privileges, you can access address blocks and subnets, if either of the roles allow access.

Examples of Scope-Level Constraints:

```
Parent CCMAAddrBlock 10.0.0.0/8 has owner 'blue' set.
  Scope 'A' has subnet 10.0.0.0/24 has parent CCMSubnet with owner 'red'.
  Scope 'B' has subnet 10.0.1.0/24 has parent CCMSubnet with no owner set.
  Scope 'C' has subnet 10.10.0.0/24 has parent CCMSubnet with owner 'green' and
primary-subnet 10.0.0.0/24.
  Scope 'D' has subnet 100.10.0.0/24 has parent CCMSubnet with owner unset, and no parent
block.

Scope 'A' owner is 'red'.
Scope 'B' owner is 'blue'.
Scope 'C' owner is 'red'.
Scope 'D' owner is unset. Only unconstrained users can access this scope.
```

Local Advanced Web UI

To add scopes, do the following:

-
- | | |
|---------------|--|
| Step 1 | From the Design menu, choose Scopes under the DHCPv4 submenu to open the List/Add DHCP Scopes. |
| Step 2 | Click the Add Scopes icon in the Scopes pane, enter a name, subnet, primary subnet, choose policy, and enter a selection-tag-list in the Add DHCP Scope dialog box. |
| Step 3 | Click Add DHCP Scope . The List/Add DHCP Scopes page appears. |
| Step 4 | Enter values for the fields or attributes as necessary. |
| Step 5 | To unset any attribute value, check the check box in the Unset? column, then click Unset Fields at the bottom of the page. |
| Step 6 | Click Save to add scope, or Revert to cancel the changes. |
- Tip** If you add new scope values or edit existing ones, click **Save** to save the scope object.
-

Prefix-Level Constraints

You can view or modify a prefix, if you have either of the following:

- The ipv6-management subrole of the dhcp-admin, or addrblock-admin role on the local cluster.
- The central-cfg-admin, or regional-addr-admin role on the regional cluster.

You can view or modify a prefix if any of the following conditions is true:

- The owner or region of the parent link matches the owner or region role constraints defined for you.
- The owner or region of this prefix matches the owner or region role constraints defined for you.
- The owner or region of the parent prefix matches the owner or region role constraints defined for you.

You can view or modify a prefix if any of the following conditions is true:

- If the matching owner or region constraint for you is marked as read-only, then you can only view the prefix.
- If the prefix references a parent link, the link owner or region constraints is applicable if the link owner or region constraints set.
- If no parent link or prefix defines any owner or region constraints, then you can access this prefix only if owner or region role constraints are not defined for you.
- If you are an unconstrained user, then you have access to all.

Examples of Prefix-Level constraints:

```
Link 'BLUE' has owner 'blue' set.
Parent Prefix 'GREEN' has owner 'green' set.
Prefix 'A' has owner 'red' set, no parent prefix, and no parent link.
Prefix 'B' has owner 'yellow' set, parent Prefix 'GREEN' and parent link 'BLUE'.
Prefix 'C' has no owner set, parent prefix 'GREEN', and no parent link.
```

```
Prefix 'C' has no owner set, no parent prefix, and no parent link.

Prefix 'A' owner is 'red'.
Prefix 'B' owner is 'blue'.
Prefix 'C' owner is 'green'.
Prefix 'D' owner is unset. Only unconstrained users can access this prefix.
```

Local Advanced and Regional Web UI

To view unified v6 address space, do the following:

-
- Step 1** From the **Design** menu, choose **Address Tree** under the **DHCPv6** submenu to open the DHCP v6 Address Tree page.
 - Step 2** View a prefix by adding its name, address, and range, then choosing a DHCP type and possible template (see the *"Viewing IPv6 Address Space" section in Cisco PrimeIP Express 8.3 DHCP User Guide*).
 - Step 3** Choose the owner from the owner drop-down list.
 - Step 4** Choose the region from the region drop-down list.
 - Step 5** Click **Add Prefix**. The newly added Prefix appears on the DHCP v6 Address Tree page.
-

Local Advanced and Regional Web UI

To list or add DHCP prefixes, do the following:

-
- Step 1** From the **Design** menu, choose **Prefixes** under the **DHCPv6** submenu to open the List/Add DHCP v6 Prefixes page.
 - Step 2** Click the **Add Prefixes** icon in the Prefixes pane, enter a name, address, and range for the prefix, then choose the DHCP type and possible template.
 - Step 3** Choose the owner from the owner drop-down list.
 - Step 4** Choose the region from the region drop-down list.
 - Step 5** Click **Add IPv6 Prefix**. The newly added Prefix appears on the List Prefixes page.
-

Link-Level Constraints

You can view or modify a link if:

- You are authorized for the ipv6-management subrole of the dhcp-admin or addrblock-admin role on the local cluster, or the central-cfg-admin or regional-addr-admin role on the regional cluster.
- The owner or region of the link matches the owner or region role constraints defined for you.
- No owner or region is defined for the link, and only if no owner or region role constraints are defined for you.

If you are an unconstrained user, then you have access to all links.

The following is an example of Link Level Constraints:

```
Link 'BLUE' has owner 'blue' set.
```

```
Link 'ORANGE' has owner unset.
```

```
Link 'BLUE' owner is 'blue'.
```

```
Link 'ORANGE' owner is unset. Only unconstrained users can access this link.
```

Local Advanced and Regional Web UI

To add links, do the following:

-
- Step 1** From the **Design** menu, choose **Links** under the **DHCPv6** submenu to open the List/Add DHCP v6 Links page.
- Step 2** Click the **Add Links** icon in the Links pane, enter a name, then choose the link type, and enter a group.
- Step 3** Click **Add Link**. The newly added DHCPv6 Link appears on the List/Add DHCP v6 Links page.
-

Centrally Managing Administrators

As a regional or local CCM administrator, you can:

- Create and modify local and regional cluster administrators, groups, and roles.
- Push administrators, groups, and roles to local clusters.
- Pull local cluster administrators, groups, and roles to the central cluster.

Each of these functions involves having at least one regional CCM administrator subrole defined. The following table describes the subroles required for these operations.

Table 6: Subroles Required for Central Administrator Management

Central Administrator Management Action	Required Regional Subroles
Create, modify, push, pull, or delete administrators	authentication
Create, modify, push, pull, or delete groups or roles	authorization
Create, modify, push, pull, or delete groups or roles with associated owners or regions	authorization owner-region
Create, modify, push, pull, or delete external authentication servers	authentication

Related Topics

[Pushing and Pulling Administrators, on page 57](#)

[Pushing and Pulling Groups, on page 61](#)

[Pushing and Pulling Roles, on page 62](#)

Pushing and Pulling Administrators

You can push administrators to, and pull administrators from local clusters on the List/Add Administrators page in the regional cluster web UI.

You can create administrators with both local and regional roles at the regional cluster. However, you can push or pull only associated local roles, because local clusters do not recognize regional roles.

Related Topics

[Pushing Administrators to Local Clusters, on page 57](#)

[Pushing Administrators Automatically to Local Clusters, on page 57](#)

[Pulling Administrators from the Replica Database, on page 58](#)

Pushing Administrators to Local Clusters

Pushing administrators to local clusters involves choosing one or more clusters and a push mode.

Regional Basic and Advanced Web UI

-
- | | |
|---------------|--|
| Step 1 | From the Administration menu, choose Administrators . |
| Step 2 | On the List/Add Administrators Page, click the Push All icon in the Administrators pane to push all the administrators listed on the page. This opens the Push Data to Local Clusters dialog box. |
| Step 3 | Choose a push mode by clicking one of the Data Synchronization Mode radio buttons. If you are pushing all the administrators, you can choose Ensure, Replace, or Exact. If you are pushing a single administrator, you can choose Ensure or Replace. In both cases, Ensure is the default mode. You would choose Replace only if you want to replace the existing administrator data at the local cluster. You would choose Exact only if you want to create an exact copy of the administrator database at the local cluster, thereby deleting all administrators that are not defined at the regional cluster. |
| Step 4 | Choose one or more local clusters in the Available field of the Destination Clusters and move it or them to the Selected field. |
| Step 5 | Click Push Data to Clusters . |
| Step 6 | On the View Push Data Report dialog box, view the push details, then click OK to return to the List/Add Administrators page. |
-

Pushing Administrators Automatically to Local Clusters

You can automatically push the new user name and password changes from the regional cluster to the local cluster. To do this, you must enable the synchronous edit mode in the regional cluster. The edit mode is set for the current Web UI session, or set as default for all users is set in the CCM Server configuration.

When synchronous mode is set, all the subsequent changes to user name and password are synchronized with local clusters. You can modify your password on the regional server, and this change is automatically propagated to local clusters.

If you are an admin user, you can make multiple changes to the user credentials on the regional cluster. All these changes are automatically pushed to local clusters.

Regional Basic and Advanced Web UI

-
- Step 1** From the **Operate** menu, choose **Manage Servers** under Servers submenu to open the Manage Servers page.
- Step 2** Click the **Local CCM Server** link on the Manage Servers pane to open the Edit CCM Server page.
- Step 3** Choose the synchronous radio buttons for the regional edit mode values for admin, dhcp, and dns.
- Step 4** Choose the webui mode value from the webui-mode drop-down list.
- Step 5** Enter the idle-timeout value.
- Step 6** To unset any attribute value, check the check box in the Unset? column, then click **Unset Fields** at the bottom of the page. To unset the attribute value or to change it, click **Save**, or **Cancel** to cancel the changes.
- Note** Enter values for the attributes marked with asterisks because they are required for CCM server operation. You can click the name of any attribute to open a description window for the attribute.
-

Connecting to CLI in Regional Mode

You must connect to the CLI in Regional Mode. The -R flag is required for regional mode. To set the synchronous edit mode:

```
nrcmd-R> session set admin-edit-mode=synchronous
```

Pulling Administrators from the Replica Database

Pulling administrators from the local clusters is mainly useful only in creating an initial list of administrators that can then be pushed to other local clusters. The local administrators are not effective at the regional cluster itself, because these administrators do not have regional roles assigned to them.

When you pull an administrator, you are actually pulling it from the regional cluster replica database. Creating the local cluster initially replicates the data, and periodic polling automatically updates the replication. However, to ensure that the replica data is absolutely current with the local cluster, you can force an update before pulling the data.

Regional Basic and Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Administrators** under the **User Access** submenu.
- Step 2** On the List/Add Administrators page, click **Pull Replica** on the **Administrators** pane. This opens the Select Replica Administrator Data to Pull dialog box.
- Step 3** Click the **Replicate** icon in the Update Replica Data column for the cluster. (For the automatic replication interval, see the [Replicating Local Cluster Data](#), on page 86.)
- Step 4** Choose a replication mode using one of the Mode radio buttons. In most cases, you would leave the default Replace mode enabled, unless you want to preserve any existing administrator properties already defined at the regional cluster by choosing Ensure, or create an exact copy of the administrator database at the local cluster by choosing Exact (not recommended).
- Step 5** Click **Pull Core Administrators** next to the cluster, or expand the cluster name and click **Pull Administrator** to pull an individual administrator in the cluster.
- Step 6** On the Select Replica Admin Data to Pull dialog box, view the change set data, then click **OK**. You return to the List/Add Administrators page with the pulled administrators added to the list.

Note If you do not have a regional cluster and would like to copy administrators, roles, or groups from one local cluster to another, you can export them and then reimport them at the target cluster by using the `cnr_exim` tool (see the [Using the cnr_exim Data Import and Export Tool](#), on page 169). However, the tool does not preserve the administrator passwords, and you must manually reset them at the target cluster. It is implemented this way to maintain password security. The export command is:

```
cnr_exim -c admin -x -e outputfile.txt
```

Pushing and Pulling External Authentication Servers

You can push all external authentication servers to local cluster or pull the external authentication server data from the local cluster on the List/Add RADIUS Server page or List/Add Active Directory Server page in the regional web UI.

Pushing RADIUS External Authentication Servers

To push external authentication servers to the local cluster, do the following:

Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **RADIUS** under the **External Authentication** submenu to view the List/Add RADIUS Server page in the regional web UI.
- Step 2** Click **Push All** icon in the RADIUS pane to push all the external authentication servers listed on the page, or **Push** to push an individual external authentication server. This opens the Push Data to Local Clusters dialog box.
- Step 3** Choose a push mode using one of the Data Synchronization Mode radio buttons.
- If you are pushing all the external authentication servers, you can choose Ensure, Replace, or Exact.
 - If you are pushing a single external authentication server, you can choose Ensure or Replace.
- In both the above cases, Ensure is the default mode.
- Choose Replace only if you want to replace the existing external authentication server data at the local cluster. Choose Exact only if you want to create an exact copy of the external authentication server data at the local cluster, thereby deleting all external authentication servers that are not defined at the regional cluster.
- Step 4** Click **Push Data to Clusters**.
-

Pulling RADIUS External Authentication Servers

To pull the external authentication server data from the local cluster, do the following:

Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **RADIUS** under the **External Authentication** submenu to view the List/Add RADIUS Server page in the regional web UI.
- Step 2** On the List/Add RADIUS Server page, click **Pull Data on the RADIUS** pane. This opens the Select Replica External Authentication Server Data to Pull dialog box.
- Step 3** Click the **Replica** icon in the Update Replica Data column for the cluster. (For the automatic replication interval, see the [Replicating Local Cluster Data](#), on page 86.)
- Step 4** Choose a replication mode using one of the Mode radio buttons.
Leave the default Replace mode enabled, unless you want to preserve any existing external authentication server properties at the local cluster by choosing Ensure.
- Note** We do not recommend that you create an exact copy of the external authentication server data at the local cluster by choosing Exact.
- Step 5** Click **Pull All External Authentication Servers** next to the cluster.
- Step 6** On the Report Pull Replica Authentication servers page, view the pull details, then click **Run**.
On the Run Pull Replica Authentication servers page, view the change set data, then click **OK**. You return to the List/Add Authentication Server page with the pulled external authentication servers added to the list.
-

Pushing AD External Authentication Servers

To push external authentication servers to the local cluster, do the following:

Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Active Directory** under the **External Authentication** submenu to view the List/Add Active Directory Server page in the regional web UI.
- Step 2** Click **Push** to push the external authentication server. This opens the Push Data to Local Clusters dialog box.
- Step 3** Choose a push mode using one of the Data Synchronization Mode radio buttons.
- If you are pushing all the external authentication servers, you can choose Ensure, Replace, or Exact.
 - If you are pushing a single external authentication server, you can choose Ensure or Replace.
- In both the above cases, Ensure is the default mode.
- Choose Replace only if you want to replace the existing external authentication server data at the local cluster. Choose Exact only if you want to create an exact copy of the external authentication server data at the local cluster, thereby deleting all external authentication servers that are not defined at the regional cluster.
- Step 4** Click **Push Data to Clusters**.
-

Pulling AD External Authentication Servers

To pull the AD external authentication server data from the local cluster, do the following:

Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Active Directory** under the **External Authentication** submenu to view the List/Add Active Directory Server page in the regional web UI.
- Step 2** On the List/Add Active Directory Server page, click **Pull Data** on the **Active Directory** pane. This opens the Select Replica External Authentication Server Data to Pull dialog box.
- Step 3** Click the **Replica** icon in the **Update Replica Data** column for the cluster (For the automatic replication interval, see the [Replicating Local Cluster Data](#), on page 86).
- Step 4** Choose a replication mode using one of the Mode radio buttons.
Leave the default Replace mode enabled, unless you want to preserve any existing external authentication server properties at the local cluster by choosing Ensure.
- Note** We do not recommend that you create an exact copy of the external authentication server data at the local cluster by choosing Exact.
- Step 5** Click **Pull All External Authentication Servers** next to the cluster.
- Step 6** On the Report Pull Replica Authentication servers page, view the pull details, then click **Run**.
On the Run Pull Replica Authentication servers page, view the change set data, then click **OK**. You return to the List/Add Authentication Server page with the pulled external authentication servers added to the list.
-

Pushing and Pulling Groups

Pushing and pulling groups is vital in associating administrators with a consistent set of roles at the local clusters. You can push groups to, and pull groups from, local clusters on the List/Add Administrator Groups page in the regional cluster web UI.

Related Topics

[Pushing Groups to Local Clusters](#), on page 61

[Pulling Groups from the Replica Database](#), on page 62

Pushing Groups to Local Clusters

Pushing groups to local clusters involves choosing one or more clusters and a push mode.

Regional Basic and Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Groups** under the **User Access** submenu.
- Step 2** On the List/Add Administrator Groups page, click the **Push All** icon on Groups pane to push all the groups listed on the page, or **Push** to push an individual group. This opens the Push Data to Local Clusters dialog box.
- Step 3** Choose a push mode using one of the Data Synchronization Mode radio buttons. If you are pushing all the groups, you can choose Ensure, Replace, or Exact. If you are pushing a single group, you can choose Ensure or Replace. In both cases, Ensure is the default mode. You would choose Replace only if you want to replace the existing group data at the

local cluster. You would choose Exact only if you want to create an exact copy of the group data at the local cluster, thereby deleting all groups that are not defined at the regional cluster.

- Step 4** By default, the associated roles and owners are pushed along with the group. Roles are pushed in Replace mode and owners in Ensure mode. To disable pushing the associated roles or owners, uncheck the respective check box.
 - Step 5** Choose one or more local clusters in the Available field of the Destination Clusters and move it or them to the Selected field.
 - Step 6** Click **Push Data to Clusters**.
 - Step 7** On the View Push Group Data Report page, view the push details, then click **OK** to return to the List/Add Administrator Groups page.
-

Pulling Groups from the Replica Database

Pulling administrator groups from the local clusters is mainly useful only in creating an initial list of groups that can then be pushed to other local clusters. The local groups are not useful at the regional cluster itself, because these groups do not have regional roles assigned to them.

When you pull a group, you are actually pulling it from the regional cluster replica database. Creating the local cluster initially replicates the data, and periodic polling automatically updates the replication. However, to ensure that the replica data is absolutely current with the local cluster, you can force an update before pulling the data.

Regional Basic and Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Groups** under the **User Access** submenu.
 - Step 2** On the List/Add Administrator Groups page, click the **Pull Replica icon** on **Groups** pane. This opens the Select Replica CCMAAdminGroup Data to Pull dialog box.
 - Step 3** Click the **Replica** icon in the Update Replica Data column for the cluster. (For the automatic replication interval, see the [Replicating Local Cluster Data](#), on page 86.)
 - Step 4** Choose a replication mode using one of the Mode radio buttons. In most cases, you would leave the default Replace mode enabled, unless you want to preserve any existing group properties at the local cluster by choosing Ensure, or create an exact copy of the group data at the local cluster by choosing Exact (not recommended).
 - Step 5** Click **Pull Core Groups** next to the cluster, or expand the cluster name and click **Pull Group** to pull an individual group in the cluster.
 - Step 6** On the Report Pull Replica Groups page, view the pull details, then click **Run**.
 - Step 7** On the Run Pull Replica Groups page, view the change set data, then click **OK**. You return to the List/Add Administrator Groups page with the pulled groups added to the list.
-

Pushing and Pulling Roles

You can push roles to, and pull roles from, local clusters on the List/Add Administrator Roles page in the regional cluster web UI. You can also push associated groups and owners, and pull associated owners, depending on your subrole permissions (see [Table 6: Subroles Required for Central Administrator Management](#), on page 56).

Related Topics

[Pushing Roles to Local Clusters, on page 63](#)

[Pulling Roles from the Replica Database, on page 63](#)

Pushing Roles to Local Clusters

Pushing administrator roles to local clusters involves choosing one or more clusters and a push mode.

Regional Advanced Web UI

-
- | | |
|---------------|--|
| Step 1 | From the Administration menu, choose Roles under the User Access submenu. |
| Step 2 | On the List/Add Administrator Roles page, click the Push All icon in the Roles pane to push all the roles listed on the page, or Push to push an individual role. This opens the Push Data to Local Clusters dialog box. |
| Step 3 | Choose a push mode using one of the Data Synchronization Mode radio buttons. If you are pushing all the roles, you can choose Ensure, Replace, or Exact. If you are pushing a single role, you can choose Ensure or Replace. In both cases, Ensure is the default mode. You would choose Replace only if you want to replace the existing role data at the local cluster. You would choose Exact only if you want to create an exact copy of the role data at the local cluster, thereby deleting all roles that are not defined at the regional cluster. |
| Step 4 | By default, the associated groups and owners are pushed along with the role. Groups are pushed in Replace mode and owners in Ensure mode. To disable pushing the associated roles or owners, uncheck the respective check box: <ul style="list-style-type: none"> • If you disable pushing associated groups and the group does not exist at the local cluster, a group based on the name of the role is created at the local cluster. • If you disable pushing associated owners and the owner does not exist at the local cluster, the role will not be configured with its intended constraints. You must separately push the group to the local cluster, or ensure that the regional administrator assigned the owner-region subrole has pushed the group before pushing the role. |
| Step 5 | Choose one or more local clusters in the Available field of the Destination Clusters and move it or them to the Selected field. |
| Step 6 | Click Push Data to Clusters . |
| Step 7 | On the View Push Role Data Report page, view the push details, then click OK to return to the List/Add Administrator Roles page. |
-

Pulling Roles from the Replica Database

Pulling administrator roles from the local clusters is mainly useful only in creating an initial list of roles that can then be pushed to other local clusters. The local roles are not useful at the regional cluster itself.

When you pull a role, you are actually pulling it from the regional cluster replica database. Creating the local cluster initially replicates the data, and periodic polling automatically updates the replication. However, to ensure that the replica data is absolutely current with the local cluster, you can force an update before pulling the data.

Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Roles** under the **User Access** submenu.
- Step 2** On the List/Add Administrator Roles page, click the **Pull Replica** icon in the **Roles** pane. This opens the Select Replica Administrator Role Data to Pull dialog box.
- Step 3** Click the **Replicate** icon in the **Update Replica Data** column for the cluster. (For the automatic replication interval, see the [Replicating Local Cluster Data](#), on page 86.)
- Step 4** Choose a replication mode using one of the Mode radio buttons. In most cases, you would leave the default Replace mode enabled, unless you want to preserve any existing role properties at the local cluster by choosing Ensure, or create an exact copy of the role data at the local cluster by choosing Exact (not recommended).
- Step 5** If you have the owner-region subrole permission, you can decide if you want to pull all the associated owners with the role, which is always in Ensure mode. This choice is enabled by default.
- Step 6** Click **Pull Core Roles** next to the cluster, or expand the cluster name and click **Pull Role** to pull an individual role in the cluster.
- Step 7** On the Report Pull Replica Roles page, view the pull details, then click **Run**.
- Step 8** On the Run Pull Replica Roles page, view the change set data, then click **OK**. You return to the List/Add Administrator Roles page with the pulled roles added to the list.
-



Managing Owners and Regions

This chapter explains how to configure owners and regions that can be applied to DHCP address blocks, subnets, prefixes, links, and zones.

- [Managing Owners, page 65](#)
- [Managing Regions, page 66](#)
- [Centrally Managing Owners and Regions, page 66](#)

Managing Owners

You can create owners to associate with address blocks, subnets, prefixes, links, and zones. You can list and add owners on a single page. Creating an owner involves creating a tag name, full name, and contact name.

Local Advanced and Regional Advanced Web UI

-
- | | |
|---------------|---|
| Step 1 | From the Administration menu, choose Owners under the Settings submenu to open the List/Add Owners page. The regional cluster also includes pull and push functions. |
| Step 2 | Click the Add Owner icon in the Owners pane on the left. This opens the Add Owner page. |
| Step 3 | Enter a unique owner tag. |
| Step 4 | Enter an owner name. |
| Step 5 | Enter an optional contact name. |
| Step 6 | Click Add Owner . |
| Step 7 | To edit an owner, click its name in the Owners pane on the left. |
-

CLI Commands

Use **owner tag create name** to create an owner. For example:

```
nrcmd> owner owner-1 create "First Owner" contact="Contact at owner-1"
```

Managing Regions

You can create regions to associate with address blocks, subnets, prefixes, links, and zones. You can list and add regions on a single page. Creating a region involves creating a tag name, full name, and contact name.

Local Advanced and Regional Advanced Web UI

-
- Step 1** From the **Administration** menu, choose **Regions** under the **Settings** submenu to open the List/Add Regions page . The regional cluster also includes pull and push functions.
- Step 2** Click the **Add Regions** icon in the Regions pane on the left.
- Step 3** Enter a unique region tag.
- Step 4** Enter a region name.
- Step 5** Enter an optional contact name.
- Step 6** Click **Add Region**.
- Step 7** To edit a region, click its name in the Regions pane on the left.
-

CLI Commands

Use **region tag create name** . For example:

```
nrcmd> region region-1 create "Boston Region" contact="Contact at region-1"
```

Centrally Managing Owners and Regions

As a regional or local CCM administrator, you can:

- Push owners and regions to local clusters.
- Pull local cluster owners and regions to the central cluster.

Each of these functions involves having at least one regional CCM administrator subrole defined (see [Roles, Subroles, and Constraints, on page 41](#)).

The following table describes the subroles required for these operations.

Table 7: Subroles Required for Central Administrator Management

Central Administrator Management Action	Required Regional Subroles
Create, modify, pull, push, or delete owners or regions	owner-region

Related Topics

[Pushing and Pulling Owners or Regions, on page 67](#)

Pushing and Pulling Owners or Regions

You can push owners or regions to, and pull them from, local clusters on the List/Add Owners page or List/Add Regions page, respectively, in the regional cluster web UI.

Related Topics

[Pushing Owners or Regions to Local Clusters, on page 67](#)

[Pulling Owners and Regions from the Replica Database, on page 67](#)

Pushing Owners or Regions to Local Clusters

Pushing owners or regions to local clusters involves choosing one or more clusters and a push mode.

Regional Web UI

-
- | | |
|---------------|--|
| Step 1 | From the Administration menu, choose Owners or Regions under the Settings submenu. |
| Step 2 | On the List/Add Owners or List/Add Regions page, click the Push All icon in the left pane, or click Push at the top of the Edit Owner page or Edit Region page, for a particular owner or region. This opens the Push Owner or Push Region page. |
| Step 3 | <p>Choose a push mode using one of the Data Synchronization Mode radio buttons.</p> <ul style="list-style-type: none"> • If you are pushing all the owners or regions, you can choose Ensure, Replace, or Exact. • If you are pushing a single owner or region, you can choose Ensure or Replace. <p>In both the above cases, Ensure is the default mode.</p> <p>Choose Replace only if you want to replace the existing owner or region data at the local cluster. Choose Exact only if you want to create an exact copy of the owner or region data at the local cluster, thereby deleting all owners or regions that are not defined at the regional cluster.</p> |
| Step 4 | Choose one or more local clusters in the Available field of the Destination Clusters and move it or them to the Selected field. |
| Step 5 | Click Push Data to Clusters . |
| Step 6 | On the View Push Owner Data Report or View Push Region Data Report page, view the push details, then click OK to return to the List/Add Owners or List/Add Regions page. |
-

Pulling Owners and Regions from the Replica Database

When you pull an owner or region, you are actually pulling it from the regional cluster replica database. Creating the local cluster initially replicates the data, and periodic polling automatically updates the replication. However, to ensure that the replica data is current with the local cluster, you can force an update before pulling the data.

Regional Web UI

-
- Step 1** From the **Administration** menu in the regional cluster web UI, choose **Owners** or **Regions** under the **Settings** submenu.
- Step 2** On the List/Add Owners or List/Add Regions page, click the **Pull Replica** icon in the left pane. This opens the Select Replica Owner Data to Pull or Select Replica Region Data to Pull page.
- Step 3** Click the **Replicate** icon in the Update Replica Data column for the cluster. (For the automatic replication interval, see [Replicating Local Cluster Data](#), on page 86.)
- Step 4** Choose a replication mode using one of the Mode radio buttons.
Leave the default Replace mode enabled, unless you want to preserve any existing owner or region properties at the local cluster by choosing Ensure.
- Note** We do not recommend that you create an exact copy of the owner or region data at the local cluster by choosing Exact.
- Step 5** Click **Pull All Owners** or **Pull All Regions** next to the cluster, or expand the cluster name and click **Pull Owner** or **Pull Region** to pull an individual owner or region in the cluster.
- Step 6** On the Report Pull Replica Owners or Report Pull Replica Regions page, click **Run**.
- Step 7** On the Run Pull Replica Owners or Run Pull Replica Region page, view the change set data, then click **OK**. You return to the List/Add Owners or List/Add Regions page with the pulled owners or regions added to the list.
-



Managing the Central Configuration

This chapter explains how to manage the central configuration at the Cisco Prime IP Express regional cluster.

- [Central Configuration Tasks, page 69](#)
- [Default Ports for Cisco Prime IP Express Services, page 70](#)
- [Licensing, page 71](#)
- [Configuring Server Clusters, page 74](#)
- [Central Configuration Management Server, page 88](#)
- [Simple Network Management, page 89](#)
- [Integrating Cisco PrimeIP Express SNMP into System SNMP, page 97](#)
- [Bring Your Own Device Web Server, page 97](#)
- [Polling Process, page 99](#)
- [Managing DHCP Scope Templates, page 101](#)
- [Managing DHCP Policies, page 103](#)
- [Managing DHCP Client-Classes, page 104](#)
- [Managing Virtual Private Networks, page 105](#)
- [Managing DHCP Failover Pairs, page 107](#)
- [Managing Lease Reservations, page 107](#)
- [Monitoring Resource Limit Alarms, page 109](#)
- [Local Cluster Management Tutorial, page 112](#)
- [Regional Cluster Management Tutorial, page 119](#)

Central Configuration Tasks

Central configuration management at the regional cluster can involve:

- Setting up server clusters, replicating their data, and polling subnet utilization and lease history data from them.
- Setting up routers.
- Managing network objects such as DHCP scope templates, policies, client-classes, options, networks, and virtual private networks (VPNs).
- Managing DHCP failover server pairs.

These functions are available only to administrators assigned the central-cfg-admin role. (The full list of functions for the central-cfg-admin are listed in [Table 5: Regional Cluster Administrator Predefined and Base Roles](#), on page 43.) Note that central configuration management does not involve setting up administrators and checking the status of the regional servers. These functions are performed by the regional administrator, as described in [Licensing](#), on page 71 and [Managing Servers](#), on page 129.

Default Ports for Cisco Prime IP Express Services

The following table lists the default ports used for the Cisco Prime IP Express services.

Table 8: Default Ports for Cisco Prime IP Express Services

Port Number	Protocol	Service
53	TCP/UDP	DNS
53	TCP/UDP	Caching DNS
67	UDP	DHCP client to server
67	TCP	Bulk or Active leasequery client to DHCP server
68	UDP	DHCP server to client
80	HTTP	BYOD web server client to server web UI
162	TCP	SNMP traps server to server
389	TCP	DHCP server to LDAP server
443	HTTPS	BYOD web server secure client to server web UI
546	UDP	DHCPv6 server to client
547	UDP	DHCPv6 client to server
647	TCP	DHCP failover server to server

Port Number	Protocol	Service
653	TCP	High-Availability (HA) DNS server to server
1234	TCP	Local cluster CCM server to server
1244	TCP	Regional cluster CCM server to server
4444	TCP	SNMP client to server
5480	HTTPS	Virtual Appliance
8080	HTTP	Local cluster client to server web UI
8090	HTTP	Regional cluster client to server web UI
8443	HTTPS	Local cluster secure client to server web UI
8453	HTTPS	Regional cluster secure client to server web UI

Firewall Considerations

When DNS (caching or authoritative) servers are deployed behind a stateful firewall (whether physical hardware or software, such as conntrack), it is recommended that:

- For at least UDP DNS traffic, stateful support be disabled if possible.
- If it is not possible to disable the stateful support, the number of allowed state table entries may need to be significantly increased.

DNS queries typically arrive from many different clients and requests from the same client may use different source ports. With thousands of queries per second, the number of these different sources can be large and if a firewall is using stateful tracking, it has to keep this state and does so for a period of time. Hence, you need to assure that the firewall can hold sufficient state - given the query traffic rates and the state time interval.

Licensing

Cisco Prime IP Express provides separate license for CCM, Authoritative DNS, Caching DNS, DHCP, and IPAM services or for combinations of these services. For more details on the Licensing, see the “License Files” section in the Overview chapter of the *Cisco Prime IP Express Installation Guide*.

You must have the Central Configuration Management (CCM) license to log into the UI. See [Logging In to the Web UIs](#), on page 13 for entering license data the first time you try to log in. You can add the additional service based licenses in the regional server after you log in.

Whenever you log into a regional or local cluster, the overall licensing status of the system is checked. If there are any violations, you will be notified of the violation and the details. This notification is done only once for each user session. In addition, you will be able to see a message on each page indicating the violation.

Regional Web UI

Choose **Licenses** from **Administration > User Access** to open the List/Add Product Licenses page. Click **Browse** to locate the license file, click the file, then click **Open**. If the license ID in the file is valid, the license key appears in the list of licenses with the message “Successfully added license file *filename*.” If the ID is not valid, the License field shows the contents of the file and the message “Object is invalid” appears.

The License Utilization section at the top of the page lists the type of license, the number of nodes allowed for the license, and the actual number of nodes used. Expand the section by clicking the plus (+) sign. The license utilization for each licensed service is listed separately in this section.

The Right To Use and the In Use counts are displayed for each licensed service. The Right To Use value will be the aggregation of the counts across all added licenses for that service. The ‘total in use’ value will be the aggregation of the latest utilization numbers obtained from all the local clusters. Only the services having a positive Right to use or In Use count will be listed in this section.

Licenses and usage count of earlier versions of Cisco IP Express will be listed under a separate section “ip-node”.

The **Expert** mode attribute lets you specify how often license utilization is collected from all the local clusters. Changes to this setting require a server restart to take effect. You can set this attribute at the Edit CCM Server page. The default value is 4 hours.

CLI Commands

Use **license file create** to register licenses that are stored in file. The file referenced should include its absolute path or path relative to where you execute the commands. For example:

```
nrcmd-R> license "C:\licenses\product.licenses" create
```

Use **license list** to list the properties of all the created licenses (identified by key), and **license listnames** to list just the keys. Use **license key show** to show the properties of a specific license key.

Adding License

Cisco will e-mail you one or more license files after you register the Cisco Prime IP Express Product Authorization Key (PAK) on the web according to the Software License Claim Certificate shipped with the product. Cisco administers licenses through a FLEXlm system. Once you have the file or files:

Regional Web UI

-
- Step 1** Locate the license file or files in a directory (or on the desktop) that is easy to find.
- Step 2** On the List/Add Product Licenses page, browse for each file by clicking the **Choose File** button.
- Note** The List/Add Product Licenses option is only available at the Regional.

- Step 3** In the Choose file window, find the location of the initial license file, then click **Open**.
- Step 4** If the license key is acceptable, the Add Superuser Administrator page appears immediately.
- Step 5** To add further licenses, from **Administration** menu choose **Licenses** under the **User Access** submenu to open the List/Add Product Licenses page. Click **Browse** to open the Choose file window, locate the additional license file, then click **Open**. If the key in the file is acceptable, the key, type, count, and expiration date appear, along with whether it is an evaluation key. If the key is not acceptable, the page shows the license text along with an error message. For the list of license types, see [Licensing, on page 71](#).
Above the table of licenses is a License Utilization area that, when expanded, shows the license types along with the total nodes that you can use and those actually used.
If Cisco Prime IP Express is installed as a distributed system, the license management is done from the regional cluster. You will not have the option of adding licenses in local cluster.

Registering a Local Cluster that is Behind a NAT

License management is done from the regional cluster when Cisco Prime IP Express is installed. You must install the regional cluster first, and load all licenses in the regional cluster. A local cluster can register with a regional either by registering with the regional cluster during the installation process. However, if the local cluster is behind a NAT instance, then the registration may fail because the initial request does not reach the regional cluster.

In Cisco Prime IP Express 8.3 and later, you can register a local cluster that is behind a NAT instance by initiating the registration from the local cluster. To register a local cluster that is spanned by a NAT instance, you must ensure that Cisco Prime IP Express 8.3 or later is installed on both the regional and local clusters. You can also verify the license utilization for the local cluster.



Note

To register a local cluster when the regional cluster is behind a NAT instance, you need to register the local cluster from the regional server by registering the local cluster from the regional server, selecting the services and re-synchronizing the data.

To register a local cluster that is behind a NAT instance, do the following:

Local Web UI

- Step 1** From **Administration** menu, choose **Licenses** under the **User Access** submenu to open the List Licenses page. On the List Licenses page, add the details of the regional cluster.
- Enter the IP address of the regional cluster.
 - Enter the SCP port of the regional cluster (1244 is the preset value).
 - Select the IP address of the local cluster that you want to register.
 - Select the component services that you want to register for the local cluster.
- Step 2** Click **Register**.
- Note** The regional CCM server maintains the license utilization history for all the local clusters in the Cisco Prime IP Express system for all counted services (DHCP, DNS, and CDNS).
To view the license utilization for the local cluster, click **Check Poll Status**.

CLI Commands

Use the following command to register or re-register a local cluster:

```
nrcmd> license register [cdns|dns|dhcp[,...]] [<regional-ip>] [<regional-port>]
```

License History

The License History page allows you to view the licenses utilized in the specified time frame.

Regional Web UI

-
- Step 1** Log into the regional cluster as superuser.
 - Step 2** From the **Administration** menu, choose **Administrators** to open the List/Add Administrators page for the local cluster version of this page, which is essentially identical.
 - Step 3** Click the Add Administrators icon in the Administrators pane, enter **example-regional-admin** in the Name field, then **examplereg** in the Password field in the Add Administrator dialog box, then click Add Administrator.
 - Step 4** Multiselect **central-cfg-admin-group** (for cluster administration) and **regional-admin-group** (for user administration) in the Groups drop-down list.
 - Step 5** Click **Save**.
-

CLI Command

Use **license showUtilHistory –full** view the number of utilized IP nodes against the RTUs (Right-to-Use) (see the **license** command in the CLIGuide.html file in the /docs directory for syntax and attribute descriptions).

Configuring Server Clusters

Server clusters are groupings of CCM, DNS, CDNS, and DHCP servers at local cluster locations. For example, an organization might have Boston and Chicago clusters of DNS and DHCP servers. A central administrator might want to affect how addresses are allocated at these clusters, or poll subnet utilization or lease history data from them. The central administrator might even want to connect to those local clusters, if the required permissions exist, to view changes there or restart the servers.

View the created clusters on the View Tree of Cluster Servers page. To get there, click **Clusters**. Once the page is populated with clusters, it shows some rich information and provides some useful functions. The Go Local icon allows single sign-on to a local cluster web UI, if an equivalent administrator account exists at the local cluster.

The View Tree of Clusters page might have been populated by manually adding clusters on the List/Add Remote Clusters page, or automatically when adding and synchronizing with routers, which also creates server clusters. The cluster names are links that you can click to edit the cluster information. The re-synchronization, replication, and polling functions are described further on in this chapter.

The DHCP server may have the Related Servers icon next to the DHCP server for the cluster. Click this icon to open the List Related Servers for DHCP Server page (see [Listing Related Servers for DHCP, DNS, and TCP Listener Servers](#), on page 77). These servers can be DNS, or DHCP failover servers.

Related Topics

- [Adding Local Clusters](#), on page 75
- [Editing Local Clusters](#), on page 76
- [Listing Related Servers for DHCP, DNS, and TCP Listener Servers](#), on page 77
- [Connecting to Local Clusters](#), on page 86
- [Synchronizing with Local Clusters](#), on page 86
- [Replicating Local Cluster Data](#), on page 86
- [Viewing Replica Data](#), on page 87
- [Polling Lease History Data](#), on page 100
- [Deactivating, Reactivating, and Recovering Data for Clusters](#), on page 87
- [Enabling Lease History Collection](#), on page 101

Adding Local Clusters

Adding local clusters to the regional cluster is the core functionality of the central-cfg-admin role.

To enable subnet utilization and lease history data collection, see [Polling Lease History Data](#), on page 100.

The minimum required values to add a cluster are its name, IP address of the machine, administrator username, and password. The cluster name must be unique and its IP address must match that of the host where the CNRDB database is located. Obtain the SCP and HTTP ports, username, and password from the local cluster administrator. The preset value at Cisco Prime IP Express installation for the SCP port is 1234 and the HTTP port is 8080.

You can also set whether you want outbound connections to local servers to be secure by setting the *use-ssl* attribute to optional or required. It is set to optional by default, and it requires the Cisco Prime IP Express Communications Security Option installed to be effective.

Regional Web UI

From the **Operate** menu, choose **Manage Servers** under the **Servers** submenu. This opens the Manage Servers page. View the local clusters on this page. You can also add server clusters on the List/Add Remote Clusters page. The List/Add Remote Clusters page provide the following functions:

- Connect to a local cluster web UI for local administration.
- Resynchronize with a local cluster to reconcile updates there.
- Pull data over to a regional cluster replica database.
- Purge replica to clear the bad replica data without deleting/re-adding the cluster. Whenever you perform purge replica, you must perform manual replication to the get the replica data again.



Note This option appears only in Expert mode.

- Query subnet utilization data from a local cluster. This function appears only if you are assigned the regional-addr-admin role with at least the subnet-utilization subrole.
- Query lease history data from a local cluster. This function appears only if you are assigned the regional-addr-admin role with at least the lease-history subrole.

To add a cluster, click the **Add Manage Clusters** icon in the **Manage Clusters** pane. This opens the Add Cluster dialog box. For an example of adding a local cluster, see [Create the Local Clusters, on page 121](#). Click **Add Cluster** to return to the List/Add Remote Clusters page.

Local Web UI

You can also manage clusters in the local web UI. See [Configuring Clusters in the Local Web UI, on page 20](#) for details.

CLI Commands

To add a cluster, use **cluster name create address** to give the cluster a name and address and set the important attributes. For example:

```
nrcmd> cluster example-cluster create 192.168.100.101 admin=admin password=changeme
```

Note that the administrator must be a superuser to fully synchronize at the local cluster.

Editing Local Clusters

Editing local clusters at the regional cluster is the core functionality of the central-cfg-admin role.

Regional Web UI

To edit a local cluster, click its name on the Manage Clusters pane to open the Edit Remote Cluster page. This page is essentially the same as the List/Add Remote Clusters page, except for an additional attribute unset function. You can choose the service (dhcp, dns, cdns, or none) that you want to run in the local by checking/unchecking the check boxes provided in the **Local Services** area. Make your changes, then click **Save**.

Local Web UI

You can also edit clusters in the local web UI. See [Configuring Clusters in the Local Web UI, on page 20](#) for details.

CLI Commands

To edit a local cluster, use **cluster name set attribute** to set or reset the attributes. For example:

```
nrcmd> cluster Example-cluster set poll-replica-interval=8h
```

Listing Related Servers for DHCP, DNS, and TCP Listener Servers

If you have related DNS or DHCP failover servers (see the *"Setting Up Failover Server Pairs"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*), you can access the attributes for these servers.

Regional Web UI

On the Failover Pairs or HA DNS Server Pair page, click the Manage Failover Servers tab and then click Related Servers tab to open the DHCP Related Server Attributes page. This page shows the communication and failover states the servers are in. The following table describes the attributes on this page. (For this page to appear, you must be assigned the central-cfg-admin role with the dhcp-management subrole.)

Table 9: Attributes for Related Servers

Related Server Attribute	Description
<i>Related Server Type</i>	Type of related server: DHCP, DNS, or LDAP.
<i>Related Server IP Address</i>	IP address of the related server. For DHCP failover partners, click this link to open the View Failover Related Server page (see Table 10: Attributes for DHCP Related Failover Servers , on page 78).
<i>Communications</i>	State of the communication—None, OK, or Interrupted.
<i>Requests</i>	Applies to DNS or LDAP related servers only, the number of requests from these servers.
<i>State</i>	For DHCP failover—None, Startup, Normal, Communications-interrupted, Partner-down, Potential-conflict, Recover, Paused, Shutdown, or Recover-done. For High-Availability (HA) DNS—Send-Update, Probe, or ha-state-unknown. Only the server that is successfully updating can be in Send-Update state. The partner server not sending updates is then always in Probe or unknown state. When the DHCP server comes up if there is no client activity, both DNS servers are often in the unknown state. This changes when the DHCP server tries to do DNS updates.
<i>Partner Role</i>	For DHCP failover only, the failover role of the partner—Main or Backup.
<i>Partner State</i>	For DHCP failover only, the partner's state—None, Startup, Normal, Communications-interrupted, Partner-down, Potential-conflict, Recover, Paused, Shutdown, or Recover-done.

Related Server Attribute	Description
<i>Update Response Complete</i>	For DHCP failover only, the percentage of completed update responses, valid only if there are outstanding update responses.

Table 10: Attributes for DHCP Related Failover Servers

Failover Partner Attribute	Description
General attributes	
<i>failover-pair-name</i>	The name of the failover pair object used to manage this server.
<i>current-time</i>	Current time on the server returning this object.
<i>comm-state</i>	None, OK, or Interrupted.
<i>smoothed-time-delta</i>	The time difference between the local server and the partner server. If the local server time is ahead of the partner server time, the attribute value is positive. If the local server time is behind the partner server time, the attribute value is negative. If the servers are not communicating, the last known attribute value is recorded.
<i>maximum-client-lead-time</i>	Current maximum client lead time (MCLT) on this system.
<i>sequence-number</i>	Sequence number unique across failover objects, if different from the sequence in the lease, the lease is considered “not up to date” independent of the sf-up-to-date lease flag.
<i>load-balancing-backup-pct</i>	The current failover load balancing backup percentage. If the backup percentage is zero, failover load balancing is not in use (disabled).
Local server information	
<i>our-ipaddr</i>	IPv4 address of the interface to this server.
<i>our-ip6address</i>	IPv6 address of the interface to this server.
<i>role</i>	Failover role of the server returning this object—None, Main, or Backup.

Failover Partner Attribute	Description
<i>state</i>	State of the local server—None, Startup, Normal, Communications- interrupted, Partner-down, Potential-conflict, Recover, Paused, Shutdown, or Recover-done.
<i>start-time-of-state</i>	Time at which the current failover state began.
<i>start-of-comm-interrupted</i>	Time at which this partner most recently went into communications- interrupted state. This is valid across reloads, while the start-time-of-state never has a time earlier than the most recent server reload.
<i>est-end-recover-time</i>	Valid if <i>update-request-in-progress</i> is not set to None. If it appears, the time at which the server enters the recover- done state if the update request outstanding is complete. If it does not appear, then the server enters recover-done whenever update-request is completed.
<i>use-other-available</i>	If false or unset, then this server cannot use other-available leases. If true, then the server can use other-available leases. Valid at all times, but should only be true if in partner-down state.
<i>use-other-available-time</i>	If, in partner-down state, the <i>use-other-available</i> is false or unset, the time when <i>use-other-available</i> will go to true.
<i>safe-period-remaining</i>	Duration in seconds remaining in safe-period. If not set to 0, then this server is currently running down a safe period with respect to its partner.
<i>load-balancing-local-hba</i>	The current hash bucket assignment of the local server, usually shown as a range of the hash bucket numbers. (See RFC 3074.)
<i>request-buffers-in-use</i>	The number of failover request buffers the DHCP server is using at the time the statistics are calculated.
<i>decaying-max-request-buffers-in-use</i>	The maximum number of failover request buffers that have recently been in use.
<i>request-buffers-allocated</i>	The number of request buffers that the server has allocated to support the failover capability.
<i>connection-start-time</i>	The time at which the most recent connection started. This value is set whenever a connection is started, and it not cleared when a connection ended.

Failover Partner Attribute	Description
<i>connection-end-time</i>	The time at which the most recent connection ended. This value is set whenever a connection is ended, and it not cleared when a new connection starts.
Partner server information	
<i>ipaddr</i>	IP address of the partner server.
<i>ip6address</i>	IPv6 address of the partner server.
<i>partner-role</i>	Failover role of the partner of the server returning this object—None, Main, or Backup.
<i>partner-state</i>	Last known state which the partner end of the failover relationship is in—None, Startup, Normal, Communications-interrupted, Partner-down, Potential-conflict, Recover, Paused, Shutdown, or Recover-done.
<i>start-time-of-partner-state</i>	Time at which the partner current failover state began.
<i>est-partner-end-recover- time</i>	If the <i>partner-state</i> is Recover, an estimated prediction of when the partner will time out its MCLT and finish being in recover state.
<i>last-comm-ok-time</i>	Time at which this server last found communications to be OK.
<i>load-balancing-partner- hba</i>	The current hash bucket assignment of the partner server, usually shown as a range of the hash bucket numbers. (See RFC 3074.)
<i>partner-vendor-major- version</i>	The vendor ID major version from the partner server.
<i>partner-vendor-minor- version</i>	The vendor ID minor version from the partner server.
Update requests sent to partner	
<i>update-request- outstanding</i>	If None or unset, then the server does not have an update request queued for its partner. If not set to None, then it does have an update request queued for its failover partner. Valid values are None, Update, and Update-all.
<i>update-request-start-time</i>	Time at which any <i>update-request-outstanding</i> request was started.
<i>update-request-done-time</i>	Time at which the last of any update request completed.

Failover Partner Attribute	Description
<i>v6-update-response-in-progress</i>	The type and origin of the response.
<i>v6-update-response-percent-complete</i>	The percent complete of the current IPv6 update response.
<i>v6-update-response-start-time</i>	The time that the IPv6 update response mentioned in <i>v6-update-response-in-progress</i> was started.
<i>v6-update-response-done-time</i>	The time that the most recent IPv6 update response sent an update done to the partner server.
Update requests processed for partner	
<i>update-response-in- progress</i>	If this server is processing an update response, gives information about the type and origin of the response.
<i>update-response-percent- complete</i>	If <i>update-response-outstanding</i> appears, the percent complete of the current update response.
<i>update-response-start- time</i>	Time that the update response mentioned in <i>update-response-in-progress</i> was started.
<i>update-response-done- time</i>	Time that the most recent update response sent an update done to the partner server.
Load Balancing Counters	
<i>load-balancing-processed- requests</i>	The number of server processed requests, both IPv4 and IPv6, subject to load balancing. This counter includes only the requests made after the latest transition of server to normal state.
<i>load-balancing-dropped- requests</i>	The number of server dropped requests, both IPv4 and IPv6, subject to load balancing. This counter includes only the requests made after the latest transition of server to normal state.
<i>load-balancing-processed- total</i>	The number of server processed requests, both IPv4 and IPv6, subject to load balancing. This counter includes the requests since this server was last started or reloaded.
<i>load-balancing-dropped- total</i>	The number of server dropped requests, both IPv4 and IPv6, subject to load balancing. This counter includes the requests since this server was last started or reloaded.
Binding Update or Ack Counters (this connection)	

Failover Partner Attribute	Description
<i>binding-updates-sent</i>	The number of binding update (BNDUPD) messages sent to the failover partner.
<i>binding-acks-received</i>	The number of binding acknowledgement (BNDACK) messages received from the failover partner.
<i>binding-updates-received</i>	The number of binding update (BNDUPD) messages received from the failover partner.
<i>binding-acks-sent</i>	The number of binding acknowledgement (BNDACK) messages sent to the failover partner.
<i>v6-binding-updates-sent</i>	The number of IPv6 binding updates (BNDUPD6) messages received from the failover partner since the start of the most recently established connection.
<i>v6-binding-acks-received</i>	The number of IPv6 binding acknowledgements (BNDACK6) messages received from the failover partner since the start of the most recently established connection.
<i>v6-binding-updates-received</i>	The number of IPv6 binding updates (BNDUPD6) messages received from the failover partner since the start of the most recently established connection.
<i>v6-binding-acks-sent</i>	The number of IPv6 binding acknowledgements (BNDACK6) messages sent to the failover partner since the start of the most recently established connection.
<i>Binding Update/Ack Counters Totals</i>	
<i>binding-updates-sent-total</i>	The number of IPv4 binding updates (BNDUPD) messages sent to the failover partner since the most recent statistics reset.
<i>binding-acks-received-total</i>	The number of IPv4 binding acknowledgements (BNDACK) messages received from the failover partner since the most recent statistics reset.
<i>binding-updates-received-total</i>	The number of IPv4 binding updates (BNDUPD) messages received from the failover partner since the most recent statistics reset.
<i>binding-acks-sent-total</i>	The number of IPv4 binding acknowledgements (BNDACK) messages sent to the failover partner since the most recent statistics reset.

Failover Partner Attribute	Description
<i>v6-binding-updates-sent-total</i>	The number of IPv6 binding updates (BNDUPD6) messages sent to the failover partner since the most recent statistics reset.
<i>v6-binding-acks-received-total</i>	The number of IPv6 binding acknowledgements (BNDACK6) messages received from the failover partner since the most recent statistics reset.
<i>v6-binding-updates-received-total</i>	The number of IPv6 binding updates (BNDUPD6) messages received from the failover partner since the most recent statistics reset.
<i>v6-binding-acks-sent-total</i>	The number of IPv6 binding acknowledgements (BNDACK6) messages sent to the failover partner since the most recent statistics reset.
<i>Flow Control Counters (this connection)</i>	
<i>current-binding-updates-in-flight</i>	The current number of binding updates (both IPv4 and IPv6) that are currently in-flight (sent).
<i>current-binding-updates-queued</i>	The current number of binding updates (both IPv4 and IPv6) that are queued at present.
<i>maximum-binding-updates-in-flight</i>	The maximum number of binding updates (both IPv4 and IPv6) that were in-flight (sent) at one time.
<i>maximum-binding-updates-queued</i>	The maximum number of binding updates (both IPv4 and IPv6) that were queued at one time.
<i>last-binding-update-sent-time</i>	The time the last binding update (either IPv4 or IPv6) was sent.
<i>last-binding-ack-received-time</i>	The time the last IPv4 or IPv6 binding acknowledgement (whether NAKed or not) was received.
<i>last-binding-update-received-time</i>	The time the last binding update (either IPv4 or IPv6) was received.
<i>last-binding-ack-sent-time</i>	The time the last IPv4 or IPv6 binding acknowledgement (whether NAKed or not) was sent.

Table 11: Attributes for DNS Related Failover Servers

Failover Partner Attribute	Description
General attributes	
<i>current-time</i>	Current time on the server returning this object.
<i>ipaddr</i>	IP address
<i>comm-state</i>	None.
<i>dns-server-state</i>	PROBE.
<i>probe-polling-event-id</i>	Zero.
<i>requests</i>	Zero.
HA DNS Configuration information	
<i>ha-dns-role</i>	STANDALONE-DNS.
<i>dns-timeout</i>	Number of milliseconds that the DHCP server will wait for a response from the DNS server for a dynamic dns update, before retrying dynamic dns update.
<i>max-dns-retries</i>	Number of times that the DHCP server will try to send dynamic updates to a DNS server.
<i>ha-dns-failover-timeout</i>	Maximum time period, in seconds, the DHCP server will wait for a reply from a DNS server, before the DHCP will failover to use next DNS Server to perform the dynamic-update. Default value is 30 seconds.
<i>ha-dns-probe-timeout</i>	If cnr-ha-dns is enabled, DHCP server will use this timer to co-ordinate and reduce latency in failing over between HA-DNS servers, when HA-DNS servers are in COMMUNICATION-INTERRUPTED state or SYNCHRONIZING. Default value is 3 seconds.
<i>ha-dns-probe-retry</i>	If cnr-ha-dns is enabled, DHCP server will use this retry count and ha-dns-probe-timeout to co-ordinate and reduce latency in failing over between HA-DNS servers, when HA-DNS servers are in COMMUNICATION-INTERRUPTED state or SYNCHRONIZING. Default value is 1 retry attempt.
Current HA DNS State Information	

Failover Partner Attribute	Description
<i>ha-dns-state</i>	State of HA-DNS Servers interaction.
<i>last-ha-dns-state</i>	Failover role of the partner of the server returning this object—None, Main, or Backup.
<i>last-ha-dns-state-change- time</i>	Time at which the failover role was last changed.
<i>last-reply-received-time</i>	Time at which the last reply was received.
<i>last-ha-dns-role-switch- time</i>	Time at which the failover role was changed from one state to another.

Table 12: Attributes for TCP Listener Related Servers

Failover Partner Attribute	Description
General attributes	
<i>comm-state</i>	None.
<i>current-connections</i>	Zero
<i>ipaddr</i>	IP address.
<i>ip6addr</i>	IPv6 address.
<i>name</i>	foobar string (w/o null terminator).
<i>port</i>	Port number.
<i>rejected-connections</i>	Zero.
<i>total-connections</i>	Zero.

Other controls are available on these pages:

- To refresh the data on the Related Server tab, click **Refresh Data**.
- On the Related Server tab, if the partner is in the Communications-interrupted failover state, you can click **Set Partner Down** in association with an input field for the partner-down date setting. This setting is initialized to the value of the *start-of-communications- interrupted* attribute. (In Normal web UI mode, you cannot set this date to be an earlier value than the initialized date. In Expert web UI mode, you can set this value to any date.) After clicking **Set Partner Down**, you return to the List Related Servers for DHCP Server page to view the result of the partner-down action. Never set both partners to Partner Down mode.
- To return from the List Related Servers for DHCP Server page or View Failover Related Server page, click **Return**.

CLI Commands

To list the related servers for a DHCP server, use **dhcp getRelatedServers**.

Connecting to Local Clusters

In the web UI, if you have an equivalent administrator account at the local cluster, you can single sign-on to the local cluster Manage Servers page by clicking the **Connect** icon on the List/Add Remote Clusters page. To return to the regional cluster web UI, click the **Return** icon at the top right corner of the local cluster page. If you do not have an equivalent account at the local cluster, the Connect icon opens the local cluster login page.

Synchronizing with Local Clusters

Synchronization is configuring regional and local clusters so that they can work together in a unified fashion. When you synchronize:

- 1 The list of local servers are copied to the regional cluster.
- 2 A shared secret is established between the regional and local clusters for single sign-on.

Synchronization occurs once when you create a local cluster at the regional cluster. However, changes might occur at the local cluster periodically, requiring you to re synchronize with it. For example, you might change the username and password used to make local connections. Resynchronization does not happen automatically—you must click the **Resynchronize** icon next to the cluster name on the List/Add Remote Clusters page. The result is a positive confirmation for success or an error message for a failure.

When you upgrade the local cluster, you should also resynchronize the cluster. For synchronization to be effective, the user account specified for the local cluster must be a superuser. If you get a synchronization error message, check the local cluster to ensure that it is running properly.

**Note**

When you resynchronize clusters at the regional cluster, an automatic reinitialization of replica data occurs. The result is that for larger server configurations, resynchronization might take several minutes. The benefit, however, is that you do not need a separate action to update the replica data.

Replicating Local Cluster Data

Replication is copying the configuration data from a local server to the regional cluster replica database. Replication needs to occur before you can pull DHCP object data into the regional server database. During replication:

- 1 The current data from the local database is copied to the regional cluster. This usually occurs once.
- 2 Any changes made in the master database since the last replication are copied over.

Replication happens at a given time interval. You can also force an immediate replication by clicking the **Replicate** icon on the List/Add Remote Clusters page.

You can set the automatic replication interval on the Add Server Cluster page, or adjust it on the Edit Server Cluster page, using the *poll-replica-interval* attribute. This interval is preset at four hours. You can also set the fixed time of day to poll replica data by using the *poll-replica-offset* attribute; its default value is zero hours (no offset). The *poll-replica-rrs* attribute controls the replication of RR data without disabling other data replication. This attribute is present in Manage Servers and Manage Clusters page and has the values -

none, all, and protected. If *poll-replica-rrs* is set to none, no RR data will be replicated for this cluster. If unset, the CCM server setting will apply.



Caution

If the replica database is corrupted in any way, the regional CCM server will not start. If you encounter this problem, stop the regional service, remove (or move) the replica database files located in the *install-path* /regional/data/replica directory (and the log files in the /logs subdirectory), then restart the regional server. Doing so recreates the replica database without any data loss.

Viewing Replica Data

In the web UI, you can view the replica data cached in the replica database at the regional cluster by choosing **View Replica Data** from **Servers** submenu under the **Operate** menu. This opens the View Replica Class List page.

Regional Web UI

Select the:

- 1 Cluster in the Select Cluster list.
- 2 Object class in the Select Class list.
- 3 Replicate the data for the cluster and class chosen. Click the **Replicate Data for Cluster** button.
- 4 View the replica data. Click **View Replica Class List**, which opens a List Replica Data for Cluster page for the cluster and specific class of object you choose. On this page, you can:
 - Click the name of an object to open a View page at the regional cluster. Return to the List Replica page by clicking **Return to object List**.



Note

The List Replica Address Blocks and List Replica Subnets pages do not provide this function. To view the address blocks or subnets for the local cluster, use the **Go Local** icon.

- Click the **Connect** icon to go to the List page for the object at the local cluster. Return to the List Replica *object* page by clicking the **Return** icon.

Click **Return** on the List Replica Data for Cluster page to return to the View Replica Class List page.

Purging Replica Data

In the Regional web UI (Expert mode), you can clear the bad replica data without deleting/re-adding the clusters by clicking the **Purge Replica** icon on the List/Add Remote Clusters page. Whenever you perform purge replica, you must perform manual replication to get the replica data again.

Deactivating, Reactivating, and Recovering Data for Clusters

Deactivating a cluster might be necessary if you suspect that a hard disk error occurred where configuration data could have been lost. You can deactivate the cluster, remedy the problem, recover cluster data from the

replica database, then reactivate the cluster. This saves you from having to delete and then recreate the cluster with all of its data lost in the process.

Deactivating, reactivating, and recovering the data for a cluster is available only in the web UI, and you must be an administrator assigned the central-config-admin role.

Data that is not recovered (and that you need to manually restore) includes:

- Contents of the **cnr.conf** file (see [Modifying the cnr.conf File, on page 156](#))
- Web UI configuration files
- Unprotected DNS resource records
- Administrator accounts



Note

If the local secret db is lost, the old references are no longer valid, even though they are restored. To recover your passwords, you have to use central management for your admins, and then push them to your local clusters. Routers, since they have their own secrets, also need to be centrally managed and then should be re-pushed. For the local cluster partner objects, running the sync from regional will create valid objects, but the old cluster objects may need to be deleted first.

- Lease history
- Extension scripts



Note

Restoring the data to a different IP address requires some manual reconfiguration of such things as DHCP failover server pair and High-Availability (HA) DNS server pair addresses.

Regional Web UI

Deactivate a cluster by clicking the Deactivate button for the cluster. This immediately changes the button to Reactivate to show the status of the cluster. Deactivating a cluster disables deleting, synchronizing, replicating data, and polling subnet utilization and lease history. These operations are not available while the cluster is deactivated.

Deactivating the cluster also displays the Recover icon in the Recover Data column of the cluster. Click this icon to recover the replica data. This opens a separate “in process” status window that prevents any operations on the web UI pages while the recovery is in process. As soon as the recovery is successful, the disabled functions are again enabled and available.

To reactivate the cluster, click the Reactivate button to change back to the Deactivate button and show the status as active.

Central Configuration Management Server

The CCM servers at the local and regional clusters provide the infrastructure for Cisco Prime IP Express operation and user interfaces. The CCM Server reads, writes, and modifies the Cisco Prime IP Express database (CCM DB). The main purpose of the CCM Server is to store and propagate data from the user to the protocol servers, and from the servers back to the user.

The change set is the fundamental unit of change to a data store. It sends incremental changes to a replicating server and provides an audit log for changes to the data store. Change sets consist of lists of change entries that are groups of one or more changes to a single network object. The web UI provides a view of the change sets for each data store.

Managing CCM Server

You can view logs and startup logs; edit the server attributes.

To view logs and startup logs, in the local cluster web UI, from the **Operate** menu, choose **Manage Servers** to open the Manage Servers page.

Editing CCM Server Properties

You can edit the CCM server properties using the Edit CCM Server page.

Local Basic or Advanced Web UI

-
- | | |
|---------------|---|
| Step 1 | To access the CCM server properties, choose Manage Servers under Operate menu to open the Manage Servers page. |
| Step 2 | Click Local CCM Server in the Manage Servers pane on the left. The Edit Local CCM Server page appears. This page displays all the CCM server attributes. |
| Step 3 | Modify the settings as per your requirement. |
| Step 4 | Click Save to save the CCM server attribute modifications. |
-

Simple Network Management

The Cisco Prime IP Express Simple Network Management Protocol (SNMP) notification support allows you to query the DHCP and DNS counters, be warned of error conditions and possible problems with the DNS and DHCP servers, and monitor threshold conditions that can indicate failure or impending failure conditions.

Cisco Prime IP Express implements SNMP Trap Protocol Data Units (PDUs) according to the SNMPv2c standard. Each trap PDU contains:

- Generic-notification code, if enterprise-specific.
- A specific-notification field that contains a code indicating the event or threshold crossing that occurred.
- A variable-bindings field that contains additional information about certain events.

Refer to the Management Information Base (MIB) for the details. The SNMP server supports only reads of the MIB attributes. Writes to the attributes are not supported.

The following MIB files are required:

- **Traps**—CISCO-NETWORK-REGISTRAR-MIB.my and CISCO-EPM-NOTIFICATION-MIB.my
- **DNS server**—CISCO-DNS-SERVER-MIB.my

**Note**

The Caching DNS server requires only a subset of the DNS MIB when it is operating. Caching DNS server only supports the *server-start* and *server-stop* notification events.

- **DHCPv4 server**—CISCO-IETF-DHCP-SERVER-MIB.my
- **DHCPv4 server capability**—CISCO-IETF-DHCP-SERVER-CAPABILITY.my
- **DHCPv4 server extensions**—CISCO-IETF-DHCP-SERVER-EXT-MIB.my
- **DHCPv4 server extensions capability**—CISCO-IETF-DHCP-SERVER-EXT-CAPABILITY.my
- **DHCPv6 server**—CISCO-NETREG-DHCPV6-MIB.my (experimental)

**Note**

The MIB, CISCO-NETREG-DHCPV6-MIB is defined to support query of new DHCP v6 related statistics and new DHCP v6 traps.

These MIB files are available in the /misc directory of the Cisco Prime IP Express installation path.

The following URL includes all files except the experimental CISCO-NETREG-DHCPV6-MIB.my file:

<ftp://ftp.cisco.com/pub/mibs/supportlists/cnr/cnr-supportlist.html>

The following dependency files are also required:

- **Dependency for DHCPv4 and DHCPv6**—CISCO-SMI.my
- **Additional dependencies for DHCPv6**—INET-ADDRESS-MIB.my

These dependency files are available along with all the MIB files at the following URL:

<ftp://ftp.cisco.com/pub/mibs/v2/>

To get the object identifiers (OIDs) for the MIB attributes, go to the equivalently named .oid file at:

<ftp://ftp.cisco.com/pub/mibs/oid/>

Related Topics

[How Notification Works](#), on page 92

[Handling SNMP Queries](#), on page 96

Setting Up the SNMP Server

To perform queries to the SNMP server, you need to set up the server properties.

Local Basic or Advanced and Regional Web UI

-
- Step 1** From the **Operate** menu, choose **Manage Servers** under the **Servers** submenu to open the Manage Servers page (see [Managing Servers, on page 129](#)).
- Step 2** Click the **Local SNMP Server** link to open the Edit Local SNMP Server page.
- Step 3** The *Community string* attribute is the password to access the server. (The community string is a read community string only.) The preset value is **public**.
- Step 4** You can specify the Log Settings, Miscellaneous Options and Settings, and Advanced Options and Settings:
- **trap-source-addr**—Optional sender address to use for outgoing traps.
 - **trap-source-ip6address**—Optional sender IPv6 address to use for outgoing traps.
 - **server-active**—Determines whether the SNMP server is active for queries. The default value is true. If set to false, the server will run, but is not accessible for queries and does not send out traps.
 - **cache-ttl**—Determines how long the SNMP caches responds to queries, default to 60 seconds.
- Step 5** To manage the SNMP server interfaces in the Advanced mode, click the **Network Interfaces** tab. You can view the default configured network interfaces, and create and edit additional ones. To create and edit them, you must be assigned the server-management subrole of the ccm-admin role.
- Step 6** To manage trap recipients for the server:
- a) Click the **Trap Recipients** tab.
 - b) Enter the name of the trap recipient.
 - c) Enter the IPv4 and/or IPv6 address of a trap recipient.
 - d) Click **Add Trap Recipient**.
 - e) Repeat for each additional trap recipient.
 - f) To set the port, community string, and agent address for a trap recipient, click its name on the Trap Recipients tab to open the Edit Trap Recipient page, then set the values.
- Step 7** Complete the SNMP server setup by clicking **Save**.
-

CLI Commands

To set the community string in the CLI so that you can access the SNMP server, use **snmp set community=name**. Use **snmp set trap-source-addr** to set the trap source IPv4 address. Use **snmp set trap-source-ip6address** to set the trap source IPv6 address. Use **snmp disable server-active** to deactivate the SNMP server and **snmp set cache-ttl=time** to set the cache time-to-live.

To set trap recipients, use **trap-recipient**, in the following syntax to include the IP address:

```
nrcmd> trap-recipientnamecreate ip-addr=
nrcmd> trap-recipientnamecreate ip6address=
```

You can also add the *agent-address*, *community*, and *port-number* values for the trap recipient.

Other SNMP-related commands include **snmp disable server-active** to prevent the server from running when started and the **snmp-interface** commands to configure the interfaces.

How Notification Works

Cisco Prime IP Express SNMP notification support allows a standard SNMP management station to receive notification messages from the DHCP and DNS servers. These messages contain the details of the event that triggered the SNMP trap.

Cisco Prime IP Express generates notifications in response to predetermined events that the application code detects and signals. Each event can also carry with it a particular set of parameters or current values. For example, the *free-address-low-threshold* event can occur in the scope with a value of 10% free. Other scopes and values are also possible for such an event, and each type of event can have different associated parameters.

The following table describes the events that can generate notifications.

Table 13: SNMP Notification Events

Event	Notification
Address conflict with another DHCP server detected (<i>address-conflict</i>)	An address conflicts with another DHCP server.
DNS queue becomes full (<i>dns-queue-size</i>)	The DHCP server DNS queue fills and the DHCP server stops processing requests. (This is usually a rare internal condition.)
Duplicate IP address detected (<i>duplicate-address</i> and <i>duplicate-address6</i>)	A duplicate IPv4 or IPv6 address occurs.
Duplicate IPv6 prefix detected (<i>duplicate-prefix6</i>)	A duplicate IPv6 prefix occurs.
Failover configuration mismatch (<i>failover-config-error</i>)	A DHCP failover configuration does not match between partners.
Free-address thresholds (<i>free-address-low</i> and <i>free-address-high</i> ; or <i>free-address6-low</i> and <i>free-address6-high</i>)	The high trap when the number of free IPv4 or IPv6 addresses exceeds the high threshold; or a low trap when the number of free addresses falls below the low threshold after previously triggering the high trap.
High-availability (HA) DNS configuration mismatch (<i>ha-dns-config-error</i>)	An HA DNS configuration does not match between partners.
HA DNS partner not responding (<i>ha-dns-partner-down</i>)	An HA DNS partner stops responding to the DNS server.
HA DNS partner responding (<i>ha-dns-partner-up</i>)	An HA DNS partner responds after having been unresponsive.
DNS masters not responding (<i>masters-not-responding</i>)	Master DNS servers stop responding to the DNS server.
DNS masters responding (<i>masters-responding</i>)	Master DNS servers respond after having been unresponsive.

Event	Notification
Other server not responding (<i>other-server-down</i>)	A DHCP failover partner, or a DNS or LDAP server, stops responding to the DHCP server.
Other server responding (<i>other-server-up</i>)	DHCP failover partner, or a DNS or LDAP server, responds after having been unresponsive.
DNS secondary zones expire (<i>secondary-zone-expired</i>)	A DNS secondary server can no longer claim authority for zone data when responding to queries during a zone transfer.
Server start (<i>server-start</i>)	The DHCP or DNS server is started or reinitialized.
Server stop (<i>server-stop</i>)	The DHCP or DNS server is stopped.

Handling SNMP Notification Events

When Cisco Prime IP Express generates a notification, it transmits a single copy of the notification as an SNMP Trap PDU to each recipient. All events (and scopes or prefixes) share the list of recipients and other notification configuration data, and the server reads them when you initialize the notification.

You can set SNMP attributes in three ways:

- For the DHCP server, which includes the traps to enable and the default free-address trap configuration if you are not specifically configuring traps for scopes or prefixes (or their templates).
- On the scope or prefix (or its template) level by setting the *free-address-config* attribute.
- For the DNS server, which includes a *traps-enabled* setting.

To use SNMP notifications, you must specify trap recipients that indicate where trap notifications should go. By default, all notifications are enabled, but you must explicitly define the recipients, otherwise no notifications can go out. The IP address you use is often **localhost**.

The DHCP server provides special trap configurations so that it can send notifications, especially about free addresses for DHCPv4 and DHCPv6. You can set the trap configuration name, mode, and percentages for the low threshold and high threshold. The mode determines how scopes aggregate their free-address levels.

DHCP v4 Notification

The DHCP v4 modes and thresholds are (see also [Handling Deactivated Scopes or Prefixes](#), on page 94):

- **scope mode**—Causes each scope to track its own free-address level independently (the default).
- **network mode**—Causes all scopes set with this trap configuration (through the scope or scope template *free-address-config* attribute) to aggregate their free-address levels if the scopes share the same *primary-subnet* .
- **selection-tags mode**—Causes scopes to aggregate their free-address levels if they share a primary subnet and have a matching list of selection tag values.

- **low-threshold**—Free-address percentage at which the DHCP server generates a low-threshold trap and re-enables the high threshold. The free-address level for scopes is the following calculation:

$$\frac{100 * \text{available-nonreserved-leases}}{\text{total-configured-leases}}$$

- **high-threshold**—Free-address percentage at which the DHCP server generates a high-threshold trap and re-enables the low threshold.

DHCP v6 Notification

The DHCP v6 modes and thresholds are (see also [Handling Deactivated Scopes or Prefixes](#), on page 94):

- **prefix mode**—Causes each prefix to track its own free-address level independently.
- **link mode**—Causes all prefixes configured for the link to aggregate their own free-address levels if all prefixes share the same link.
- **v6-selection-tags mode**—Causes prefixes to aggregate their free-address levels if they share a link and have a matching list of selection tag values.
- **low-threshold**—Free-address percentage at which the DHCP server generates a low-threshold trap and re-enables the high threshold. The free-address level for prefixes is the following calculation:

$$\frac{100 * \text{max-leases} - \text{dynamic-leases}}{\text{max-leases}}$$

- **high-threshold**—Free-address percentage at which the DHCP server generates a high-threshold trap and re-enables the low threshold.

Handling Deactivated Scopes or Prefixes

A deactivated scope or prefix never aggregates its counters with other scopes or prefixes. For example, if you configure a prefix with **link** or **v6-selection-tags** trap mode, and then deactivate the prefix, its counters disappear from the total count on the aggregation. Any changes to the leases on the deactivated prefix do not apply to the aggregate totals.

Therefore, to detect clients for deactivated scopes or prefixes, you must set the event mode to **scope** or **prefix**, and not to any of the aggregate modes (**network**, **selection-tags**, **link**, or **v6-selection-tags**).

The use case for setting traps on deactivated prefixes, for example, is network renumbering. In this case, you might want to monitor both the new prefixes (as an aggregate, ensuring that you have enough space for all the clients) and old prefixes to ensure that their leases are freed up. You would probably also want to set the high threshold on an old prefix to 90% or 95%, so that you get a trap fired when most of its addresses are free.

Local Basic or Advanced Web UI

Access the SNMP attributes for the DHCP server by choosing **Manage Servers** from the **Operate** menu, then click **Local DHCP Server** in the left pane. You can view the SNMP attributes under SNMP (in Basic mode) or SNMP Settings (in Advanced mode) in the Edit DHCP Server page.

The four *lease-enabled* values (free-address6-low, free-address6-high, duplicate-address6, duplicate-prefix6) pertain to DHCPv6 only. Along with the traps to enable, you can specify the default free-address trap configuration by name, which affects all scopes and prefixes or links not explicitly configured.

To add a trap configuration, do the following:

-
- Step 1** In Advanced mode, from the **Deploy menu** choose **Traps** under the DHCP submenu to access the DHCP trap configurations. The List/Add Trap Configurations page appears.
 - Step 2** Click the **Add Traps** icon in the left pane to open the Add AddrTrapConfig page.
 - Step 3** Enter the name, mode, and threshold percentages, then click **Add AddrTrapConfig**.
-

To edit a trap configuration, do the following:

-
- Step 1** Click the desired trap name in the Traps pane to open the Edit Trap Configuration page
 - Step 2** Modify the name, mode, or threshold percentages.
 - Step 3** Click the **on** option for the *enabled* attribute to enable the trap configuration.
 - Step 4** Click **Save** for the changes to take effect.
-

Deleting Trap Configuration

To delete a trap configuration, select the trap in the Traps pane and click the **Delete** icon, then confirm or cancel the deletion.

Regional Basic or Advanced Web UI

In the regional web UI, you can add and edit trap configurations as in the local web UI. You can also pull replica trap configurations and push trap configurations to the local cluster on the List/Add Trap Configurations page.

Server Up/Down Traps

Every down trap must be followed by a corresponding up trap. However, this rule is not strictly applicable in the following scenarios:

- 1** If a failover partner or LDAP server or DNS server or HA DNS partner is down for a long time, down traps will be issued periodically. An up trap will be generated only when that server or partner returns to service.
- 2** If the DHCP or DNS server is reloaded or restarted, the prior state of the partner or related servers is not retained and duplicate down or up traps can result.



Note

Other failover partner or LDAP server or DNS server or HA DNS partner up or down traps occur only to communicate with that partner or server, and therefore may not occur when the other partner or server goes down or returns to service.

CLI Commands

To set the trap values for the DHCP server at the local cluster, use **dhcp set traps-enabled=value**. You can also set the *default-free-address-config* attribute to the trap configuration. For example:

```
nrcmd> dhcp set traps-enabled=server-start,server-stop,free-address-low,free-address-high
nrcmd> dhcp set default-free-address-config=v4-trap-config
```



Note

If you do not define a *default-free-address-config* (or *v6-default-free-address-config* for IPv6), Cisco Prime IP Express creates an internal, unlisted trap configuration named **default-aggregation-addr-trap-config**. Because of this, avoid using that name for a trap configuration you create.

To define trap configurations for DHCPv4 and DHCPv6, use **addr-trap name create** followed by the *attribute=value* pairs for the settings. For example:

```
nrcmd> addr-trap v4-trap-conf create mode=scope low-threshold=25% high-threshold=30%
nrcmd> addr-trap v6-trap-conf create mode=prefix low-threshold=20% high-threshold=25%
```

Handling SNMP Queries

You can use SNMP client applications to query the following MIBs:

- CISCO-DNS-SERVER-MIB.my
- CISCO-IETF-DHCP-SERVER-MIB.my
- CISCO-IETF-DHCP-SERVER-EXT-MIB.my
- CISCO-NETREG-DHCPV6-MIB.my (experimental)

When the SNMP server receives a query for an attribute defined in one of these MIBs, it returns a response PDU containing that attribute value. For example, using the NET-SNMP client application (available over the Internet), you can use one of these commands to obtain a count of the DHCPDISCOVER packets for a certain address:

```
C:\net-snmp5.2.2\bin>snmpget -m ALL -v 2c -c public
192.168.241.39:4444.iso.org.dod.internet.private.enterprises.cisco.ciscoExperiment.
ciscoIetfDhcpSrvMIB.ciscoIetfDhcpv4SrvMIBObjects.cDhcpv4Counters.cDhcpv4CountDiscovers
```

```
CISCO-IETF-DHCP-SERVER-MIB::cDhcpv4CountDiscovers.0 = Counter32: 0
C:\net-snmp5.2.2\bin>snmpget -m ALL -v 2c -c public
192.168.241.39:4444
1.3.6.1.4.1.9.10.102.1.3.1
```

```
CISCO-IETF-DHCP-SERVER-MIB::cDhcpv4CountDiscovers.0 = Counter32: 0
```

Both commands return the same results. The first one queries the full MIB attribute name, while the second one queries its OID equivalent (which can be less error prone). As previously described, the OID equivalents of the MIB attributes are located in the relevant files at the following URL:

<ftp://ftp.cisco.com/pub/mibs/oid/>

For example, the CISCO-IETF-DHCP-SERVER-MIB.oid file includes the following OID definition that corresponds to the previous query example:

```
"cDhcpv4CountDiscovers" "1.3.6.1.4.1.9.10.102.1.3.1"
```


Here are some possible SNMP query error conditions:

- The community string sent in the request PDU does not match what you configured.
- The version in the request PDU is not the same as the supported version (SNMPv2).
- If the object being queried does not have an instance in the server, the corresponding variable binding type field is set to SNMP_NOSUCHINSTANCE. With a GetNext, if there is no next attribute, the corresponding variable binding type field is set to SNMP_ENDOFMIBVIEW.
- If no match occurs for the OID, the corresponding variable binding type field is set to SNMP_NOSUCHOBJECT. With a GetNext, it is set to SNMP_ENDOFMIBVIEW.
- If there is a bad value returned by querying the attribute, the error status in the response PDU is set to SNMP_ERR_BAD_VALUE.

Integrating Cisco PrimeIP Express SNMP into System SNMP

You can integrate the Cisco Prime IP Express SNMP server into the SNMP server for the system it runs on. The integration can be done in a way where the system will respond to queries for Cisco Prime IP Express MIB entries. On systems using NET-SNMP (and compatible servers) this is done by adding the following entries to the `/etc/snmp/snmpd.conf` configuration file

```
view systemview included .1.3.6.1.4.1.9.9
view systemview included .1.3.6.1.4.1.9.10
```

```
proxy -v 2c -c public 127.0.0.1:4444 .1.3.6.1.4.1.9.9
proxy -v 2c -c public 127.0.0.1:4444 .1.3.6.1.4.1.9.10
```

The community string **public** and the port number **4444** may have to be replaced if the Cisco Prime IP Express SNMP server has been configured with different values for those settings.

NET-SNMP is commonly available on Linux and other Unix-like systems. On other systems, similar mechanisms may also be available.

Bring Your Own Device Web Server

The BYOD web server at the regional cluster provides the infrastructure for Cisco Prime IP Express BYOD operation. The main purpose of the BYOD Web Server is to authenticate the user against AD and collect the device metadata by registering the user's own device in Cisco Prime IP Express.

Managing BYOD Web Server

You can view logs and startup logs; edit the server attributes.

To view logs and startup logs, in the regional cluster web UI, from the **Operate menu**, choose **Manage Servers** under the **Server** submenu to open the Manage Servers page.

Editing BYOD Web Server Properties

You can edit the BYOD web server properties using the Edit Local BYOD Web Server page.

Regional Basic or Advanced or Expert Web UI

-
- Step 1** To access the BYOD web server properties, choose **Manage Servers** under **Operate** menu to open the Manage Servers page.
- Step 2** Click Local **BYOD Web Server** in the Manage Servers pane on the left. The Edit Local BYOD Web Server page appears. This page displays the BYOD web server attributes.
- **KeyStore Settings:** Redirects the "http call" of the BYOD web server to secure "https" with a combination of key store file and key store password.
 - **LDAP Settings:** Specifies the remote LDAP server used for client registration.
 - **Additional Attributes (Auto- start):** Indicates if the BYOD server should be started automatically after every server agent restart.
- Step 3** Modify the settings as per your requirement.
- Step 4** Click **Save** to save the BYOD web server attribute modifications.
- Step 5** Click **Start Server** or **Restart Server** to apply the modifications to the BYOD web server.
-

Setting Up BYOD Theme and Content

You can create the content and multiple BYOD themes at the regional cluster which can be applied to BYOD web server interface.

Adding and Previewing BYOD Themes

You can create your own themes on the regional cluster using the BYOD Theme page and apply the created theme to the BYOD web server so that the logo, background, font, and other properties of the BYOD interface are displayed as per your customization. The created theme can be previewed prior to publishing it to the BYOD web server.

To add and preview a theme:

Regional Advanced or Expert Web UI

-
- Step 1** From the **Deploy** menu, choose **Theme** under the **BYOD** submenu to open the List/Add Custom Theme page.
- Step 2** Click the **Add Theme** icon in the Theme pane. The **Add Custom Theme** window appears.
- Step 3** Enter the Theme Name in the Add Custom Theme window.
- Step 4** Click **Add Custom Theme** to create a new BYOD Theme.
- Step 5** Update the Edit Custom Theme page with required theme attributes.
- Step 6** Click the **Review Theme** icon in the top right corner of the List/Add Custom Theme page. The Theme Preview window appears displaying the BYOD page with the newly added theme.
- Note** You can navigate between the BYOD pages with **Register** and **Reboot** to view how the theme is applied to the BYOD pages. By default, the **Theme preview** window loads the BYOD Device Registration page.
- Step 7** Click **Reboot** to preview your theme in the Device Activation page.

Note You must close the Theme Preview window after preview to return to the List/Add Custom Theme page in the regional server.

- Step 8** Click **Save** in the List/Add Custom Theme page in the regional server to apply the theme to the BYOD web server or click **Revert** to change the attribute values prior to saving the Custom Theme.
- Note** You can modify and preview the theme any number of times. Only the recently saved theme is applied to the BYOD web server.
-

Adding and Previewing BYOD Content

You can create the BYOD web server contents such as login page message, about, terms of services, contact details, and help message on the BYOD content page of the regional cluster, and preview it prior to publishing it to the BYOD web server. These contents can be published in the BYOD web server interface for the device registration and login pages.

To add and review content:

Regional Advanced or Expert Web UI

-
- Step 1** From the **Deploy** menu, choose **Content** under the **BYOD** submenu to open the Edit BYOD content page.
- Step 2** Upload the file or enter relevant text in the Edit BYOD content page.
- Note** You must upload only .html , .htm or .txt files.
- Step 3** Click **Review** to preview the content in the Edit BYOD content page before saving. A **Content Review** window containing the contents appears.
- Step 4** Click on **About/Terms of Service/Contact/Help** in the content review page to preview the content added in the EDIT BYOD content page of the regional server.
- Step 5** Click **Save** to publish the added BYOD content to the BYOD web server.
-

Polling Process

When the regional cluster polls the local cluster for subnet utilization or lease history, it first requests all available data up to the current time. This time is recorded in the history databases, and subsequent polls request only new data from this time forward. All times are stored relative to each local cluster time, adjusted for that cluster time zone.

If the times on each server are not synchronized, you might observe odd query results. For example, if the regional cluster time lags behind that of a local cluster, the collected history might be in the future relative to the time range queries at the regional cluster. If so, the result of the query would be an empty list. Data merged from the several clusters could also appear out of sequence, because of the different time skews between local clusters. This type of inconsistency would make it difficult to interpret trends. To avoid these issues, using a network time service for all clusters is strongly recommended.

Polling Lease History Data

Lease history data is automatically collected at any regional cluster where these feature is enabled for the DHCP server or failover pair. The default polling interval to update the regional databases is 4 hours. You can poll the servers by clicking the Lease History icon on the List/Add Remote Clusters page. For this manual polling, if the server is in a failover relationship, data is only retrieved for the subnets where the server is the main. If you have address space privileges (you are assigned the regional-addr-admin role with at least the lease-history subrole), you can query the lease history data by choosing Current Utilization or Lease History from **Operate menu** (see the "Running IP Lease Histories" section in *Cisco PrimeIP Express 8.3 DHCP User Guide*).

Related Topics

[Polling Process, on page 99](#)

[Adjusting the Polling Intervals, on page 100](#)

Adjusting the Polling Intervals

You can adjust the automatic polling interval for subnet utilization and lease history, along with other attributes. These attributes are set in three places at the regional cluster, with the following priority:

- 1 **Cluster**—These values override the server-wide settings, unless they are unset, in which case the server values are used. The cluster values are set when adding or editing the cluster. In the CLI, set the attributes listed in the table below, using the **cluster** command.
- 2 **Regional CCM server** (the preset polling interval is 4 hours)—This is set on the Edit CCM Server page, accessible by clicking **Servers**, then the Local CCM Server link. In the CLI, set the attributes listed in the table below using the **ccm** command.



Note

If lease history collection is not explicitly turned on at the local cluster DHCP server (see [Enabling Lease History Collection, on page 101](#)), no data is collected, even though polling is on by default.

Table 14: Lease History Polling Regional Attributes

Attribute Type	Lease History
Polling interval—How often to poll data	<i>poll-lease-hist-interval</i> 0 (no polling) to 1 year, preset to 4 hours for the CCM server
Retry interval—How often to retry after an unsuccessful polling	<i>poll-lease-hist-retry</i> 0 to 4 retries
Offset—Hour of the day to guarantee polling	<i>poll-lease-hist-offset</i> 0 to 24h (0h=midnight)

The polling offset attribute ensures that polling occurs at a specific hour of the day, set as 24-hour time, in relation to the polling interval. For example, if you set the interval to 4h and the offset to 6h (6 A.M.), the polling occurs at 2 A.M., 6 A.M., 10 A.M., 2 P.M., 6 P.M., and 10 P.M. each day.

Enabling Lease History Collection

-
- Step 1** Configure the local cluster DHCP server with scopes and address ranges so that clients have requested leases.
- Step 2** Explicitly enable lease history data collection. The DHCP server attributes to set are:
- **ip-history**—Enable or disable the lease history database for v4-only (DHCPv4), v6-only (DHCPv6), or both.
 - **ip-history-max-age**—Limit on the age of the history records (preset to 4 weeks).
- In the CLI, set the attributes using the **dhcp set ip-history=<value> (v4-only, v6-only, both, or disable)** command.
- Step 3** If in staged dhcp edit mode, reload the local cluster DHCP server.
- Step 4** At the regional cluster, create the cluster that includes this DHCP server.
- Step 5** In the regional web UI, go to the Lease History Settings section of the List/Add Remote Clusters page.
- Step 6** Set the attributes in [Table 14: Lease History Polling Regional Attributes](#) , on page 100.
- Step 7** Click **Save**.
- Step 8** On the List/Add Remote Clusters page, click the **Replica** icon next to the cluster name.
- Step 9** Click the **Lease History** icon for the cluster involved to obtain the initial set of lease history data. This data is refreshed automatically at each polling interval.
-

Managing DHCP Scope Templates

Scope templates apply certain common attributes to multiple scopes. These common attributes include a scope name based on an expression, policies, address ranges, and an embedded policy options based on an expression. The scope templates you add or pull from the local clusters are visible on the List/Add DHCP Scope Templates page (choose **Scope Templates** from the **Design > DHCPv4** menu).

For details on creating and editing scope templates, and applying them to scopes, see the *"Creating and Applying Scope Templates"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*. The regional cluster web UI has the added feature of pushing scope templates to local clusters and pulling them from local clusters.

Related Topics

[Pushing Scope Templates to Local Clusters](#), on page 101

[Pulling Scope Templates from Replica Data](#), on page 102

Pushing Scope Templates to Local Clusters

You can push the scope templates you create from the regional cluster to any of the local clusters. In the web UI, go to the List/Add DHCP Scope Templates page, and do any of the following:

- if you want to push a specific template to a cluster, select the scope template from the Scope Templates pane on the left, and click **Push** (at the top of the page). This opens the Push DHCP Scope Template page.

- If you want to push all of the available scope templates, click the **Push All** icon at the top of the Scope Templates pane. This opens the Push Data to Local Clusters page.

Regional Web UI

The Push DHCP Scope Template page and Push Data to Local Clusters page identify the data to push, how to synchronize it with the local cluster, and the cluster or clusters to which to push it. The data synchronization modes are:

- **Ensure** (preset value)—Ensures that the local cluster has new data without affecting any existing data.
- **Replace**—Replaces data without affecting other objects unique to the local cluster.
- **Exact**—Available for “push all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the local cluster.

Choose the destination cluster or clusters in the Available field and move it or them to the Selected field.



Tip

The synchronization mode and cluster choice settings are persistent for the duration of the current login session, so that they are in effect each time you access this page, unless you change them.

After making these choices, click **Push Data to Clusters**. This opens the View Push Scope Template Data Report page.

Pulling Scope Templates from Replica Data

You may choose to pull scope templates from the replica data of the local clusters instead of explicitly creating them. (You may first want to update the policy replica data by clicking the **Replicate** icon next to the cluster name.) To pull the scope templates in the regional web UI, click the **Pull Replica** icon at the top of the Scope Templates pane.

Regional Web UI

The Select Replica DHCP Scope Template Data to Pull page shows a tree view of the regional server replica data for the local clusters' scope templates. The tree has two levels, one for the local clusters and one for the scope templates in each cluster. You can pull individual scope templates from the clusters, or you can pull all of their scope templates. To pull individual scope templates, expand the tree for the cluster, then click **Pull Scope Template** next to its name. To pull all the scope templates from a cluster, click **Pull All Scope Templates**.

To pull the scope templates, you must also choose a synchronization mode:

- **Ensure**—Ensures that the regional cluster has new data without affecting any existing data.
- **Replace** (preset value)—Replaces data without affecting other objects unique to the regional cluster.
- **Exact**—Available for “pull all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the regional cluster.

Managing DHCP Policies

Every DHCP server must have one or more policies defined for it. Policies define lease duration, gateway routers, and other configuration parameters, in what are called DHCP options. Policies are especially useful if you have multiple scopes, because you need only define a policy once and apply it to the multiple scopes.

For details on creating and editing DHCP policies, and applying them to scopes, see the *"Configuring DHCP Policies" section in Cisco PrimeIP Express 8.3 DHCP User Guide*. The regional cluster web UI has the added feature of pushing policies to, and pulling them from, the local clusters.

Related Topics

[Pushing Policies to Local Clusters, on page 103](#)

[Pulling Policies from Replica Data, on page 103](#)

Pushing Policies to Local Clusters

You can also push the policies you create from the regional cluster to any of the local clusters. In the regional web UI, go to List/Add DHCP Policies page, and do any of the following:

- If you want to push a specific policy to a cluster, select the policy from the Policies pane on the left, and click **Push** (at the top of the page).
- If you want to push all the policies, click the **Push All** icon at the top of the Policies pane.

Regional Web UI

The Push DHCP Policy Data to Local Clusters page identifies the data to push, how to synchronize it with the local cluster, and the cluster or clusters to which to push it. The data synchronization modes are:

- **Ensure** (preset value)—Ensures that the local cluster has new data without affecting any existing data.
- **Replace**—Replaces data without affecting other objects unique to the local cluster.
- **Exact**—Available for push-all operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the local cluster.

Choose the destination cluster or clusters in the Available field and move it or them to the Selected field. Then click **Push Data to Clusters** to open the View Push Policy Data Report page.



Tip

The synchronization mode and cluster choice settings are persistent for the duration of the current login session, so that they are in effect each time you access this page, unless you change them.

Pulling Policies from Replica Data

You may choose to pull policies from the replica data of the local clusters instead of explicitly creating them. (In the regional web UI, you may first want to update the policy replica data by clicking the **Replicate** icon next to the cluster name). To pull the policies, click the **Pull Replica** icon at the top of the Policies pane.

Regional Web UI

The Select Replica DHCP Policy Data to Pull page shows a tree view of the regional server replica data for the local clusters' policies. The tree has two levels, one for the local clusters and one for the policies in each cluster. You can pull individual policies from the clusters, or you can pull all of their policies. To pull individual policies, expand the tree for the cluster, then click **Pull Policy** next to its name. To pull all the policies from a cluster, click **Pull All Policies**.

To pull all the policies, you must also choose a synchronization mode:

- **Ensure**—Ensures that the regional cluster has new data without affecting any existing data.
- **Replace** (preset value)—Replaces data without affecting other objects unique to the regional cluster.
- **Exact**—Available for “pull all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the regional cluster.

Managing DHCP Client-Classes

Client-classes provide differentiated services to users that are connected to a common network. You can group your user community based on administrative criteria, and then ensure that each user receives the appropriate class of service. Although you can use the Cisco Prime IP Express client-class facility to control any configuration parameter, the most common uses are for:

- **Address leases**—How long a set of clients should keep its addresses.
- **IP address ranges**—From which lease pool to assign clients addresses.
- **DNS server addresses**—Where clients should direct their DNS queries.
- **DNS hostnames**—What name to assign clients.
- **Denial of service**—Whether unauthorized clients should be offered leases.

For details on creating and editing client-classes, see the *"Managing Client-Classes and Clients" chapter in Cisco PrimeIP Express 8.3 DHCP User Guide*. The regional cluster web UI has the added feature of pushing client-classes to, and pulling them from, the local clusters.

Related Topics

[Pushing Client-Classes to Local Clusters, on page 104](#)

[Pushing Client-Classes to Local Clusters, on page 104](#)

Pushing Client-Classes to Local Clusters

You can also push the client-classes you create from the regional cluster to any of the local clusters. In the Regional web UI, go to the List/Add DHCP Client Classes page, and do any of the following:

- If you want to push a specific client-class to a cluster in the web UI, select the client-class from the Client Classes pane on the left, and click **Push** (at the top of the page). This opens the Push DHCP Client Class page.

- If you want to push all the client-classes, click the **Push All** icon at the top of the Client Classes pane. This opens the Push Data to Local Clusters page.

Regional Web UI

The Push DHCP Client Class page and Push Data to Local Clusters page identifies the data to push, how to synchronize it with the local cluster, and the cluster or clusters to which to push it. The data synchronization modes are:

- **Ensure** (preset value)—Ensures that the local cluster has new data without affecting any existing data.
- **Replace**—Replaces data without affecting other objects unique to the local cluster.
- **Exact**—Available for “push all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the local cluster.

Choose the destination cluster or clusters in the Available field and move it or them to the Selected field. Then click **Push Data to Clusters** to open the View Push Client-Class Data Report page.



Tip

The synchronization mode and cluster choice settings are persistent for the duration of the current login session, so that they are in effect each time you access this page, unless you change them.

Pulling Client-Classes from Replica Data

You may choose to pull client-classes from the replica data of the local clusters instead of explicitly creating them. (In the web UI, you might first want to update the client-class replica data by clicking the **Replicate** icon next to the cluster name.) To pull the client-classes, click the **Pull Replica** icon at the top of the Client Classes pane.

Regional Web UI

The Select Replica DHCP Client-Class Data to Pull page shows a tree view of the regional server replica data for the local clusters' client-classes. The tree has two levels, one for the local clusters and one for the client-classes in each cluster. You can pull individual client-classes from the clusters, or you can pull all of their client-classes. To pull individual client-classes, expand the tree for the cluster, then click **Pull Client-Class** next to its name. To pull all the client-classes from a cluster, click **Pull All Client-Classes**.

To pull the client-classes, you must also choose a synchronization mode:

- **Ensure**—Ensures that the regional cluster has new data without affecting any existing data.
- **Replace** (preset value)—Replaces data without affecting other objects unique to the regional cluster.
- **Exact**—Available for “pull all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the regional cluster.

Managing Virtual Private Networks

A virtual private network (VPN) is a specialized address space identified by a key. A VPN allows address overlap in a network, because the addresses are distinguished by separate keys. Most IP addresses exist in the

global address space outside of a VPN. You can create regional VPNs only if you are an administrator assigned the dhcp-management subrole of the central-cfg-admin role.

For details on creating and editing VPNs, and applying them to various network objects, see the *"Configuring Virtual Private Networks Using DHCP"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*. The regional web UI has the added feature of pushing VPNs to local clusters and pulling them from local clusters.

Related Topics

[Pushing VPNs to Local Clusters, on page 106](#)

[Pulling VPNs from Replica Data, on page 106](#)

Pushing VPNs to Local Clusters

You can push the VPNs you create from the regional cluster to any of the local clusters. In the Regional web UI, go to the List/Add VPNs page, and do any of the following:

- If you want to push a specific VPN to a cluster in the web UI, select the VPN from the VPNs pane on the left, and click **Push** (at the top of the page). This opens the Push VPN page.
- If you want to push all the VPNs, click the **Push All** icon at the top of the VPNs pane. This opens the Push Data to Local Clusters page.

Regional Web UI

The Push VPN page and Push Data to Local Clusters page identify the data to push, how to synchronize it with the local cluster, and the cluster or clusters to which to push it. The data synchronization modes are:

- **Ensure** (preset value)—Ensures that the local cluster has new data without affecting any existing data.
- **Replace**—Replaces data without affecting other objects unique to the local cluster.
- **Exact**—Available for “push all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the local cluster.

Choose the destination cluster or clusters in the Available field and move it or them to the Selected field. Then click **Push Data to Clusters** to open the View Push VPN Data Report page.



Tip

The synchronization mode and cluster choice settings are persistent for the duration of the current login session, so that they are in effect each time you access this page, unless you change them.

Pulling VPNs from Replica Data

Instead of explicitly creating VPNs, you can pull them from the local clusters. (In the regional web UI, you may first want to update the VPN replica data by clicking the **Replica** icon next to the cluster name.) To pull the replica data, click the **Pull Replica** icon at the top of the VPNs pane on the left, to open the Select Replica VPN Data to Pull page.

This page shows a tree view of the regional server replica data for the local clusters' VPNs. The tree has two levels, one for the local clusters and one for the VPNs in each cluster. You can pull individual VPNs or you

can pull all of them. To pull individual VPNs, expand the tree for the cluster, then click **Pull VPN** next to its name. To pull all the VPNs, click **Pull All VPNs**.

To pull the VPNs, you must choose a synchronization mode:

- **Ensure**—Ensures that the regional cluster has new data without affecting any existing data.
- **Replace** (preset value)—Replaces data without affecting other objects unique to the regional cluster.
- **Exact**—Available for “pull all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the regional cluster.

Managing DHCP Failover Pairs

With DHCP failover, a backup DHCP server can take over for a main server if the latter comes off the network for any reason. You can use failover to configure two servers to operate as a redundant pair. If one server is down, the other server seamlessly takes over so that new DHCP clients can get, and existing clients can renew, their addresses. Clients requesting new leases need not know or care about which server responds to their lease request. These clients can obtain leases even if the main server is down.

In the regional web UI, you can view any created failover pairs on the List/Add DHCP Failover Pairs page. To access this page, click **DHCP**, then **Failover**. This functionality is available only to administrators who are assigned the dhcp-management subrole of the central-cfg-admin role.

For details on creating and editing failover pairs, see the *"Setting Up Failover Server Pairs" section in Cisco PrimeIP Express 8.3 DHCP User Guide*. The regional cluster web UI has the added feature of pulling addresses from local clusters to create the failover pairs.

To pull the address space for a failover pair, you must have regional-addr-admin privileges.

Regional Web UI

-
- | | |
|---------------|---|
| Step 1 | On the List/Add DHCP Failover Pairs page or View Unified Address Space page, click the Pull Replica icon in the Failover Pairs pane. |
| Step 2 | Choose the data synchronization mode (Update , Complete , or Exact) on the Select Pull Replica Address Space page. The results of choosing these modes are described in the table on the page. |
| Step 3 | Click the Report button in the Synchronize Failover Pair tab and click Return . |
| Step 4 | Click Run on the Report Pull Replica Address Space page. |
| Step 5 | Click OK on the Run Pull Replica Address Space page. |
-

Managing Lease Reservations

You can push lease reservations you create from the regional cluster to any of the local clusters. In the regional cluster web UI, go to the List/Add DHCPv4 Reservations page or List/Add DHCPv6 Reservations page, and click the **Push All** icon in the Reservations pane on the left. Note that you cannot push individual reservations. If the cluster pushed to is part of a DHCP failover configuration, pushing a reservation also pushes it to the partner server.

Related Topics

[DHCPv4 Reservations, on page 108](#)

[DHCPv6 Reservations, on page 108](#)

DHCPv4 Reservations

To create DHCPv4 reservations, the parent subnet object must exist on the regional server. If there are pending reservation edits at regional, these can be pushed to the subnet local cluster or failover pair. If the subnet has never been pushed, the parent scope is added to the local cluster or pair.

Once a subnet is pushed to a local cluster or pair, reservations are pushed to that cluster or pair. To move the scopes and subnet to another local cluster or failover pair, the subnet must first be reclaimed.

DHCPv6 Reservations

To create DHCPv6 reservations, the parent prefix must exist on the regional server. When there are pending reservation or prefix changes, you can push the updates to the local cluster.

Once a prefix is pushed to a local cluster, it can only update that local cluster. To move the prefix to another local cluster, it must first be reclaimed.

Regional Web UI

The ensuing page identifies the data to push, how to synchronize it with the local cluster, and the cluster or clusters to which to push it. The data synchronization modes are:

- **Ensure**—Ensures that the local cluster has new data without affecting any existing data.
- **Replace** (preset value)—Replaces data without affecting other objects unique to the local cluster.
- **Exact**—Available for “push all” operations only. Use this with caution, because it overwrites the data and deletes any other objects unique to the local cluster.

Choose the destination cluster or clusters in the Available field and move it or them to the Selected field.



Tip

The synchronization mode and cluster choice settings are persistent for the duration of the current login session, so that they are in effect each time you access this page, unless you change them.

After making these choices, click **Push Data to Clusters**. This opens the View Push Reservations Data Report page. Click **OK** on this page.

You can also pull the replica address space on the List/Add DHCP v6 Reservations page, and opt whether to omit reservations when doing so. You should use this option only to reduce processing time when you are sure that there are no pending changes to reservations to merge. To omit reservations for the pull, check the *Omit Reservations?* check box, then click **Pull Data**.

See the *"Managing DHCPv6 Addresses"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*.

Monitoring Resource Limit Alarms

Resource limit alarms enable you to monitor Cisco Prime IP Express system resources and provide an indication when one or more product resources has entered potentially dangerous level and requires attention. Resource limit alarms are designed to convey the resource limit information in an organized and consolidated way.


Note

The log messages related to resource limits are logged to the `ccm_monitor_log` files. For more information on log files, see [Log Files](#), on page 133.

You can reset the predefined threshold levels for both critical and warning levels for each monitored resource.

Cisco Prime IP Express reports the current status, the current value, and the peak value of the monitored resources in the web UI and CLI. The peak value is compared to the configured warning or critical limit for the resource limit alarm and the status of the resource limit alarm is displayed as OK, Warning, or Critical. Cisco Prime IP Express displays the alarms on the web UI and CLI until the resulting condition no longer occurs and the peak value is reset.

The resource limit alarms are updated at regular intervals based on the polling interval you configure. For more information on setting up the polling interval, see [Setting Resource Limit Alarms Polling Interval](#), on page 111.

If SNMP traps are enabled for the resource limit alarms, Cisco Prime IP Express generates SNMP traps when the monitored resources exceed the critical or warning levels. SNMP traps are generated whenever the current value exceeds the configured warning or critical level.

The resource limit alarms can be configured both at the regional and in the local cluster. The resource limit alarms data is consolidated at the individual local cluster level. The resource limits alarms available on the regional cluster level pertain to only the regional cluster. The table below lists the types of resource limit alarms that are available on the regional or the local cluster.

Table 15: Resource Limit Alarms

	Regional Cluster	Local Cluster
Data Free Space in../Data Partition	✓	✓
Shadow Backup Time	✓	✓
CCM Memory	✓	✓
CNR Server Agent Memory	✓	✓
Tomcat Memory	✓	✓
DHCP Memory	x	✓
CDNS Memory	x	✓
DNS Memory	x	✓
SNMP Memory	✓	✓

Lease Count	x	✓
Zone Count	x	✓
Resource Records Count	x	✓

Configuring Resource Limit Alarm Thresholds

You can configure the warning and critical limits for the resource limit alarms using the **Edit CCM Server** page.

Local and Regional Web UI

-
- Step 1** To access the CCM server properties, choose **Manage Servers** under the **Operate** menu to open the Manage Servers page.
- Step 2** Click **Local CCM Server** in the Manage Servers pane on the left. The Edit Local CCM Server page appears. This page displays all the CCM server attributes.
- Step 3** Click the **Configure Resource Limits** tab.
- Step 4** Modify the settings as per your requirement.
Note To enable the SNMP traps for the resource limit alarms, select the Enable Traps option in the Trap Configuration group.
- Step 5** Click **Save** to save the CCM server attribute modifications.
-

CLI Commands

To set the resource limit alarms on the local or regional cluster, use **resource set attribute=value**. Use **resource show** to review the current setting and use **resource report <all | full | level>** command to report on the resources.

To view the defined warning and critical levels, use **resource report levels** command.

A 109 status message is reported (if at least one resource is in the critical or warning state) under the following scenarios.

- Execute 'resource report' command.
- Connect to a cluster via CLI.
- Exit from CLI.

Setting Resource Limit Alarms Polling Interval

You can set how often Cisco Prime IP Express polls for alarm data from the server and updates the web UI data. The *stats-history-sample-interval* controls the CCM server system polling rate.

-
- Step 1** To edit the alarm poll interval, you need to edit the user preferences by going to **User Preferences** under the **admin** menu (at the top of the main page).
- Step 2** After making the user preference settings, click **Modify User Preferences**.
-

Viewing Resource Limit Alarms

Resource limit alarms are displayed on the Alarms toolbar. To see a summary of the alarms, in the Cisco Prime IP Express web UI, click the **Alarms** toolbar on the bottom of the web UI. This opens the Alarms toolbar overlay which displays the status, resource values (current, configured warning, and critical value), and the peak value for each resource limit alarm. Based on the peak value for each resource limit, the status of resource limit is displayed as OK, Warning, or Critical on the web UI and CLI. The alarms are updated at regular intervals based on the polling interval you configure. For more information on setting up the polling interval, see [Setting Resource Limit Alarms Polling Interval](#), on page 111.



Note

When a resource is in a warning or critical state, the resource limit alarm is also displayed on the Configuration Summary page.

Resetting Resource Limit Alarms Peak Value

Cisco Prime IP Express maintains the peak values for each resource limit. The peak value is updated only when the current value exceeds the peak value. The peak value is compared to the configured warning or critical limit for the resource limit alarm and the status of the resource limit alarm is displayed as OK, Warning, or Critical.

When the peak value exceeds the configured warning or critical limit the status of the resource limit alarm is shown as Warning or Critical (on the web UI and CLI) respectively until the peak value is explicitly reset. To reset the peak value, perform the following steps:

-
- Step 1** On the **Alarms** toolbar, select the Alarm for which you want to reset the peak value.
- Step 2** Click **Reset Alarm** to clear the peak value.
-

CLI Commands

To reset the peak value on the local or regional cluster, use **resource reset name**.

**Note**

If no resource name is provided, all are reset.

Export Resource Limit Alarms Data

You can export the resource limit alarms data to a CSV file. To export the resource limit alarms:

-
- Step 1** Click **Alarms** in the alarms toolbar at the bottom of the web UI.
 - Step 2** Click **Export to CSV**.
 - Step 3** The File Download pop-up window displays. Click **Save**.
 - Step 4** In the Save As pop-up window, choose the location you want to save the file to and click **Save**.
-

Local Cluster Management Tutorial

This tutorial describes a basic scenario on a local cluster of the Example Company. Administrators at the cluster are responsible for users, zone data, DHCP data, address space data, and the servers in general. The task is to set up two zones (example.com and boston.example.com), hosts in the zones, and a subnet. The local cluster must also create a special administrator account so that the regional cluster in San Jose can perform the central configuration and replicate the local cluster administrators and address space at another cluster, as described in [Regional Cluster Management Tutorial](#), on page 119.

Related Topics

- [Administrator Responsibilities and Tasks](#), on page 112
- [Create the Administrators](#), on page 113
- [Create the Address Infrastructure](#), on page 114
- [Create the Zone Infrastructure](#), on page 114
- [Create a Host Administrator Role with Constraints](#), on page 116
- [Create a Group to Assign to the Host Administrator](#), on page 118
- [Test the Host Address Range](#), on page 119

Administrator Responsibilities and Tasks

The local cluster administrators have the following responsibilities and tasks:

- **example-cluster-admin**—Created by the superuser:
 - At the Boston cluster, creates the other local administrators (example-zone-admin and example-host-admin).
 - Creates the basic network infrastructure for the local clusters.
 - Constrains the example-host-role to an address range in the boston.example.com zone.

- Creates the example-host-group (defined with the example-host-role) that the example-zone-admin will assign to the example-host-admin.
- **example-zone-admin:**
 - Creates the example.com and boston.example.com zones, and maintains the latter zone.
 - Assigns the example-host-group to the example-host-admin.
- **example-host-admin**—Maintains local host lists and IP address assignments.

Create the Administrators

For this example, the superuser in Boston creates the local cluster, zone, and host administrators, as described in the [Administrator Responsibilities and Tasks](#), on page 112.

Local Basic Web UI

-
- Step 1** At the Boston local cluster, log in as superuser (usually **admin**).
- Step 2** In Basic mode, from the **Administration** menu, choose **Administrators**.
- Step 3** Add the local cluster administrator (with superuser access)—On the List/Add Administrators page:
- a) Click the **Add Administrators** icon in the Administrators pane, enter **example-cluster-admin** in the Name field.
 - b) Enter **exampleadmin** in the Password field, then click **Add Admin**.
 - c) Check the Superuser check box.
 - d) Do not choose a group from the Groups list.
 - e) Click **Save**.
- Step 4** Add the local zone administrator on the same page:
- a) Click the **Add Administrators** icon in the Administrators pane, enter **example-zone-admin** in the Name field, and **examplezone** in the Password field, then click **Add Admin**.
 - b) Multiselect **ccm-admin-group**, **dns-admin-group**, and **host-admin-group** in the Groups drop-down list. The dns-admin-group is already predefined with the dns-admin role to administer DNS zones and servers. The ccm-admin-group guarantees that the example-zone-admin can set up the example-host-admin with a constrained role later on. The host-admin-group is mainly to test host creation in the zone.
 - c) Click **Save**.
- Step 5** Add the local host administrator on the same page:
- a) Click the **Add Administrators** icon in the Administrators pane, enter **example-host-admin** in the Name field, and **examplehost** in the Password field, then click **Add Admin**.
 - b) Do not choose a group at this point. (The example-zone-admin will later assign example-host-admin to a group with a constrained role.)
 - c) Click **Save**.
- Note** For a description on how to apply constraints to the administrator, see the [Create a Host Administrator Role with Constraints](#), on page 116.
-

Create the Address Infrastructure

A prerequisite to managing the zones and hosts at the clusters is to create the underlying network infrastructure. The network configuration often already exists and was imported. However, this tutorial assumes that you are starting with a clean slate.

The local example-cluster-admin next creates the allowable address ranges for the hosts in the boston.example.com zone that will be assigned static IP addresses. These addresses are in the 192.168.50.0/24 subnet with a range of hosts from 100 through 200.

Local Advanced Web UI

-
- Step 1** At the local cluster, log out as superuser, then log in as the **example-cluster-admin** user with password **exampleadmin**. Because the administrator is a superuser, all features are available.
- Step 2** Click **Advanced** to go to Advanced mode.
- Step 3** Click **Design**, then **Subnets** under DHCPv4 submenu.
- Step 4** On the List/Add Subnets page, enter the boston.example.com subnet address:
- a) Click the **Add Subnets** icon in the Subnets pane, enter **192.168.50** in the Address field.
 - b) Choose **24** in the mask drop-down list—This subnet will be a normal Class C network.
 - c) Leave the Owner, Region, and Address Type fields as is. Add description if desired.
 - d) Click **Add Subnet**.
- Step 5** Click the 192.168.50.0/24 address to open the Edit Subnet page.
- Step 6** In the IP Ranges fields, enter the static address range:
- a) Enter **100** in the Start field. Tab to the next field.
 - b) Enter **200** in the End field.
 - c) Click **Add IP Range**. The address range appears under the fields.
- Step 7** Click **Save**.
- Step 8** Click **Address Space** to open the View Unified Address Space page. The 192.168.50.0/24 subnet should appear in the list. If not, click the **Refresh** icon.
-

Create the Zone Infrastructure

For this scenario, example-cluster-admin must create the Example Company zones locally, including the example.com zone and its subzones. The example-cluster-admin also adds some initial host records to the boston.example.com zone.

Related Topics

[Create the Forward Zones, on page 115](#)

[Create the Reverse Zones, on page 115](#)

[Create the Initial Hosts, on page 116](#)

Create the Forward Zones

First, create the example.com and boston.example.com forward zones.

Local Basic Web UI

-
- Step 1** At the local cluster, log in as the **example-zone-admin** user with password **examplezone**.
- Step 2** From the **Design** menu, choose **Forward Zones** under the **Auth DNS** submenu. This opens the List/Add Forward Zones page.
- Step 3** Create the example.com zone (tab from field to field):
- Click the **Add Forward Zone** icon in the Forward Zones pane, enter **example.com** in the Name field.
 - In the Nameserver FQDN field, enter **ns1**.
 - In the Contact E-Mail field, enter **hostmaster**.
 - In the Serial Number field, enter the serial number.
 - Click **Add Zone**.
- Step 4** Create the **boston.example.com** zone in the same way, using the same values as in the previous steps:
- Creating a zone with a prefix added to an existing zone opens the Create Subzone in Parent Zone page, because the zone can be a potential subzone. Because you do want to create this zone as a subzone to example.com, click **Create as Subzone** on the Create Subzone in Parent Zone page.
 - Because nameservers are different in each zone, you must create a glue Address (A) record to tie the zones together. Enter 192.168.50.1 in the A record field, then click **Specify Glue Records**. Then click **Report, Run, and Return**.
 - The List/Add Zones page should now list example.com and boston.example.com.
- Step 5** Click **Advanced**, then **Show Forward Zone Tree** to show the hierarchy of the zones. Return to list mode by clicking **Show Forward Zone List**.
-

Create the Reverse Zones

Next, create the reverse zones for example.com and boston.example.com. This way you can add reverse address pointer (PTR) records for each added host. The reverse zone for example.com is based on the 192.168.50.0 subnet; the reverse zone for boston.example.com is based on the 192.168.60.0 subnet.

Local Basic Web UI

-
- Step 1** At the local cluster, you should be logged in as the example-zone-admin user, as in the previous section.
- Step 2** From the **Design** menu, choose **Reverse Zones** under the **Auth DNS** submenu.
- Step 3** On the List/Add Reverse Zones page, click the **Add Reverse Zone** icon in the Reverse Zones pane, enter **50.168.192.in-addr.arpa** in the Name field. (There is already a reverse zone for the loopback address, 127.in-addr.arpa.)
- Step 4** Enter the required fields to create the reverse zone, using the forward zone values:
- Nameserver**—Enter **ns1.example.com**. (be sure to include the trailing dot).
 - Contact E-Mail**—Enter **hostmaster.example.com**. (be sure to include the trailing dot).

c) **Serial Number**—Enter the serial number.

Step 5 Click **Add Reverse Zone** to add the zone and return to the List/Add Reverse Zones page.

Step 6 Do the same for the boston.example.com zone, using **60.168.192.in-addr.arpa** as the zone name and the same nameserver and contact e-mail values as in **Step 4**. (You can cut and paste the values from the table.)

Create the Initial Hosts

As a confirmation that hosts can be created at the Boston cluster, the example-zone-admin tries to create two hosts in the example.com zone.

Local Advanced Web UI

Step 1 As the example-zone-admin user, click **Advanced** to enter Advanced mode.

Step 2 From the **Design** menu, choose **Hosts** under the **Auth DNS** submenu. This opens the List/Add Hosts for Zone page. You should see boston.example.com and example.com in the Select Zones box on the left side of the window.

Step 3 Click example.com in the list of zones.

Step 4 Add the first static host with address 192.168.50.101:

- a) Enter **userhost101** in the Name field.
- b) Enter the complete address **192.168.50.101** in the IP Address(es) field. Leave the IPv6 Address(es) and Alias(es) field blank.
- c) Ensure that the Create PTR Records? check box is checked.
- d) Click **Add Host**.

Step 5 Add the second host, **userhost102**, with address **192.168.50.102**, in the same way. The two hosts should now appear along with the nameserver host on the List/Add Hosts for Zone page.

Create a Host Administrator Role with Constraints

In this part of the tutorial, the Boston example-cluster-admin creates the example-host-role with address constraints in the boston.example.com zone.

Local Advanced Web UI

Step 1 Log out as the example-zone-admin user and log in as the **example-cluster-admin** user (with password **exampleadmin**).

Step 2 Click **Advanced** to enter Advanced mode.

Step 3 From the **Administration** menu, choose **Roles** under User Access submenu to open the List/Add Administrator Roles page.

Step 4 Add the example-host-role:

- a) Click the **Add Role** icon in the Roles pan to open the Add Roles dialog box.
- b) Enter **example-host-role** in the Name field.
- c) Click **Add Role**. The example-host-role should now appear in the list of roles on the List/Add Administrator Roles page.

Step 5

Add the constraint for the role:

- a) Click **Add Constraint**.
- b) On the Add Role Constraint for Role page, scroll down to Host Restrictions.
- c) For the *all-forward-zones* attribute, click the **false** radio button.
- d) For the *zones* attribute, enter **boston.example.com**.
- e) For the *ipranges* attribute, enter the range **192.168.50.101–192.168.50.200**
- f) The *zone-regexp* and *host-regexp* attribute fields are for entering regular expressions to match zones and hosts, respectively, in regex syntax. (See the following table for the commonly used regex values.)

Table 16: Common Regex Values

Value	Matches
. (dot)	Any character (a wildcard). Note that to match a literal dot character (such as in a domain name), you must escape it by using a backslash (\), such that \.com matches .com .
\char	Literal character (<i>char</i>) that follows, or the <i>char</i> has special meaning. Used especially to escape metacharacters such as the dot (.) or another backslash. Special meanings include \d to match decimal digits, \D for nondigits, \w for alphanumerics, and \s for whitespace.
char?	Preceding <i>char</i> once or not at all, as if the character were optional. For example, example\?.com matches example.com or examplecom .
char*	Preceding <i>char</i> zero or more times. For example, ca*t matches ct , cat , and caaat . This repetition metacharacter does iterative processing with character sets (see [charset]).
char+	Preceding <i>char</i> one or more times. For example, ca+t matches cat and caaat (but not ct).

Value	Matches
[<i>charset</i>]	Any of the characters enclosed in the brackets (a character set). You can include character ranges such as [a–z] (which matches any lowercase character). With the * repetition metacharacter applied, the search engine iterates through the set as many times as necessary to effect a match. For example, a[bcd]*b will find abcbcd (by iterating through the set a second time). Note that many of the metacharacters (such as the dot) are inactive and considered literal inside a character set.
[^ <i>charset</i>]	Anything but the <i>charset</i> , such that [^a-zA-Z0-9] matches any nonalphanumeric character (which is equivalent to using \W). Note that the caret outside a character set has a different meaning.
^	Beginning of a line.
\$	End of a line.

g) Click **Add Constraint**. The constraint should have an index number of 1.

Step 6 Click **Save**.

Create a Group to Assign to the Host Administrator

The Boston example-cluster-admin next creates an example-host-group that includes the example-host-role so that the example-zone-admin can assign this group to the example-host-admin.

Local Advanced Web UI

-
- Step 1** As example-cluster-admin, still in Advanced mode, from the **Administration** menu, choose **Groups** submenu to open the List/Add Administrator Groups page.
- Step 2** Create the example-host-group and assign the example-host-role to it:
- Click the **Add Groups** icon in the Groups pane, enter **example-host-group** in the Name field.
 - From the Base Role drop-down list, choose **example-host-role**.
 - Click **Add Group**.
 - Add a description such as **Group for the example-host-role**, then click **Save**.
- Step 3** Log out as example-cluster-admin, then log in as the **example-zone-admin** user (with password **examplezone**).
- Step 4** As example-zone-admin, assign the example-host-group to the example-host-admin:
- In Basic mode, from the **Administration** menu, choose **Administrators**.

- b) On the List/Add Administrators page, click `example-host-admin` to edit the administrator.
 - c) On the Edit Administrator page, choose **example-host-group** in the Available list, then click << to move it to the Selected list.
 - d) Click **Save**. The `example-host-admin` should now show the `example-host-group` in the Groups column on the List/Add Administrators page.
-

Test the Host Address Range

The `example-host-admin` next tests an out-of-range address and then adds an acceptable one.

Local Advanced Web UI

-
- Step 1** At the local cluster, log out as `example-zone-admin`, then log in as **example-host-admin** (with password **examplehost**).
 - Step 2** Click **Advanced** to enter Advanced mode.
 - Step 3** From the **Design** menu, choose **Hosts** from the **Auth DNS** submenu.
 - Step 4** On the List/Add Hosts for Zone page, try to enter an out-of-range address (note the range of valid addresses in the Valid IP Ranges field):
 - a) Enter **userhost3** in the Name field.
 - b) Deliberately enter an out-of-range address (**192.168.50.3**) in the IP Address(es) field.
 - c) Click **Add Host**. You should get an error message.
 - Step 5** Enter a valid address:
 - a) Enter **userhost103**.
 - b) Enter **192.168.50.103** in the IP Address(es) field.
 - c) Click **Add Host**. The host should now appear with that address in the list.
-

Regional Cluster Management Tutorial

This tutorial is an extension of the scenario described in the [Local Cluster Management Tutorial](#), on page 112. In the regional cluster tutorial, San Jose has two administrators—a regional cluster administrator and a central configuration administrator. Their goal is to coordinate activities with the local clusters in Boston and Chicago so as to create DNS zone distributions, router configurations, and DHCP failover configurations using the servers at these clusters. The configuration consists of:

- One regional cluster machine in San Jose.
- Two local cluster machines, one in Boston and one in Chicago.
- One Cisco uBR7200 router in Chicago.

Related Topics

- [Administrator Responsibilities and Tasks, on page 120](#)
- [Create the Regional Cluster Administrator, on page 120](#)
- [Create the Central Configuration Administrator, on page 121](#)
- [Create the Local Clusters, on page 121](#)
- [Add Zone Management to the Configuration Administrator, on page 122](#)
- [Create a Zone for the Local Cluster, on page 123](#)
- [Pull Zone Data and Create a Zone Distribution, on page 123](#)
- [Create a Subnet and Pull Address Space, on page 124](#)
- [Push a DHCP Policy, on page 125](#)
- [Create a Scope Template, on page 125](#)
- [Create and Synchronize the Failover Pair, on page 126](#)

Administrator Responsibilities and Tasks

The regional administrators have the following responsibilities and tasks:

- **example-regional-admin**—Created by the superuser at the San Jose regional cluster, who creates the example-cfg-admin.
- **example-cfg-admin:**
 - Defines the Boston and Chicago clusters and checks connectivity with them.
 - Adds a router and modifies a router interface.
 - Pulls zone data from the local clusters to create a zone distribution.
 - Creates a subnet and policy, and pulls address space, to configure DHCP failover pairs in Boston and Chicago.

Create the Regional Cluster Administrator

The regional superuser first creates the example-regional-administrator, defined with groups, to perform cluster and user administration.

Regional Web UI

-
- Step 1** Log into the regional cluster as superuser.
 - Step 2** From the **Administration** menu, choose **Administrators** to open the List/Add Administrators page for the local cluster version of this page, which is essentially identical.
 - Step 3** Click the Add Administrators icon in the Administrators pane, enter **example-regional-admin** in the Name field, then **examplereg** in the Password field in the Add Administrator dialog box, then click Add Administrator.
 - Step 4** Multiselect **central-cfg-admin-group** (for cluster administration) and **regional-admin-group** (for user administration) in the Groups drop-down list.
 - Step 5** Click **Save**.
-

Create the Central Configuration Administrator

As part of this tutorial, the example-regional-admin next logs in to create the example-cfg-admin, who must have regional configuration and address management capabilities.

Regional Web UI

-
- Step 1** Log out as superuser, then log in as **example-regional-admin** with password **examplereg**. Note that the administrator has all but host and address space administration privileges.
 - Step 2** From the **Administration** menu, choose **Administrators** to open the List/Add Administrators page.
 - Step 3** Click the **Add Administrators** icon in the Administrators pane, enter **example-cfg-admin** in the Name field, then **cfgadmin** in the Password field in the Add Administrator dialog box, then click **Add Administrator**.
 - Step 4** Multiselect **central-cfg-admin-group** and **regional-addr-admin-group** in the Groups drop-down list.
 - Step 5** Click **Save**. The example-cfg-admin now appears with the two groups assigned.
You can also add constraints for the administrator. Click **Add Constraint** and, on the Add Role Constraint for Role page, choose the read-only, owner, or region constraints, then click **Add Constraint**.
-

Create the Local Clusters

The example-cfg-admin next creates the two local clusters for Boston and Chicago.

Regional Web UI

-
- Step 1** Log out as example-regional-admin, then log in as **example-cfg-admin** with password **cfg admin**.
- Step 2** From the **Operate** menu, choose **Servers from the Manage Clusters** submenu to open the List/Add Remote Clusters page.
- Step 3** Click the **Add Manage Clusters** icon in the **Manage Clusters** pane.
- Step 4** On the Add Cluster dialog box, create the Boston cluster based on data provided by its administrator:
- Enter **Boston-cluster** in the name field.
 - Enter the IP address of the Boston server in the ipaddr field.
 - Enter **example-cluster-admin** in the admin field, then **exampleadmin** in the password field.
 - Enter in the SCPO-port field the SCP port to access the cluster as set at installation (**1234** is the preset value).
 - Click **Add Cluster**.
- Step 5** Create the Chicago cluster in the same way, except use **Chicago-cluster** in the name field, enter the remaining values based on data provided by the Chicago administrator, then click **Add Cluster**. The two clusters should now appear on the List/Add Remote Clusters page.
- Step 6** Connect to the Boston cluster. Click the **Go Local** icon next to Boston-cluster. If this opens the local cluster Manage Servers page, this confirms the administrator connectivity to the cluster. To return to the regional cluster web UI, click the **Go Regional** icon.
- Step 7** Connect to the Chicago cluster to confirm the connectivity in the same way.
- Step 8** Confirm that you can replicate data for the two forward zones from the Boston cluster synchronization:
- From the **Operate** menu, choose **Replica Data** from the **Servers** submenu.
 - On the View Replica Class List page, click Boston-cluster in the Select Cluster list.
 - In the Select Class list, click **Forward Zones**.
 - Click the **Replicate** icon in the Replicate Data column.
 - Click **View Replica Class List**. On the List Replica Forward Zones for Cluster page, you should see the boston.example.com and example.com zones.
-

Add Zone Management to the Configuration Administrator

Because there are no zones set up at the Chicago cluster, the example-cfg-admin can create a zone at the regional cluster to make it part of the zone distribution. However, the example-regional-admin must first modify the example-cfg-admin to be able to create zones.

Regional Web UI

-
- Step 1** Log out as example-cfg-admin, then log in as **example-regional-admin**.
- Step 2** From the **Administration** menu, choose **Administrators**.
- Step 3** On the List/Add Administrators page, click example-cfg-admin from the Administrators pane.
- Step 4** On the Edit Administrator page, click central-dns-admin-group in the Groups Available list, then move it (using <<) to the Selected list. The Selected list should now have central-cfg-admin-group, regional-addr-admin-group, and central-dns-admin-group.
- Step 5** Click **Save**. The change should be reflected on the List/Add Administrators page.
-

Create a Zone for the Local Cluster

The example-cfg-admin next creates the chicago.example.com zone for the zone distribution with the Boston and Chicago zones.

Regional Web UI

-
- Step 1** Log out as example-regional-admin, then log in as **example-cfg-admin**.
- Step 2** From the **Design** menu, choose **Forward Zones** under the **Auth DNS** submenu.
- Step 3** Click the **Add Forward Zones** icon in the **Forward Zones** pane.
- Step 4** On the Add Zone dialog box, enter:
- a) **Name**—chicago.example.com.
 - b) **Nameserver FQDN**—ns1.
 - c) **Contact E-mail**—hostmaster.
 - d) **Nameservers**—ns1 (click **Add Nameserver**).
 - e) Click **Add Zone**.
- Step 5** Click the **Reverse Zones** submenu.
- Step 6** On the List Reverse Zones page, create the **60.168.192.in-addr.arpa** reverse zone for the Chicago zone, with the proper attributes set.
-

Pull Zone Data and Create a Zone Distribution

The example-cfg-admin next pulls zone data from Boston and Chicago and creates a zone distribution.

Regional Web UI

-
- Step 1** As example-cfg-admin, from the **Design** menu, choose **Views** under the **Auth DNS** submenu to view the List/Add Zone Views page.
- Step 2** On the List/Add Zone Views page, pull the zone from the replica database:
- Click the **Pull Replica** icon in the **Views** pane.
 - On the Select Replica Downsize Data to Pull dialog box, leave the Data Synchronization Mode defaulted as Update, then click **Report** to open the Report Pull Replica Zone Data page.
 - Notice the change sets of data to pull, then click **Run**.
 - On the Run Pull Replica Zone Data page, click **OK**.
- Step 3** On the List/Add Zone Views page, notice that the Boston cluster zone distribution is assigned an index number (**1**) in the Name column. Click the number.
- Step 4** On the Edit Zone Views page, in the Primary Server field, click Boston-cluster. (The IP address of the Boston-cluster becomes the first master server in the Master Servers list.)
- Step 5** Because we want to make the Chicago-cluster DNS server a secondary server for the Boston-cluster:
- Click **Add Server** in the Secondary Servers area.
 - On the Add Zone Distribution Secondary Server page, choose **Chicago-cluster** in the Secondary Server drop-down list.
 - Click **Add Secondary Server**.
- Step 6** On the Edit Zone Distribution page, in the Forward Zones area, move **chicago.example.com** to the Selected list.
- Step 7** In the Reverse Zones area, move **60.168.192.in-addr.arpa** to the Selected list.
- Step 8** Click **Modify Zone Distribution**.
-

Create a Subnet and Pull Address Space

The example-cfg-admin next creates a subnet at the regional cluster. This subnet will be combined with the other two pulled subnets from the local clusters to create a DHCP failover server configuration.

Regional Web UI

-
- Step 1** As example-cfg-admin, from the **Design** menu, choose **Subnets** under the **DHCPv4** submenu to open the List/Add Subnets page.
- Step 2** Create an additional subnet, 192.168.70.0/24 by clicking the **Add Subnets** icon in the Subnets pane:
- Enter **192.168.70** (the abbreviated form) as the subnet network address in the Address/Mask field.
 - Leave the **24** (255.255.255.0) selected as the network mask.

c) Click **Add Subnet**.

Step 3 Click **Address Space** to confirm the subnet you created.

Step 4 On the View Unified Address Space page, click **Pull Replica Address Space**.

Step 5 On the Select Pull Replica Address Space page, leave everything defaulted, then click **Report**.

Step 6 The Report Pull Replica Address Space page should show the change sets for the two subnets from the clusters. Click **Run**.

Step 7 Click **OK**. The two pulled subnets appear on the List/Add Subnets page.

Push a DHCP Policy

The example-cfg-admin next creates a DHCP policy, then pushes it to the local clusters.

Regional Web UI

Step 1 As example-cfg-admin, from the **Design** menu, choose **Policies** under the **DHCP Settings** submenu.

Step 2 On the List/Add DHCP Policies page, click the **Add Policies** icon in the **Policies** pane.

Step 3 On the Add DHCP Policy dialog box, create a central policy for all the local clusters:

- a) Enter **central-policy-1** in the Name field. Leave the Offer Timeout and Grace Period values as is.
- b) Enter a lease period. In the DHCP > DHCPv4 > Options drop-down list, choose **dhcp-lease-time [51] (unsigned time)**, then enter **2w** (two weeks) for the lease period in the Value field.
- c) Click **Add Option**.
- d) Click **Add Policy**. The central-policy-1 should appear on the List/Add DHCP Policies page.

Step 4 Push the policy to the local clusters:

- a) Select the policy, central-policy-1 and click the **Push** button.
- b) On the Push DHCP Policy Data to Local Clusters page, leave the Data Synchronization Mode as **Ensure**. This ensures that the policy is replicated at the local cluster, but does not replace its attributes if a policy by that name already exists.
- c) Click **Select All** in the Destination Clusters section of the page.
- d) Click << to move both clusters to the Selected field.
- e) Click **Push Data to Clusters**.
- f) View the push operation results on the View Push DHCP Policy Data Report page, then click **OK**.

Create a Scope Template

The example-cfg-admin next creates a DHCP scope template to handle failover server pair creation.

Regional Web UI

-
- Step 1** As the example-cfg-admin user, from the Design menu, choose **Scope Templates** under the **DHCPv4** submenu.
- Step 2** On the List/Add DHCP Scopes page, click the **Add Scopes** icon in the **Scope Templates** pane. Enter **scope-template-1** in the Name field, then click **Add Scope Templates**.
- Step 3** The template should appear on the List/Add DHCP Scopes page. Set the basic properties for the scope template—Enter or choose the following values in the fields:
- a) **Scope Name Expression**—To autogenerate names for the derivative scopes, concatenate the example-scope string with the subnet defined for the scope. To do this, enter (**concat “example-scope-” subnet**) in the field (including the parentheses).
 - b) **Policy**—Choose **central-policy-1** in the drop-down list.
 - c) **Range Expression**—Create an address range based on the remainder of the subnet (the second through last address) by entering (**create-range 2 100**).
 - d) **Embedded Policy Option Expression**—Define the router for the scope in its embedded policy and assign it the first address in the subnet by entering (**create-option “routers” (create-ipaddr subnet 1)**).
- Step 4** Click **Save**.
-

Create and Synchronize the Failover Pair

The example-cfg-admin next creates the failover server pair relationship and synchronizes the failover pair. The DHCP server at Boston becomes the main, and the server at Chicago becomes the backup.

Regional Web UI

-
- Step 1** As the example-cfg-admin user, from the **Deploy** menu, choose **Failover** under the **DHCP** submenu.
- Step 2** On the List/Add DHCP Failover Pairs page, click the **Add Failover Pair** icon in the **Failover Pairs** pane.
- Step 3** On the Add DHCP Failover Pair dialog box, enter or choose the following values:
- a) **Failover Pair Name**—Enter **central-fo-pair**.
 - b) **Main Server**—Click **Boston-cluster**.
 - c) **Backup Server**—Click **Chicago-cluster**.
 - d) **Scope Template**—Click **scopetemplate-1**
 - e) Click **Add Failover Pair**.
- Step 4** Synchronize the failover pair with the local clusters:
- a) On the List/Add DHCP Failover Pairs page, click the **Report** icon in the Synchronize column.
 - b) On the Report Synchronize Failover Pair page, accept **Local Server** as the source of network data.
 - c) Accept **Main to Backup** as the direction of synchronization.
 - d) Accept the operation **Update**.
 - e) Click **Report** at the bottom of the page.
 - f) On the View Failover Pair Sync Report page, click **Run Update**.

g) Click **Return**.

Step 5

Confirm the failover configuration and reload the server at the Boston cluster:

- a) On the List/Add DHCP Failover Pairs page, click the **Go Local** icon next to Boston-cluster.
- b) On the Manage DHCP Server page, click the **Reload** icon.
- c) Click the **Go Regional** icon at the top of the page to return to the regional cluster.

Step 6

Confirm the failover configuration and reload the server at the Chicago cluster in the same way.



Maintaining Servers and Databases

This chapter explains how to administer and control your local and regional server operations.

- [Managing Servers, page 129](#)
- [Scheduling Recurring Tasks, page 131](#)
- [Logs, page 133](#)
- [Running Data Consistency Rules, page 137](#)
- [Monitoring and Reporting Server Status, page 140](#)
- [Troubleshooting DHCP and DNS Servers, page 156](#)
- [Using the TAC Tool, page 160](#)

Managing Servers

If you are assigned the server-management subrole of the ccm-admin role, you can manage the Cisco PrimeIP Express servers as follows:

- **Start**—Load the database and start the server.
- **Stop**—Stop the server.
- **Reload**—Stop and restart the server. (Note that you do not need to reload the server for all RR updates, even protected RR updates. For details, see the *"Managing DNS Update" chapter in Cisco PrimeIP Express 8.3 DHCP User Guide.*)
- **Check statistics**—See the [Displaying Statistics, on page 143](#).
- **View logs**—See the [Searching the Logs, on page 135](#).
- **Manage interfaces**—See the specific protocol pages for how to manage server interfaces.

Starting and stopping a server is self-explanatory. When you reload the server, Cisco Prime IP Express performs three steps—stops the server, loads configuration data, and restarts the server. Only after you reload the server does it use your changes to the configuration.

**Note**

The CDNS, DNS, DHCP, and SNMP servers are enabled by default to start on reboot. You can change this using `[server] type enable` or **disable start-on-reboot** in the CLI.

**Note**

If **exit-on-stop** attribute of DHCP, or DNS server is enabled, then the statistics and scope utilization data only from the last start (reload) is reported while if the attribute is disabled, information across reloads is displayed.

Local Basic or Advanced and Regional Web UI

You can manage the protocol servers in the following ways depending on if you are a:

- **Local or regional cluster administrator**—Choose **Manage Servers** from the **Operate** menu to open the Manage Servers page.

The local and regional cluster web UI access to server administration is identical, even though the available functions are different. As a regional administrator, you can check the state and health of the regional CCM server and server agent. However, you cannot stop, start, reload, or view statistics, logs, or interfaces for them.

At the local cluster, to manage the DHCP, DNS, CDNS, or SNMP servers, select the server in the Manage Servers pane and do any of the following:

- Click the **Statistics** tab to view statistics for the server. (See the [Displaying Statistics](#), on page 143.)
- Click the **Log** tab in the View Log column to view the log messages for the server. (See the [Searching the Logs](#), on page 135.)
- Click the **Start Server** button to start the server.
- Click the **Stop Server** button stop the server.
- Click the **Restart Server** button to reload the server.

- **Local cluster DNS administrator**—Choose **DNS Server** from the **Deploy** menu to open the Manage DNS Authoritative Server page.

Along with the Statistics, Startup Logs, Logs, HA DNS Server Status, Start Server, Stop Server, and Restart Server functions, you can also perform other functions when you click the Commands button to open the DNS Commands dialog box.

The server command functions are:

- **Forcing all zone transfers**(see the *"Enabling Zone Transfers" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*—Click the **Run** icon. This is the equivalent of **dns forceXfer secondary** in the CLI.
- **Scavenging all zones** (see the *"Scavenging Dynamic Records" section in Cisco PrimeIP Express 8.3 DHCP User Guide*—Click the **Run** icon. This is the equivalent of **dns scavenge** in the CLI.

- **Local cluster Caching DNS server**—Choose **CDNS Server** from the **Deploy** menu to open the Manage DNS Caching Server page.

Along with the Statistics, Startup Logs, Logs, Start Server, Stop Server, and Restart Server functions, you can also perform other functions when you click Commands button to open the CDNS Commands dialog box.

In Advanced and Expert modes, you can flush Caching CDNS cache and flush the resource records. Click the Commands button to execute the commands.

- **Local cluster DHCP administrator**—Click **DHCP Server** from the **Deploy** menu to open the Manage DHCP Server page.

Along with the Statistics, Startup Logs, Logs, Start Server, Stop Server, and Restart Server functions, you can also perform other functions when you click the Commands button to open the DHCP Server Commands dialog box.

This page provides the Get Leases with Limitation ID feature, to find clients that are associated through a common limitation identifier (see the *"Administering Option 82 Limitation" section in Cisco PrimeIP Express 8.3 DHCP User Guide*). Enter at least the IP address of the currently active lease in the IP Address field, then click the **Run** icon. You can also enter the limitation ID itself in the form *nn:nn:nn* or as a string ("*nnnn*"), in which case the IP address becomes the network in which to search. This function is the equivalent of **dhcp limitationList ipaddress limitation-id show** in the CLI.

CLI Commands

In the CLI, the regional cluster allows CCM server management only:

- To start the server, use **server type start** (or simply **type start**; for example, **dhcp start**).
- To stop the server, use **server type stop** (or simply **type stop**; for example, **dhcp stop**). If stopping the server, it is advisable to save it first using the **save** command.
- To reload the server, use **server type reload** (or simply **type reload**; for example, **dhcp reload**). Cisco Prime IP Express stops the server you chose, loads the configuration data, and then restarts the server.
- To set or show attributes for the server, use **[server] type set attribute=value** or **[server] type show**. For example:

```
nrcmd> ccm set ipaddr=192.168.50.10
```

Scheduling Recurring Tasks

In Basic and Advanced user mode in the local cluster web UI, you can schedule a number of recurring tasks. These tasks are:

- Reloading the DHCP server.
- Reloading the DNS server.
- Synchronizing DHCP failover server pairs:
 - If in staged dhcp edit mode, reload the main DHCP server.
 - Synchronize the failover configuration to the backup DHCP server.
 - If in staged dhcp edit mode, reload the backup DHCP server.
- Synchronizing High-Availability (HA) DNS server pairs:

- If in staged dhcp edit mode, reload the main DNS server.
- Synchronize the HA DNS configuration to the backup DNS server.
- If in staged dhcp edit mode, reload the backup DNS server.
- Synchronizing zone distribution maps:
 - If in staged dhcp edit mode, reload the main DNS server.
 - If in staged dhcp edit mode, reload the backup HA DNS server.
 - Synchronize the zone distribution maps.
 - If in staged dhcp edit mode, reload the secondary DNS server or servers.

Local Basic or Advanced Web UI

To set up one or more of these recurring server tasks:

-
- Step 1** From the **Operate** menu, choose **Schedule Tasks** to open the List/Add Scheduled Tasks page.
- Step 2** Click the **Add Scheduled Tasks** icon in the Scheduled Tasks pane on the left to open the Add Scheduled Task page.
- Step 3** Enter values in the appropriate fields:
- a) Name of the scheduled task. This can be any identifying text string.
 - b) Pull down from the available list of task types, which are:
 - **dhcp-reload**—Reloads the DHCP server
 - **dns-reload**—Reloads the DNS server
 - **cdns-reload**—Reloads the Caching DNS server
 - **sync-dhcp-pair**—Synchronizes the DHCP failover server pair
 - **sync-dns-pair**—Synchronizes the HA DNS failover server pair
 - **sync-zd-map**—Synchronizes zone distribution maps
 - **sync-dns-update-map**—Synchronizes DNS update maps
 - c) Indicate the time interval for the scheduled task, such as 60m or 4w2d.
- Step 4** Click **Add Scheduled Task**.
- Step 5** If you click the name of the task on the List/Add Scheduled Tasks page, on the Edit Scheduled Task page you can view (in the Task Status section) the last status or the list of last errors (if any) that occurred during the task execution. Click **Run Now** to run the task immediately.
- Note** The DNS server startup and background loading slows down when HA is enabled before the HA DNS server communicates to its partner. You need to allow the HA DNS server to communicate with its partner before reloading or restarting the DNS server.
-

Logs

Log Files

The following table describes the Cisco Prime IP Express log files in the *install-path* /logs directory.

Table 17: Log Files in .../logs Directory

Component	File in /logs Directory	Local/Regional	Logs
Installation	install_cnr_log	Both	Installation process
Upgrade	ccm_upgrade_status_log	Both	Upgrade process
	dns_upgrade_status_log	Local	Upgrade process
Server agent	agent_server_1_log	Both	Server agent starts and stops
Port check	checkports_log	Both	Network ports
DNS server	name_dns_1_log	Local	DNS activity
	dns_startup_log	Local	DNS startup activity
CDNS server	cdns_log	Local	CDNS activity
	cdns_startup_log	Local	CDNS startup activity
DHCP server	name_dhcp_1_log	Local	DHCP activity
	dhcp_startup_log	Local	DHCP startup activity
SNMP server	cnrsnmp_log	Both	SNMP activity
CCM database	config_ccm_1_log	Both	CCM configuration, starts, stops
	ccm_startup_log		CCM startup activity
Web UI	cnrwebui_log	Both	Web UI state
Tomcat/web UI (in cnrwebui subdirectory)	catalina.date .log.txt jsui_log.date .txt cnrwebui_access_log.date .txt	Both	CCM database for Tomcat server and web UI (Because new files are created daily, periodically archive old log files.)
Resource Limits	ccm_monitor_log	Both	Resource limit activity.

Each component can generate a number of log files, each with a pre-configured maximum size of 1 MB. The first log file name has the `_log` suffix. When this file reaches its maximum size, it gets the `.01` version extension appended to its name and a new log file is created without the version extension. Each version extension is incremented by one for each new file created. When the files reach their configured maximum number, the oldest file is deleted and the next oldest assumes its name. The usual maximum number is four for the DNS, and DHCP servers.

Cisco Prime IP Express also has `server_startup_log` files. This applies to the CCM, DHCP, and DNS servers. These files log the start up and shut down phases of the server (the information is similar to the normal log file information). Server startup log files are useful in diagnosing problems that have been reported when the server was last started.

The number of these start-up logs is fixed at four for a server, and the size is fixed at one MB per server.

**Note**

Some user commands can create *User authentication* entries in the Server Agent log because of separate connections to the cluster. Do not interpret these as a system security violation by another user.

CLI Commands

You can check the configured maximums for the DNS, and DHCP servers using `[server] type serverLogs show` in the CLI, which shows the maximum number (*nlogs*) and size (*logsize*) of these protocol server log files. You can adjust these parameters using `[server] type serverLogs set nlogs=value` and `[server] type serverLogs set logsize=value`. You cannot adjust these maximums for any of the other log files.

**Note**

A change to the server logs will not take effect until you restart Cisco Prime IP Express.

Logging Server Events

When you start Cisco PrimeIP Express, it automatically starts logging Cisco Prime IP Express system activity. Cisco Prime IP Express maintains all the logs by default on:

- **Windows**—*install-path \logs*
- **Linux**—*install-path /logs* (to view these logs, use the **tail -f** command)

**Tip**

To avoid filling up the Windows Event Viewer and preventing Cisco Prime IP Express from running, in the Event Log Settings, check the **Overwrite Events as Needed** box. If the events do fill up, save them to a file, then clear them from the Event Log.

Local Basic or Advanced and Regional Web UI

Server logging is available in the web UI when you open the Manage Servers page for a server (see the [Managing Servers, on page 129](#)), then click the **Log** icon in the View Log column for the server. This opens the Log for Server page. The log is in chronological order with the page with the latest entries shown first. If you need to see earlier entries, click the left arrow at the top or bottom of the page.

Related Topics

[Searching the Logs, on page 135](#)

[Logging Format and Settings, on page 135](#)

Logging Format and Settings

The server log entries include the following categories:

- **Activity**—Logs the activity of your servers.
- **Info**—Logs standard operations of the servers, such as starting up and shutting down.
- **Warning**—Logs warnings, such as invalid packets, user miscommunication, or an error in a script while processing a request.
- **Error**—Logs events that prevent the server from operating properly, such as out of memory, unable to acquire resources, or errors in configuration.



Note

Warnings and errors go to the Event Viewer on Windows (see the Tip in [Logging Server Events, on page 134](#)). For a description of the log messages for each server module, see the *install-path* /docs/msgid/MessageIdIndex.html file.

Local Basic or Advanced and Regional Web UI

You can affect which events to log. For example, to set the logging for the local cluster DNS and DHCP server:

- **DNS**—From the **Deploy > DNS** menu, choose **DNS Server** to open the Manage DNS Server page. Click the name of the server to open the Edit DNS Server page. Expand the Log Settings section to view the log settings. Make changes to the attributes as desired, click **Save**, then reload the server. (See *Table 4 in the "Troubleshooting DNS Servers" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide* for the log settings to maximize DNS server performance.)
- **DHCP**—From the **Deploy > DHCP** menu, choose **DHCP Server** to open the Manage DHCP Server page. Click the name of the server to open the Edit DHCP Server page. Expand the Log Settings section to view the log settings. Make changes to the attributes as desired, click **Save**, then reload the server. (See *Table 6 in the "Tuning the DHCP Server" section in Cisco PrimeIP Express 8.3 DHCP User Guide* for the log settings to maximize DHCP server performance.)

CLI Commands

Use **dns set log-settings**, **dhcp set log-settings**, and **tftp set log-settings** for the respective servers.

Searching the Logs

The web UI provides a convenient way to search for entries in the activity and startup log files. You can locate specific message text, log message IDs, and message timestamps using a regular expression string entry.

When you click the **Log** icon in the View Log or View Startup Log column on the Manage Servers page (or

one of the specific server pages), this opens a Log for Server page. In the text field next to the Search icon at the top or bottom of the page, enter the search string in the regular expression syntax. (For example, entering **name?** searches for occurrences of the string *name* in the log file.) Click the **Search** icon to view the results of log search.

Click the name of the log message, which opens the Log for Server page with the full message text. To view the full message text, click the name of the log message. Change between Table and Text view by clicking the **Log** icon. Click **Close** on the Log Search Result page to close the browser window.

View Change Log

In the web UI, you can view the change logs and tasks associated with configurations you make.

Local Basic and Advanced Web UI

From the **Operate** menu, choose **Change Log**. To view the change log, you must be assigned the database subrole of the ccm-admin or regional-admin role:

- The View Change Log page shows all the change logs, sorted by DBSN name. To get to the bottom of the list, click the right arrow at the bottom left of the page. Click the DBSN number of the change log entry to open a View Change Set page for it.
On the View Change Log page, you can filter the list, manually trim it, and save it to a file. You can filter the list by:
 - Start and end dates
 - Administrator who initiated the changes
 - Configuration object class
 - Specific object
 - Object identifier (ID), in the format OID-00:00:00:00:00:00:00:00
 - Server
 - Database

Click **Filter List** or **Clear Filter** (to clear the filter that persists through the session). You can initiate a trim of the change log by setting how many days old you want the record to get before trimming it, by setting a number of days value in the “older than” field and clicking the **Delete** icon.

To save the change log entries to a comma-separated values (CSV) file, click the **Save** icon.

If a task is associated with a change log, it appears on the View Change Set page. You can click the task name to open the View CCM Task page for it.

Dynamic Update on Server Log Settings

The DHCP and the DNS servers register the changes on the server logs only during the server configuration, which happens during a reload. Reloading the servers is time consuming. Cisco Prime IP Express allows the DHCP and DNS servers to register the changes to log settings, without a reload.

Local Basic or Advanced Web UI

To dynamically update DHCP server log settings, do the following:

-
- Step 1** From the **Deploy > DHCP** menu, choose **DHCP Server**. The Manage DHCP Server page appears.
 - Step 2** Click the name of the DHCP server in the left pane to open the Edit DHCP Server page.
 - Step 3** Modify the log settings as desired.
 - Step 4** Click **Save** at the bottom of the page. The new log settings are applied to the DHCP server. The Manage DHCP Server page is displayed with an updated page refresh time.
-

Local Basic or Advanced Web UI

To dynamically update DNS server log settings, do the following:

-
- Step 1** From the **Deploy > DNS** menu, choose **DNS Server**. This opens the Manage DNS Server page.
 - Step 2** Click the name of the DNS server in the left pane to open the Edit DNS Server page.
 - Step 3** Modify the log settings as desired.
 - Step 4** Click **Save** at the bottom of the page. The new log settings are applied to the DNS server. The Manage DNS Server page is displayed with an updated page refresh time.
- Note** If the dhcp-edit-mode or dns-edit-mode is set to synchronous, and if the server running, the change in server log settings is communicated to the server.
-

CLI Commands

To dynamically update the DHCP or DNS server log settings using the CLI, you must have the appropriate edit-mode set to synchronous. After changing the server log settings, use the save command to save the settings.

For example:

```
nrcmd>session set dhcp-edit-mode=synchronous
nrcmd>dhcp set log-settings=new-settings
nrcmd>save
```

Running Data Consistency Rules

Using consistency rules, you can check data inconsistencies such as overlapping address ranges and subnets. You can set data consistency rules at the regional and local clusters.

The table on the List Consistency Rules page explains these rules. Check the check box next to the rule that you want to run.

**Note**

You must set the locale parameters on UNIX to en_US.UTF-8 when running Java tools that use Java SDK, such as `cnr_rules`.

The List Consistency Rules page includes functions to select all rules and clear selections. You can show the details for each of the rule violations as well as view the output. The rule selections you make are persistent during your user session.

Local Basic or Advanced and Regional Web UI

To run consistency rules, do the following:

-
- Step 1** From the **Operate > Reports** menu, choose **Consistency Reports**.
The List Consistency Rules page appears.
- Step 2** Check the check boxes for each of the listed consistency rules that you want to apply.
- To select all the rules, click the **Select All Rules** link.
 - To clear all selections, click the **Clear Selection** link.
- Step 3** Click **Run Rules**.
The Consistency Rules Violations page appears. The rules are categorized by violation type.
- To show details for the violations, click the **Show Details** link.
 - To show the output, click the page icon.
- Step 4** Click **Return** to return to the List Consistency Rules page.
-

CLI Tool

Use the `cnr_rules` consistency rules tool from the command line to check for database inconsistencies. You can also use this tool to capture the results of the rule in a text or XML file.

The `cnr_rules` tool is located at:

- **Windows**—...\\bin\\cnr_rules.bat
- **Linux**—.../usrbin/cnr_rules

To run the `cnr_rules` tool, enter:

```
> cnr_rules -N username -P password [options]
```

- `-N username` —Authenticates using the specified username.
- `-P password` —Authenticates using the specified password.

- *options* —Describes the qualifying options for the tool, as described in the following table. If you do not enter any options, the command usage appears.

Table 18: *cnr_rules Options*

Option	Description
Example	
-list	<p>Lists the available consistency rules.</p> <p>Note The list of available commands is tailored to the permissions of the administrator specified in the value of the -N option.</p> <pre>> cnr_rules -N admin -P changeme -list</pre>
-run [rule-match]	<p>Run the available rules. Optionally, you can run a subset of the available rules by applying a case-insensitive rule-match string.</p> <ul style="list-style-type: none"> • Runs all rules: <pre>> cnr_rules -N admin -P changeme -run</pre> <ul style="list-style-type: none"> • Runs only the rules whose names contain the string "dhcp": <pre>> cnr_rules -N admin -P changeme -run dhcp</pre> <p>Tip To match a string containing spaces, enclose the string using double-quotation marks ("). For example: > cnr_rules -N admin -P changeme -run "router interface"</p>
-details	<p>Includes details of the database objects that violate consistency rules in the results.</p> <p>Runs the DNS rules, and includes details of the database object in the results:</p> <pre>> cnr_rules -N admin -P changeme -run DNS -details</pre>
-xml	<p>Generates rule results in an XML file.</p> <p>Note When using the -xml option, the -details option is ignored because the XML file includes all the detailed information.</p> <pre>> cnr_rules -N admin -P changeme -run -xml</pre>

Option	Description
-path <i>classpath</i>	Changes the Java classpath that is searched to locate the available consistency rules (optional). In order to run a new, custom consistency rule, you can use this option. You must get the support of a support engineer to do this.
<p>You can redirect the output of any of these preceding commands to another file. Use the following syntax to capture the rule results in a:</p> <ul style="list-style-type: none"> Text file: <pre>> cnr_rules -N username -P password -run -details > filename.txt</pre> <ul style="list-style-type: none"> XML file: <pre>> cnr_rules -N username -P password -run -xml > filename.xml</pre>	
-interactive	<p>Runs the tool in an interactive session.</p> <pre>> cnr_rules -N admin -P changeme -run -interactive RuleEngine [type ? for help] > ? Commands: load <class> // load the specified rule class run <rule-match> // run rules matching a string, or '*' for all list // list rules by name xml // toggle xml mode detail // toggle detail mode (non-xml only) quit // quit RuleEngine</pre>

Monitoring and Reporting Server Status

Monitoring the status of a server involves checking its:

- State
- Health
- Statistics
- Log messages

- Address usage
- Related servers (DNS and DHCP)
- Leases (DHCP)

Related Topics

[Server States, on page 141](#)

[Displaying Health, on page 141](#)

[Displaying Statistics, on page 143](#)

[Displaying IP Address Usage, on page 152](#)

[Displaying Related Servers, on page 153](#)

[Displaying Leases, on page 155](#)

Server States

All Cisco Prime IP Express protocol servers (DNS, DHCP, and SNMP) pass through a state machine consisting of the following states:

- **Loaded**—First step after the server agent starts the server (transitional).
- **Initialized**—Server was stopped or fails to configure.
- **Unconfigured**—Server is not operational because of a configuration failure (transitional).
- **Stopped**—Server was administratively stopped and is not running (transitional).
- **Running**—Server is running successfully.

The two essential states are initialized and running, because the server transitions through the states so quickly that the other states are essentially invisible. Normally, when the server agent starts the server, it tells the server to be up. The server process starts, sets its state to loaded, then moves up to running. If you stop the server, it walks down the states to initialized, and if you restart, it moves up to running again. If it fails to configure for some reason, it drops back to initialized, as if you had stopped it.

There is also an exiting state that the server is in very briefly when the process is exiting. The user interface can also consider the server to be disabled, but this rarely occurs and only when there is no server process at all (the server agent was told not to start one).

Displaying Health

You can display aspects of the health of a server, or how well it is running. The following items can decrement the server health, so you should monitor their status periodically. For the:

- Server agent (local and regional clusters)
- CCM server (local and regional clusters)
- DNS server (local cluster):
 - Configuration errors

- Memory
- Disk space usage
- Inability to contact its root servers
- Caching DNS server (local cluster)
- DHCP server (local cluster):
 - Configuration errors
 - Memory
 - Disk space usage
 - Packet caching low
 - Options not fitting in the stated packet limit
 - No more leases available

Server Health Status

The server health status varies from the value 0 to 10. The value 0 means the server is not running and 10 means the server is running. Some of the servers report only 0 or 10, and not anything in between. When a server reports a value from 1 to 9, it means that it detected conditions that indicate possible problems. It has nothing to do with the actual performance of the server. So, if the health of the server is a value from 1 to 9, the server log files need to be reviewed to see what errors were logged.



Note

Depending on the level of activity and the size and number of log files, the condition that reduced the server health might not be visible in the log files. It is important to review the log files, but the servers do not log all the conditions that reduce the server health.

The following conditions can reduce the DHCP server health:

- Configuration errors (occurs when the server is getting started or restarting)
- When the server detects out-of-memory conditions
- When packet receive failures occur
- When packets are dropped because the server is out of request or response buffers
- When the server is unable to construct a response packet



Tip

Health values range from 0 (the server is not running) to 10 (the highest level of health). It is recommended that the health status can be ignored, with the understanding that zero means server is not running and greater than zero means server is running. On Linux, you can run the **cnr_status** command, in the *install-path* /usrbin/ directory, to see if your local cluster server is running. For more information on how to check whether the local cluster server is running, see the *Cisco Prime IP Express Installation Guide*.

Local Basic or Advanced and Regional Web UI

From the **Operate** menu, select **Manage Servers**. Check the Manage Servers page for the state and health of each server.

CLI Commands

Use `[server] type getHealth`. The number 10 indicates the highest level of health, 0 that the server is not running.

Displaying Statistics

To display server statistics, the server must be running.

Local Basic or Advanced and Regional Web UI

Go to the Manage Servers page, click the name of the server in the left pane, then click the **Statistics** tab, if available. On the Server Statistics page, click the name of the attribute to get popup help.

The DHCP, DNS, and CDNS statistics are each divided into two groups of statistics. The first group is for total statistics and the second group is for sample statistics. The total statistics are accumulated over time. The sample statistics occur during a configurable sample interval. The names of the two categories vary per server and per user interface, and are identified in the following table.

Table 19: Server Statistics Categories

Server	User Interface	Total Statistics (Command)	Sample Statistics (Command)
DHCP	Web UI	Total Statistics	Activity Summary
	CLI	Total Counters since the start of the last DHCP server process (dhcp getStats)	Sampled counters since the last sample interval (dhcp getStats sample)
DNS	Web UI	Total Statistics	Sample Statistics
	CLI	Total Counters since the start of the last server process (dns getStats)	Sampled counters since the last sample interval (dns getStats sample)
CDNS	Web UI	Total Statistics	Sample Statistics
	CLI	Total Counters since the start of the last server process (cdns getStats total)	Sampled counters since the last sample interval (cdns getStats sample)

To set up the sample counters, you must activate either the *collect-sample-counters* attribute for the server or a *log-settings* attribute value called activity-summary. You can also set a *log-settings* value for the sample interval for each server, which is preset to 5 minutes. The *collect-sample-counters* attribute is preset to true

for the DNS server, but is preset to false for the DHCP server. For example, to enable the sample counters and set the interval for DHCP, set the following attributes for the DHCP server:

- Enable *collect-sample-counters* (**dhcp enable collect-sample-counters**)
- Set *log-settings* for activity-summary (**dhcp set log-settings=activity-summary**)
- Set *activity-summary-interval* to 5m (**dhcp set activity-summary-interval=5m**)

CLI Commands

In the CLI, if you use **[server] type getStats**, the statistics are encoded in curly braces followed by sets of digits, as described in [Table 20: DNS Statistics](#) for DNS, [Table 22: DHCP Statistics](#) for DHCP Statistics. The **server type getStats all** command is more verbose and identifies each statistic on a line by itself. Using the additional **sample** keyword shows the sample statistics only.

Reset the counters and total statistic by using **dhcp resetStats**, **dns resetStats**, or **cdns resetStats**.

DNS Statistics

The DNS server statistics in the web UI appear on the DNS Server Statistics page, click on the statistic's name to read its description. You can refresh the DNS Server Statistics.

The DNS server statistics that you can view are:

- Attribute—Displays server statistics such as server identifier, recursive service, process uptime, time since reset, and so on.

Total Statistics

- Performance Statistics—Displays the total statistics of the DNS Server performance.
- Query Statistics—Displays the total statistics of the queries.
- Security Statistics—Displays the total statistics of the security.
- Error Statistics—Displays the total statistics of the errors.
- Max Counter Statistics—Displays the total statistics of the maximum number of concurrent threads, RRs, DNS update latency, concurrent packets, and so on.
- HA Statistics—Displays the total statistics of the HA DNS Server.
- IPv6 Statistics—Displays the total statistics of the IPv6 packets received and sent.

Sample Statistics

- Performance Statistics—Displays the sample statistics about the DNS Server performance.
- Query Statistics—Displays the sample statistics about the queries.
- Security Statistics—Displays the sample statistics about the security.
- Error Statistics—Displays the sample statistics about the errors.
- HA Statistics—Displays the sample statistics about the HA DNS Server.
- IPv6 Statistics—Displays the sample statistics about the IPv6 packets received and sent.

**Note**

To get the most recent data, click the Refresh Server Statistics icon at the top left corner of the page.

The CLI `dns getStats` command has the following options:

```
dns getStats [performance | query | errors | security | maxcounters | ha | ipv6 | all]
[total | sample]
```

The `dns getStats all` command is the most commonly used.

```
nrcmd> dns getStats
nrcmd> dns getStats
```

```
100 Ok
{1} 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16
```

Table 20: DNS Statistics

Digit	Statistic	Description
{1}	id	Implementation ID (release and build information).
2	config-recurs	Recursion services—(1) available, (2) restricted, (3) unavailable.
3	config-up-time	Time (in seconds) elapsed since the last server startup.
4	config-reset-time	Time (in seconds) elapsed since the last server reset (restart).
5	config-reset	Status or action to reinitializes any name server state—If using the (2) reset action, reinitializes any persistent name server state; the following are read-only statuses: (1) other—server in some unknown state, (3) initializing, or (4) running.
6	counter-auth-ans	Number of queries answered authoritatively.
7	counter-auth-no-names	Number of queries returning authoritative no such name responses.
8	counter-auth-no-data-resps	Number of queries returning authoritative no such data (empty answer) responses. (Deprecated statistics)

Digit	Statistic	Description
9	counter-non-auth-datas	Number of queries answered nonauthoritatively (cached). (Deprecated statistics)
10	counter-non-auth-no-datas	Number of queries answered nonauthoritatively with no data.
11	counter-referrals	Number of queries forwarded to other servers.
12	counter-errors	Number of responses answered with errors (RCODE values other than 0 or 3).
13	counter-rel-names	Number of requests received for names of only one label (relative names).
14	counter-req-refusals	Number of refused queries.
15	counter-req-unparses	Number of unparsable requests.
16	counter-other-errors	Number of aborted requests due to other errors.
17	total-zones	Total number of configured zones.

CDNS Statistics

The CDNS server statistics in the web UI appear on the DNS Caching Server Statistics page, click on the name of the statistics to read its description. You can refresh the CDNS Server Statistics.

Table 21: CDNS Statistics

Digit	Statistic	Description
{1}	name	Name identifying the DNS Caching Server.
2	time-current	The current time given by the CDNS Server.
3	time-up	The amount of time the server has been up and running.
4	time-elapsed	The elapsed since last statistics poll.

Digit	Statistic	Description
5	queries-total	Total number of queries received by the CDNS Server.
6	queries-over-tcp	Total number of queries received over TCP by the CDNS Server.
7	queries-over-ipv6	Total number of queries received over TCP by the CDNS Server.
8	queries-with-edns	Number of queries with EDNS OPT RR present.
9	queries-with-edns-do	Number of queries with EDNS OPT RR with DO (DNSSEC OK) bit set.
10	queries-type-A	Number of A queries received.
11	queries-type-AAAA	Number of AAAA queries received.
12	queries-type-CNAME	Number of CNAME queries received.
13	queries-type-PTR	Number of PTR queries received.
14	queries-type-NS	Number of NS queries received.
15	queries-type-SOA	Number of SOA queries received.
16	queries-type-MX	Number of MX queries received.
17	queries-type-DS	Number of DS queries received.
18	queries-type-DNSKEY	Number of DNSKEY queries received.
19	queries-type-RRSIG	Number of RRSIG queries received.
21	queries-type-NSEC	Number of NSEC queries received.
22	queries-type-NSEC3	Number of NSEC3 queries received.
23	queries-type-other	Number of queries received of type 256+.

Digit	Statistic	Description
24	queries-with-flag-QR	Number of incoming queries with QR (query response) flag set. These queries are dropped.
25	queries-with-flag-AA	Number of incoming queries with AA (auth answer) flag set. These queries are dropped.
26	queries-with-flag-TC	Number of incoming queries with TC (truncation) flag set. These queries are dropped.
27	queries-with-flag-RD	Number of incoming queries with RD (recursion desired) flag set.
28	queries-with-flag-RA	Number of incoming queries with RA (recursion available) flag set.
29	queries-with-flag-Z	Number of incoming queries with Z flag set.
30	queries-with-flag-AD	Number of incoming queries with AD flag set.
31	queries-with-flag-CD	Number of incoming queries with CD flag set.
32	queries-failing-acl	Number of queries being dropped or refused due to ACL failures.
33	cache-hits	The total number of queries that were answered from cache.
34	cache-misses	The total number of queries that were not found in the cache.
35	cache-prefetches	Number of prefetches performed.
36	requestlist-total	The total number of queued requests waiting for recursive replies.
37	requestlist-total-user	The total number of queued user requests waiting for recursive replies.
38	requestlist-total-system	The total number of queued system requests waiting for recursive replies.

Digit	Statistic	Description
39	requestlist-total-average	The average number of requests on the request list.
40	requestlist-total-max	The maximum number of requests on the request list.
41	requestlist-total-overwritten	The number of requests on the request list that were overwritten by newer entries.
42	requestlist-total-exceeded	The number of requests dropped because the request list was full.
43	recursive-replies-total	The total number of recursive queries replies.
44	recursive-time-average	The average time to complete a recursive query.
45	recursive-time-median	The median time to complete a recursive query.
46	mem-process	An estimate of the memory in bytes of the CDNS process.
47	mem-cache	Memory in bytes of RRSet cache.
48	mem-query-cache	Memory in bytes of incoming query message cache.
49	mem-iterator	Memory in bytes used by the CDNS iterator module.
50	mem-validator	Memory in bytes used by the CDNS validator module.
51	answers-with-NOERROR	Number of answers from cache or recursion that result in rcode of NOERROR being returned to client.
52	answers-with- NXDOMAIN	Number of answers from cache or recursion that result in rcode of NXDOMAIN being returned to client.
53	answers-with-NODATA	Number of answers that result in pseudo rcode of NODATA being returned to client.

Digit	Statistic	Description
54	answers-with-other-errors	Number of answers that result in pseudo rcode of NODATA being returned to client.
55	answers-secure	Number of answers that correctly validated.
56	answers-unsecure	Number of answers that did not correctly validate.
57	answers-rrset-unsecure	Number of RRSets marked as bogus by the validator.
58	answers-unwanted	Number of replies that were unwanted or unsolicited. High values could indicate spoofing threat.
59	reset-time	Reports the most recent time the stats were reset (i.e. cdns resetStats in nrcmd).
60	sample-time	Reports the time the server collected the last set of sample statistics.
61	sample-interval	Reports the sample interval used by the server when collecting sample statistics.

DHCP Statistics

The DHCP server statistics in the web UI appear on the DHCP Server Statistics page, click on the statistic's name to read its description.

The DHCP server statistics details are available for:

- **Attribute**—Displays the server statistics such as server start time, server reload time, server up time, and statistics reset time.
- **Total Statistics**—Displays the total statistics of the scopes, request buffers, response buffers, packets and so on.
- **Lease Counts (IPv4)**—Displays the sample statistics of the IPv4 lease counts such as active leases, configured leases, reserved leases, and reserved active leases.
- **Packets Received (IPv4)**—Displays the sample statistics of the IPv4 packets received.
- **Packets Sent (IPv4)**—Displays the sample statistics of the IPv4 packets sent.

- Packets Failed (IPv4)—Displays the statistics of the failed IPv4 packets.

The Additional Attributes are:

- Failover Statistics—Displays the statistics of the DHCP failover server.
- IPv6 Statistics—Displays the statistics of the IPv6 prefixes configured, timed-out IPv6 offer packets and so on.
- Lease Counts (IPv6)—Displays the statistics of the IPv6 lease counts of active leases, configured leases, reserved leases, and reserved active leases.
- Packets Received (IPv6)—Displays the statistics of the IPv6 packets received.
- Packets Sent (IPv6)—Displays the statistics of the IPv6 packets sent.
- Packets Failed (IPv6)—Displays the statistics of the failed IPv6 packets.

Additional Attributes also includes Top Utilized Aggregations.

The CLI `dhcp getStats` command has the following options:

```
dhcp getStats [[all | server [,] failover [,] dhcpv6] [total | sample]
```

The `dhcp getStats all` command is the most commonly used.

```
nrcmd> dhcp getStats
```



Note

To get the most recent data, click the Refresh Server Statistics icon at the top left of the page.

The CLI `dhcp getStats` command has the following options:

```
dhcp getStats[[all| server[,] failover  
[,] dhcpv6] [total| sample]
```

The `dhcp getStatsall` command is the most commonly used. The `dhcp getStats` command without this option returns the statistics in a single line of positional values in the following format (The table below shows how to read these values):

```
(The table below shows how to read these values):  
nrcmd> dhcp getStats  
100 Ok  
{1} 2 3 4 5 6 7 8
```

Table 22: DHCP Statistics

Digit	Statistic	Description
{1}	start-time-str	Date and time of last server reload, as a text string.
2	total-discovers	Number of DISCOVER packets received.
3	total-requests	Number of REQUEST packets received.
4	total-releases	Number of RELEASED packets received.

Digit	Statistic	Description
5	total-offers	Number of OFFER packets sent.
6	total-acks	Number of acknowledgement (ACK) packets sent.
7	total-naks	Number of negative acknowledgement (NAK) packets sent.
8	total-declines	Number of DECLINE packets received.

Displaying IP Address Usage

Displaying IP address usage gives an overview of how clients are currently assigned addresses.

Local Advanced and Regional Web UI

You can look at the local or regional cluster address space, or generate a subnet utilization or lease history report at the regional cluster, to determine IP address usage. These functions are available in both web UIs in the **Design > DHCPv4** menu, if you have address space privileges at the local or regional cluster.

You can determine the current address space utilization by clicking the View icon in the Current Usage column for the unified address space, address block, and subnet (see the *"Viewing Address Utilization for Address Blocks, Subnets, and Scopes"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*). You can also get the most current IP address utilization by querying the lease history (see the *"Querying Leases"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*). In the latter case, the regional CCM server references the appropriate DHCP server directly. To ensure this subnet-to-server mapping, you must update the regional address space view so that it is consistent with the relevant local cluster. Do this by pulling the replica address space, or reclaiming the subnet to push to the DHCP server (see the *"Reclaiming Subnets"* section in *Cisco PrimeIP Express 8.3 DHCP User Guide*). Also ensure that the particular DHCP server is running.

CLI Commands

You can generate an IP address usage report using the **report** command. The command has the following syntax:

```
report[column-separator=string | dhcpv4
| dhcp-only| dhcpv6| file=outputfile |
vpn=
```

The column-separator specifies the character string that separates the report columns (the preset value is the space character). If you want to include more than one space, precede them with the backslash (\) escape character (enclosed in quotation marks). You can specify DHCPv4 or DHCPv6 addresses (**dhcp-only** is the same as **dhcpv4**). Not specifying the VPN returns the addresses in the current VPN only.

Displaying Related Servers

Cisco Prime IP Express displays the relationship among servers in a DNS zone distribution or a DHCP failover configuration. In the web UI, you can view a related servers page when you click the Related Servers icon on various pages. You can use the display of related servers to diagnose and monitor misconfigured or unreachable servers.

Related Topics

[Monitoring Remote Servers Using Persistent Events, on page 153](#)

[DNS Zone Distribution Servers, on page 154](#)

[DHCP Failover Servers, on page 155](#)

Monitoring Remote Servers Using Persistent Events

To service clients that require updates to DNS and LDAP related servers, the DHCP server uses a persistent event algorithm to ensure updates to related servers when a related server is temporarily unavailable. In addition, the algorithm prevents a misconfigured or offline DNS server from using up all the available update resources.

At startup, the DHCP server calculates the number of related servers in the configuration that require persistent events. A preconfigured Maximum Pending Events attribute (an Expert mode attribute that specifies the number of in-memory events that is preset to 40,000) is divided by the number of servers to obtain a limit on the number of events permitted for each remote server. This calculation covers related DNS and LDAP servers (DHCP failover does not use persistent storage for events). The DHCP server uses this calculation to issue log messages and take the action described in the following table. The table shows a hypothetical case of a DHCP server with four related DNS servers each having a limit of 10K events.

Table 23: Persistent Event Algorithm

Event Reached	DHCP Server Action
50% of the calculated per-server limit (Maximum Pending Events value divided by the number of total related servers); for example, 5K events on a related server out of a total of 40K maximum pending events	<p>Issues an INFO log message every 2 minutes, as long as the limits are exceeded:</p> <pre>The queue of events for the <i>name</i> remote server at <i>address</i> has <i>x</i> events, and has reached the info limit of <i>y</i>/2 events out of an upper limit of <i>y</i> events per remote server. The remote server may be misconfigured, inoperative, or unreachable .</pre>

Event Reached	DHCP Server Action
100% of the calculated per-server limit and less than 50% of the Maximum Pending Events value; for example, 10K events on a related server, with fewer than 10K total maximum pending events	Issues a WARNING log message every 2 minutes, as long as the limits are exceeded: The queue of events for the <i>name</i> remote server at address has <i>x</i> events, has exceeded the limit of <i>y</i> events per remote server, but is below the limit of <i>z</i> total events in memory. The remote server may be misconfigured, inoperative, or unreachable.
100% of the calculated per-server limit and 50% or more of the Maximum Pending Events value; for example, 10K events on a related server, with 20K total maximum pending events	Issues an ERROR log message every 2 minutes, as long as the limits are exceeded: The queue of events for the <i>name</i> remote server at <i>address</i> has <i>x</i> events, and has grown so large that the server cannot continue to queue new events to the remote server. The limit of <i>y</i> events per remote server and <i>z</i> /2 total events in memory has been reached. This and future updates to this server will be dropped. The current eventID <i>n</i> is being dropped. The server drops the current triggering event and all subsequent events with that server.
100% of the Maximum Pending Events value; for example, 40K events across all related servers	Issues an ERROR log message: The queue of pending events has grown so large that the server cannot continue to queue new events. The queue's size is <i>z</i> , and the limit is <i>z</i> . The server drops all subsequent events with all related servers.

SNMP traps and DHCP server log messages also provide notification that a related server is unreachable.

DNS Zone Distribution Servers

A DNS zone distribution simplifies creating multiple zones that share the same secondary server attributes. You can view and set the primary and secondary DNS servers in a zone distribution.

Local Basic or Advanced Web UI

From the **Deploy > DNS** menu, click **Zone Distribution**. This opens the List Zone Distributions page. The local cluster allows only one zone distribution, the default. Click this zone distribution name to open the Edit Zone Distribution page, which shows the authoritative and secondary servers in the zone distribution.

Regional Web UI

From the **Deploy > DNS** menu, choose **Zone Distributions**. This opens the List/Add Zone Distributions page. The regional cluster allows creating more than one zone distribution. Click the zone distribution name to open the Edit Zone Distribution page, which shows the primary, authoritative, and secondary servers in the zone distribution.

CLI Commands

Create a zone distribution using **zone-dist name create primary-cluster**, then view it using **zone-dist list**. For example:

```
nrcmd> zone-dist distr-1 create Boston-cluster
nrcmd> zone-dist list
```

DHCP Failover Servers

Related servers in a DHCP failover pair relationship can show the following information:

- **Type**—Main or backup DHCP server.
- **Server name**—DNS name of the server.
- **IP address**—Server IP address in dotted octet format.
- **Requests**—Number of outstanding requests, or two dashes if not applicable.
- **Communication status**—OK or INTERRUPTED.
- **Cluster state**—Failover state of this DHCP server.
- **Partner state**—Failover state of its partner server.

For details on DHCP failover implementation, see the *"Managing DHCP Failover" section in Cisco PrimeIP Express 8.3 DHCP User Guide*

Local Basic or Advanced Web UI

From the **Deploy > DHCP** menu, choose **Failover Pairs**. The List/Add DHCP Failover Pairs page shows the main and backup servers in the failover relationship.

CLI Commands

Use **dhcp getRelatedServers** to display the connection status between the main and partner DHCP servers. If there are no related servers, the output is simply 100 Ok .

Displaying Leases

After you create a scope, you can monitor lease activity and view lease attributes.

Local Basic or Advanced Web UI

From the **Design > DHCPv4** menu, choose **Scopes**; or from the **Design > DHCPv6** menu, choose **Prefixes** (in Advanced mode). On the List/Add DHCP Scopes or List/Add DHCPv6 Prefixes page, click the **View** icon in the Leases column to open the List DHCP Leases for Scope or List DHCP Leases for Prefix page.

Regional Web UI

From the **Operate > Reports > DHCPv4** menu or **Operate > Reports > DHCPv6** menu, choose **Lease History**. Set the query parameters, then click **Query Lease History**. (See the *"Querying Leases" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide*.)

Troubleshooting DHCP and DNS Servers

The following sections describe troubleshooting the configuration and the DNS, and DHCP servers.

Related Topics

[Immediate Troubleshooting Actions](#), on page 156

[Modifying the cnr.conf File](#), on page 156

[Troubleshooting Server Failures](#), on page 158

[Linux Troubleshooting Tools](#), on page 159

[Using the TAC Tool](#), on page 160

Immediate Troubleshooting Actions

When facing a problem, it is crucial not to cause further harm while isolating and fixing the initial problem. Here are things to do (or avoid doing) in particular:

- Have 512 MB or more of memory and 2.5 GB or more of a data partition.
- Do not reboot a cable modem termination system (CMTS).
- Enable DHCP failover.
- Do not reload, restart, or disrupt Cisco Prime IP Express with failover resynchronization in progress.

Modifying the cnr.conf File

Cisco Prime IP Express uses the **cnr.conf** file for basic configuration parameters. This file is normally located in the *install-path*/conf directory. Cisco Prime IP Express creates the file during installation and processes it line by line.

You can edit this file if configuration parameters change. Note that during normal operation, you would not want to change the values. However, certain conditions might require you to modify certain values, such as when you move the data files for disk space reasons.

The format of the **cnr.conf** file consists of parameter name-value pairs, one per line; for example, for a Windows local cluster installation:

```
cnr.rootdir=C:\\Program Files (x86)\\Cisco Prime IP Express\\Local
cnr.ccm-port=1234
cnr.cisco-gss-appliance-integration=n
cnr.datadir=C:\\CiscoPrimeIPExpress\\Local\\data
cnr.java-home=C:\\Program Files\\Java\\jre1.5.0_12
cnr.logdir=C:\\CiscoPrimeIPExpress\\Local\\logs
cnr.https-port=8443
cnr.tempdir=C:\\CiscoPrimeIPExpress\\Local\\temp
cnr.http-port=8080
cnr.ccm-mode=local
cnr.ccm-type=cnr
cnr.http-enabled=y
cnr.https-enabled=n
cnr.keystore-file=C:
cnr.keystore-password=unset
cnr.backup-time=23:45
```

Directory paths must be in the native syntax for the operating system. The format allows the use of colons (:) in directory paths, but not as name-value pair separators; it does not allow line continuation or embedded unicode characters. Other modifications to the file might include the location of the log directory (see [Log Files, on page 133](#)) or the time `cnr_shadow_backup` backups should occur (see [Setting Automatic Backup Time, on page 163](#)).

In rare cases, you might want to modify the file; for example, to exclude certain data from daily backups due to capacity issues. To do this, you need to add the appropriate settings manually.



Caution

We recommend that you use the default settings in this file. If you must change these settings, do so only in consultation with the Cisco Technical Assistance Center (TAC) or the Cisco Prime IP Express development team.

The following settings are supported:

- `cnr.backup-dest`—Specify the destination to place backed up databases. Defaults to `cnr.datadir` if not specified.
- `cnr.backup-dbs`—Provide a comma-separated list of the databases you want to backup. For a local cluster the default is `ccm,dhcp,dns,mcd`. For a regional cluster it is `ccm,lease6hist,leasehist,subnetutil,replica`.
- `cnr.backup-files`—Provide a comma-separated list of files and the complete path to the files that you want copied as part of the backup. Files are copied to `cnr.backup-dest`.
- `cnr.dbrecover-backup`—Specify whether to run db recover and db verify on a backed up Oracle Berkeley database. The default is true. This setting is used for daily backups only. Manual backups ignore this setting. Disabling the automatic operation means that you must run the operation manually, preferably on a separate machine, or at a time when the Cisco Prime IP Express servers are relatively idle.
- `cnr.daily-backup`—Specify whether to run the daily back up. The default is true.

Modifying the `cnr.conf` File for Syslog Support

Cisco Prime IP Express supports logging to a Syslog server (on Linux). The Syslog support is not enabled by default. To configure which messages need to be logged, based on logging levels, the `cnr.conf` file must be updated.

In addition, on Windows, event logging for Warnings and Errors is enabled by default (for Windows Event log). In this release, you can log more (or less) to the event log by changing the log settings.

The following `cnr.conf` configuration parameters are supported:

- `cnr.syslog.enable`—Specifies whether logging to Syslog server or Windows Event log is enabled for Prime IP Express servers.
 - To disable all logging, the value can be 0, off, or disabled.
 - To enable all logging, the value can be 1, on, or enabled.
 - By default, this parameter is disabled for Linux and enabled for Windows.
- `cnr.syslog.levels`—Specifies the severity levels to be logged to Syslog or Windows Event log. If Syslog is enabled, this defaults to warning and error. The value can be a case-blind, comma separated, list of the following keywords: error, warning, info, activity, and debug. This parameter is ignored if Syslog is disabled.



Note

While it is possible to enable all of the severity levels and thus all messages written to the server log files are also logged to Syslog, this is not recommended unless the server log settings are reviewed and minimized. The performance impact on Syslog and the servers may vary greatly depending on how logging is configured. Syslog may rate limit the messages, so useful messages may also be lost.

- `cnr.syslog.facility`—Specifies the facility under which Syslog logs (Linux OS). This parameter is ignored for Windows. The valid facility keywords are `daemon` (the default), `local0`, `local1`, `local2`, `local3`, `local4`, `local5`, `local6`, `local7`.



Note

- These parameters apply to all Cisco Prime IP Express servers (`cnrservagt`, `ccm`, `cdns`, `cnrsnmp`, `dns`, and `dhcp`).
- To apply any change to the `cnr.conf` parameters, Cisco Prime IP Express must be restarted.

The following `cnr.conf` configuration parameters allow server-specific overrides of the above parameters. `server` is one of `cnrservagt`, `ccm`, `cdns`, `cnrsnmp`, `dns`, and `dhcp`.

- `cnr.syslog.server.enable`—Specifies whether Syslog or Windows Event logging is enabled for the specified server (`cnr.syslog.enable` is ignored for that server).
- `cnr.syslog.server.levels`—Specifies the severity levels for the specified server (`cnr.syslog.levels` is ignored for that server).
- `cnr.syslog.server.facility`—Specifies the Syslog facility for the specified server (`cnr.syslog.facility` is ignored for that server).

The server specific configuration value is used, if specified. Otherwise, all parameters of the server are used. For example, to enable Syslog only for DHCP, add the following to the `cnr.conf` file:

```
cnr.syslog.dhcp.enable=1
```

To change the severity levels to include all non-debug logging (this assumes logging has been enabled for some or all servers), use:

```
cnr.syslog.enable=1
cnr.syslog.levels=error,warning,info,activity
```

To enable Syslog only for the DNS server:

```
cnr.syslog.dns.enable=1
cnr.syslog.dns.levels=error,warning,info,activity
```



Tip

Syntax or other errors in the `cnr.conf` parameters are not reported and are ignored (that is, if a levels keyword is mistyped, that keyword is ignored). Therefore, if a configuration change does not work, check if the parameter(s) have been specified correctly.

Troubleshooting Server Failures

The server agent processes (`nwreglocal` and `nwregregion`) normally detect server failures and restart the server. You can usually recover from the failure and the server is not likely to fail again immediately after restarting.

On rare occasions, the source of the server failure prevents the server from successfully restarting, and the server fails again as soon as it restarts. In such instances, perform the following steps:

-
- Step 1** If the server takes a significantly long time to restart, stop and restart the server agent. On:
- Windows:


```
net stop nwreglocal or nwregregion
net start nwreglocal or nwregregion
```
 - Linux:


```
/etc/rc.d/init.d/nwreglocal stop or nwregregion stop
/etc/rc.d/init.d/nwreglocal start or nwregregion start
```
- Step 2** Keep a copy of all the log files. Log files are located in the *install-path* /logs directory on Linux, and the *install-path* \logs folder on Windows. The log files often contain useful information that can help isolate the cause of a server failure.
- Step 3** Use the TAC tool, as described in [Using the TAC Tool, on page 160](#), or save the core or user.dmp file, if one exists, depending on the operating system:
- **Windows**—The user.dmp file is located in the system directory, which varies depending on the Windows system. Search for this file and save a renamed copy.
 - **Linux**—The core file is located in the *install-path* . Save a renamed copy of this file that Cisco PrimeIP Express does not overwrite.
- Step 4** On Windows, use the native event logging application to save the System and Application event logs to files. You can do this from the Event Viewer. These event logs often contain data that helps debug Cisco Prime IP Express server problems. For a description of the log messages for each server module, see the *install-path* /docs/msgid/MessageIdIndex.html file.
-

Linux Troubleshooting Tools

You can also use the following commands on Linux systems to troubleshoot Cisco Prime IP Express. To:

- See all Cisco Prime IP Express processes:


```
ps -leaf | grep nwr
```
- Monitor system usage and performance:


```
top
vmstat
```
- View login or bootup errors:
 - On Linux—`grep /var/log/messages*`
- View the configured interfaces and other network data:


```
ifconfig -a
```

Using the TAC Tool

There may be times when any amount of troubleshooting steps will not resolve your problem and you have to resort to contacting the Cisco Technical Assistance Center (TAC) for help. Cisco Prime IP Express provides a tool so that you can easily assemble the server or system error information, and package this data for TAC support engineers. This eliminates having to manually assemble this information with TAC assistance. The resulting package from this tool provides the engineers enough data so that they can more quickly and easily diagnose the problem and provide a solution.

The **cnr_tactool** utility is available in the bin directory of the Windows, and usrbin directory of the UNIX or Linux, installation directories. Execute the **cnr_tactool** utility:

```
> cnr_tactool -N username -P password [-d output-directory]
```

The output directory is optional and normally is the temp directory of the installation directories (in the /var path on Linux). If you do not supply the username and password on the command line, you are prompted for them:

```
> cnr_tactool
```

```
username:
password:
[processing messages....]
```

The tool generates a packaged tar file whose name includes the date and version. The tar file contains all the diagnostic files.



Backup and Recovery

This chapter explains how to maintain the Cisco Prime IP Express databases.

- [Backing Up Databases, page 161](#)
- [Syntax and Location, page 162](#)
- [Backup Strategy, page 162](#)
- [Backing Up CNRDB Data, page 164](#)
- [Database Recovery Strategy, page 165](#)
- [Virus Scanning While Running Cisco Prime IP Express, page 168](#)
- [Troubleshooting Databases, page 168](#)

Backing Up Databases

Because the Cisco Prime IP Express databases do a variety of memory caching and can be active at any time, you cannot rely on third-party system backups to protect the database. They can cause backup data inconsistency and an unusable replacement database.

For this purpose, Cisco Prime IP Express provides a shadow backup utility, `cnr_shadow_backup`. Once a day, at a configurable time, Cisco Prime IP Express takes a snapshot of the critical files. This snapshot is guaranteed to be a consistent view of the databases.

Related Topics

- [Syntax and Location, on page 162](#)
- [Backup Strategy, on page 162](#)
- [Database Recovery Strategy, on page 165](#)
- [Backing Up CNRDB Data, on page 164](#)
- [Backing Up All CNRDBs Using tar or Similar Tools, on page 165](#)
- [Recovering CNRDB Data from Backups, on page 167](#)
- [Recovering All CNRDBs Using tar or Similar Tools, on page 167](#)

[Recovering Single CNRDB from tar or Similar Tools, on page 168](#)

[Virus Scanning While Running Cisco Prime IP Express, on page 168](#)

Syntax and Location

Be sure to understand that the notation “.../data/db” in the following sections refers to directories in the Cisco Prime IP Express product data location path, depending on the operating system:

- **Windows**—“.../data” means the data directory, which by default is `C:\IPExpress\{Local | Regional}\data`.
- **Linux**—“.../data” means the data directory, which by default is `/var/nwreg2/{local | regional}/data`.

Cisco Prime IP Express database utility programs mentioned in the following sections are located in the “.../bin” directory, which you run as its full path name:

- **Windows**—“.../bin/*program*” means the program file in the bin directory, which by default is `C:\Program Files\Cisco Prime IP Express\{Local | Regional}\bin\program` for a 32-bit OS and `C:\Program Files (x86)\Cisco Prime IP Express\{Local | Regional}\bin\program` for a 64-bit OS.
- **Linux**—“.../bin/*program*” means the program file in the bin directory, which by default is `/opt/nwreg2/local/usrbin/program` or `/opt/nwreg2/regional/usrbin/program`.



Note

Use only the approved utilities for each type of database. In Windows, if you want to run the utility from outside the installed path, you must set the CNR_HOME environment variable.

Backup Strategy

The backup strategy involves either:

- Making CCM perform a nightly shadow backup for you (See the [Setting Automatic Backup Time, on page 163](#)) and using the shadow backups for permanent backup and then doing an explicit backup - either using the `cnr_shadow_backup` utility and backing up the backup files (*.bak DBs) or

Shutting down Cisco Prime IP Express and performing a backup using TAR or other similar tools.

Manual Backup (Using `cnr_shadow_backup` utility)

Use the `cnr_shadow_backup` utility to back up the following databases:

- **CNRDB databases**—...data/dhcp, ...data/dns/csetdb, ...data/dns/rrdb, ...data/cdns, ...data/leasehist, ...data/lease6hist, ...data/subnetutil, ...data/mcd, ...data/replica, and ...data/ccm/ndb

**Note**

If you change the location of the data directory, you must edit the **cnr.conf** file, which is located in `.../conf` (see [Modifying the cnr.conf File](#), on page 156). Change the **cnr.datadir** variable to the full path to the data directory. For example, the following is the default value on Windows:

cnr.datadir=C:\\IPExpress\\{Local|Regional}\\data

The most basic component of a backup strategy is the daily shadow backup. When problems occur with the operational database, you might need to try recovering based on the shadow backup of the previous day. Therefore, you must recognize and correct any problems that prevent a successful backup.

The most common problem is disk space exhaustion. To get a rough estimate of disk space requirements, take the size of the `.../data` directory and multiply by 10. System load, such as usage patterns, application mix, and the load on Cisco Prime IP Express itself, may dictate that a much larger reserve of space be available.

You should regularly archive existing shadow backups (such as to tape, other disks, or other systems) to preserve them for possible future recovery purposes.

**Caution**

Using a utility on the wrong type of database other than the one recommended can cause database corruption. Use only the utilities indicated. Also, never use the database utilities on the operational database, only on a copy.

Related Topics

[Setting Automatic Backup Time](#), on page 163

[Performing Manual Backups](#), on page 163

[Using Third-Party Backup Programs with cnr_shadow_backup](#), on page 164

Setting Automatic Backup Time

You can set the time at which an automatic backup should occur by editing the **cnr.conf** file (in `.../conf`). Change the **cnr.backup-time** variable to the hour and minute of the automatic shadow backup, in 24-hour *HH:MM* format, then restart the server agent. For example, the following is the preset value:

cnr.backup-time=23:45

Performing Manual Backups

You can also initiate a manual backup with the `cnr_shadow_backup` utility, which requires root privileges. Enter the `cnr_shadow_backup` command at the prompt to perform the backup.

**Note**

To restore DHCP data from a failover partner that is more up to date than a backup, see [Restoring DHCP Data from a Failover Server](#), on page 175.

Using Third-Party Backup Programs with `cnr_shadow_backup`

You should avoid scheduling third-party backup programs while `cnr_shadow_backup` is operating. Third-party backup programs should be run either an hour earlier or later than the `cnr_shadow_backup` operation. As described in [Setting Automatic Backup Time, on page 163](#), the default shadow backup time is daily at 23:45.

Configure third-party backup programs to skip the Cisco Prime IP Express operational database directories and files, and to back up only their shadow copies.

The operational files are listed in [Backup Strategy, on page 162](#). On Linux, Cisco Prime IP Express also maintains lock files in the following directories:

- Cisco Prime IP Express server processes—`/var/nwreg2/local/temp/np_destiny_trampoline` or `/var/nwreg2/regional/temp/np_destiny_trampoline`

The lock files are recreated during a reboot. These files are important while a system is running. Any maintenance process (such as virus scanning and archiving) should exclude the temporary directories, operational database directories, and files.

Windows does not maintain lock files, but uses named-pipes instead.

Backing Up CNRDB Data

In the case of the CNRDB databases, the `cnr_shadow_backup` utility copies the database and all log files to a secondary directory in the directory tree of the installed Cisco Prime IP Express product. For:

- **DHCP**—The operational database is in the `.../data/dhcp/ndb` and `.../data/dhcp/clientdb` directories, with the log files in the `.../data/dhcp/ndb/logs` directory. The shadow copies are in the `.../data/dhcp.bak/ndb` directory.
- **DNS**—The operational database is in the `.../data/dns/rddb` directory. The important operational components are the High-Availability (HA) DNS is in the `.../data/dns/hadb` directory, with log files in the `.../data/dns/hadb/logs` directory. The shadow copies are in the `.../data/dns.bak` directory.
- **CDNS**—The operational database is in the `.../data/cdns` directory. The shadow copies are in the `.../data/cdns.bak` directory.
- **CCM**—The operational database and log files are in the `.../data/ccm/ndb` directory. The shadow copies are in the `.../data/ccm.bak` directory.
- **MCD change log**—The operational database and log files are in the `.../data/mcd/ndb` directory. The shadow copies are in the `.../data/mcd.bak` directory. MCD Change Log database may not exist if there are no change log entries. Also, the database is deleted when the MCD change log history is trimmed or when there is no MCD change log data to begin with.
- **Lease history**—The operational database and log files are in the `.../data/leasehist` and `.../data/lease6hist` directories. The shadow copies are in the `.../data/leasehist.bak` and `.../data/lease6hist.bak` directories.
- **Subnet utilization**—The operational database and log files are in the `.../data/subnetutil` directory. The shadow copies are in the `.../data/subnetutil.bak` directory.
- **Replica**—The operational database and log files are in the `.../data/replica` directory.

The actual file naming convention is:

- **Database**—dhcp.ndb and dns.ndb.
- **Log files**—log.0000000001 through log.9999999999. The number of files varies with the rate of change to the server. There are typically only a small number. The specific filename extensions at a site vary over time as the database is used. These log files are not humanly readable.

Backing Up All CNRDBs Using tar or Similar Tools

This section describes the procedure for backing up all Cisco Prime IP Express databases using tar or similar tools.

-
- Step 1** Shut down Cisco PrimeIP Express.
Backups cannot be done using tar or similar tools if Cisco Prime IP Express is running.
- Step 2** Back up the entire data directory and subdirectories:
- ```
> /var/nwreg2/local/data or /var/nwreg2/regional/data
> /opt/nwreg2/*/conf
```
- Step 3** Restart Cisco PrimeIP Express when the backup is complete.
- Note** Technically the backups do not need to include the \*.bak directories (and subdirectories of those directories) as those contain nightly shadow backups. However, unless your available storage space is severely limited, we recommend a full backup of the entire data directory (and subdirectories) including the shadow backups.
- 

## Database Recovery Strategy

Cisco Prime IP Express uses the CNRDB database. The following table lists the types of CNRDB database that must be backed up and recovered.

**Table 24: Cisco Prime IP Express Databases for Recovery**

| Subdirectory | Cluster         | Type  | Description                                                                                                          |
|--------------|-----------------|-------|----------------------------------------------------------------------------------------------------------------------|
| ccm          | local, regional | CNRDB | Central Configuration Management database. Stores local centrally managed cluster and the SNMP server data.          |
| dns          | local           | CNRDB | DNS database. Stores zone state information, names of protected RRs, and zone configuration data for the DNS server. |

| Subdirectory   | Cluster  | Type  | Description                                                                                                                                                    |
|----------------|----------|-------|----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| cdns           | local    | CNRDB | Caching DNS database. Stores the initial DNSSEC root trust anchor and root hints.                                                                              |
| dhcp           | local    | CNRDB | DHCP database. Stores lease state data for the DHCP server.                                                                                                    |
| dhcpeventstore | local    |       | Queue that Cisco Prime IP Express maintains to interact with external servers, such as for LDAP and DHCPv4 DNS Update interactions. Recovery is not necessary. |
| replica        | regional | CNRDB | Stores replica data for the local clusters.                                                                                                                    |
| lease6hist     | regional | CNRDB | DHCPv6 lease history database.                                                                                                                                 |
| leasehist      | regional | CNRDB | DHCPv4 lease history database.                                                                                                                                 |

The general approach to recovering a Cisco Prime IP Express installation is:

- 1 Stop the Cisco Prime IP Express server agent.
- 2 Restore or repair the data.
- 3 Restart the server agent.
- 4 Monitor the server for errors.

After you are certain that you executed a successful database recovery, always manually execute the `cnr_shadow_backup` utility to make a backup of the current configuration and state.

## Recovering CNRDB Data from Backups

If there are any indications, such as server log messages or missing data, that database recovery was unsuccessful, you may need to base a recovery attempt on the current shadow backup (in the Cisco Prime IP Express installation tree). To do this:

- 
- Step 1** Stop the Cisco PrimeIP Express server agent.
- Step 2** Move the operational database files to a separate temporary location.
- Step 3** Copy each `../data/name .bak` directory to `../data/name` ; for example, copy `../data/ccm.bak` to `../data/ccm`.  
**Note** If you set the `cnr.dbrecover` variable to `false` in the `cnr.conf` file to disable recovery during the `cnr_shadow_backup` nightly backup, you must also do a recovery as part of these steps.
- Step 4** Rename the files.  
 The CNRDB database maintains centrally managed configuration data that is synchronized with the server configuration databases.
- Step 5** Create a new data directory and then untar or recover the backed up directory.  
 We recommend that you run the DB directory and recovery tools to ensure that the databases are good.  
**Note** Ensure that the logs subdirectory is present in the same directory or the logs path is mentioned in the `DB_CONFIG` file.
- Step 6** Restart the server agent.  
**Note** If the recovery fails, perhaps because the current shadow backup is simply a copy of corrupted files, use the most recent previous shadow backup. This illustrates the need to regularly archive shadow backups. You cannot add operational log files to older shadow backup files. All data added to the database since the shadow backup was made will be lost.  
 After a successful database recovery, initiate an immediate backup and archive the files using the `cnr_shadow_backup` utility (see [Performing Manual Backups](#), on page 163).
- 

## Recovering All CNRDBs Using tar or Similar Tools

This section describes the procedure for recovering all Cisco Prime IP Express databases using tar or similar tools.

- 
- Step 1** Shut down Cisco PrimeIP Express.
- RHEL/CentOS 6.x:  
`/etc/init.d/nwreglocal stop`
  - RHEL/CentOS 7.x:  
`systemctl stop nwreglocal`
  - Windows:  
`net stop nwreglocal`
- Step 2** Rename the active data directory (such as `mv data old-data`).
- Note** You must have sufficient disk space for twice the size of the data directory (and all the files in it and its subdirectories). If you do not have sufficient disk space, move the active data directory to another drive.

- Step 3** Create a new data directory and then untar or recover the backed up directory.  
We recommend that you run the CNRDB directory and recovery tools to ensure that the databases are good.
- Step 4** Start Cisco PrimeIP Express.
- Note** Technically the restores do not need to include the \*.bak directories (and subdirectories of those directories) as those contain nightly shadow backups. However, unless your available storage space is severely limited, we recommend a full restore of the entire data directory (and subdirectories) including the shadow backups.
- 

## Recovering Single CNRDB from tar or Similar Tools

This section describes the procedure for recovering single database using tar or similar tools.

- 
- Step 1** Shut down Cisco PrimeIP Express.
- RHEL/CentOS 6.x:  
`/etc/init.d/nwreglocal stop`
  - RHEL/CentOS 7.x:  
`systemctl stop nwreglocal`
  - Windows:  
`net stop nwreglocal`
- Step 2** Rename the active data directory (such as `mv data old-data`).
- Note** You must have sufficient disk space for twice the size of the data directory (and all the files in it and its subdirectories). If you do not have sufficient disk space, move the active data directory to another drive.
- Step 3** Create a new data directory and then untar or recover only the files in that directory (and its subdirectories) from the backup.  
We recommend that you run the CNRDB integrity and recovery tools to ensure that the CNRDB are good.
- Step 4** Repeat **Step 2** to **Step 3** for other DBs that have to be recovered.
- Step 5** Start Cisco PrimeIP Express.
- 

## Virus Scanning While Running Cisco Prime IP Express

If you have virus scanning enabled on your system, it is best to configure it to exclude certain Cisco Prime IP Express directories from being scanned. Including these directories might impede Cisco Prime IP Express operation. The ones you can exclude are the `.../data`, `.../logs`, and `.../temp` directories and their subdirectories.

## Troubleshooting Databases

The following sections describe troubleshooting the Cisco Prime IP Express databases.



## Related Topics

[Using the cnr\\_exim Data Import and Export Tool, on page 169](#)

[Using the cnrdb\\_recover Utility, on page 171](#)

[Using the cnrdb\\_verify Utility, on page 172](#)

[Using the cnrdb\\_checkpoint Utility, on page 173](#)

[Using the cnrdb\\_util Utility, on page 173](#)

[Restoring DHCP Data from a Failover Server, on page 175](#)

## Using the cnr\_exim Data Import and Export Tool

The cnr\_exim data import and export tool now supports the following for a user :

- Exporting all the data
- Exporting and importing license related data
- Importing all of the data

The cnr\_exim tool also serves to export unprotected resource record information. However, cnr\_exim simply overwrites existing data and does not try to resolve conflicts.



### Note

You cannot use cnr\_exim tool for import or export of data from one version of Cisco Prime IP Express to another. It can be used only for import or export of data from or to the same versions of Cisco Prime IP Express.

Before using the cnr\_exim tool, exit from the CLI, then find the tool on:

- **Windows**—...\bin\cnr\_exim.exe
- **Linux**—.../usrbin/cnr\_exim

You must reload the server for the imported data to become active.

Note that text exports are for reading purposes only. You cannot reimport them.

The text export prompts for the username and password (the cluster defaults to the local cluster). The syntax is:

```
> cnr_exim -e exportfile [-N username -P password -C cluster]
```

To export (importable) raw data, use the **-x** option:

```
> cnr_exim -e exportfile -x
```

To export DNS server and zone components as binary data in raw format, use the **-x** and **-c** options:

```
> cnr_exim -e exportfile -x -c "dnsserver,zone"
```

The data import syntax is (the import file must be in raw format):

```
> cnr_exim -i importfile [-N username -P password -C cluster]
```

You can also overwrite existing data with the **-o** option:

```
> cnr_exim -i importfile -o
```

The following table describes all the qualifying options for the `cnr_exim` tool.

**Table 25: `cnr_exim` Options**

| Option                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
|---------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>-a</b> <i>value</i>          | Allows exporting and importing of protected or unprotected RRs. Valid <i>values</i> are:<br><br><b>protectedRR unprotectedRR</b><br>On export or import, all RRs are exported by default, so you must use a value to export or import just the protected or unprotected RRs.                                                                                                                                                                                                                                                                                           |
| <b>-c</b> " <i>components</i> " | Imports or exports Cisco Prime IP Express components, as a quoted, comma-delimited string. Use <b>-c help</b> to view the supported components. User are not exported by default; you must explicitly export them using this option, and they are always grouped with their defined groups and roles. Secrets are never exported.<br><br><b>Note</b> After you import administrator names, you must set new passwords for them. If you export groups and roles separately from usernames (which are not exported by default), their relationship to usernames is lost. |
| <b>-C</b> <i>cluster</i>        | Imports from or exports to the specified cluster. Preset to <b>localhost</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>-e</b> <i>exportfile</i>     | Exports the configuration to the specified file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>-h</b>                       | Displays help text for the supported options.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>-i</b> <i>importfile</i>     | Imports the configuration to the specified file. The import file must be in raw format.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <b>-N</b> <i>username</i>       | Imports or exports using the specified username.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>-o</b>                       | When used with the <b>-i</b> (import) option, overwrites existing data.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <b>-p</b> <i>port</i>           | Port used to connect to the SCP server.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <b>-P</b> <i>password</i>       | Imports or exports using the specified password.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <b>-t</b> <i>exportfile</i>     | Specifies a file name to export to, exports data in s-expression format.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |

| Option    | Description                                                                                                                                                                                                                                                     |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>-v</b> | Displays version information                                                                                                                                                                                                                                    |
| <b>-x</b> | When used with the <b>-e</b> (export) option, exports binary data in (importable) raw format.                                                                                                                                                                   |
| <b>-d</b> | Specifies the directory path of cnr_exim log file.                                                                                                                                                                                                              |
| <b>-b</b> | Specifies that the core (base) objects are to be included in the import/export.                                                                                                                                                                                 |
| <b>-w</b> | Specifies the view tag to export. This option allows the user to export zone and RRs data which has the same view tag as mentioned in “w” option. All other objects will not take this option into consideration and will be exported as earlier if it is used. |

## Using the cnrdb\_recover Utility

The **cnrdb\_recover** utility is useful in restoring the Cisco Prime IP Express databases to a consistent state after a system failure. You would typically use the **-c** and **-v** options with this command (The following table describes all of the qualifying options). The utility is located in the installation bin directory.

**Table 26: cnrdb\_recover Options**

| Option        | Description                                                                                                                                                                                                                                         |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>-c</b>     | Performs a catastrophic recovery instead of a normal recovery. It not only examines all the log files present, but also recreates the .ndb (or .db) file in the current or specified directory if the file is missing, or updates it if is present. |
| <b>-e</b>     | Retains the environment after running recovery, rarely used unless there is a DB_CONFIG file in the home directory.                                                                                                                                 |
| <b>-h dir</b> | Specifies a home directory for the database environment. By default, the current working directory is used.                                                                                                                                         |
| <b>-t</b>     | Recovers to the time specified rather than to the most current possible date. The time format is <code>[[CC]YY]MMDDhhmm[.ss]</code> (the brackets indicating optional entries, with the omitted year defaulting to the current year).               |
| <b>-v</b>     | Runs in verbose mode.                                                                                                                                                                                                                               |

| Option    | Description                                                          |
|-----------|----------------------------------------------------------------------|
| <b>-V</b> | Writes the library version number to the standard output, and exits. |

In the case of a catastrophic failure, restore a snapshot of all database files, along with all log files written since the snapshot. If not catastrophic, all you need are the system files at the time of failure. If any log files are missing, **cnrdb\_recover -c** identifies the missing ones and fails, in which case you need to restore them and perform the recovery again.

Use of the catastrophic recovery option is highly recommended. In this way, the recovery utility plays back all the available database log files in sequential order. If, for some reason, there are missing log files, the recovery utility will report errors. For example, the following gap in the log files listed:

```
log.0000000001
log.0000000053
```

results in the following error that might require you to open a TAC case:

```
db_recover: Finding last valid log LSN:file:1 offset 2411756
db_recover: log_get: log.0000000002: No such file or directory
db_recover: DBENV->open: No such for or directory
```

## Using the cnrdb\_verify Utility

The **cnrdb\_verify** utility is useful for verifying the structure of the Cisco Prime IP Express databases. The command requires a file parameter. Use this utility only if you are certain that there are no programs running that are modifying the file. The following table describes all its qualifying options. The utility is located in the installation bin directory. The syntax is described in the usage information when you run the command:

```
C:\Program Files\Cisco Prime IP Express\Local\bin>cnrdb_verify
```

```
usage: db_verify [-NoqV] [-h dir] [-P password] file
```

**Table 27: cnrdb\_verify Options**

| Option             | Description                                                                                                                                     |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>-h dir</b>      | Specifies a home directory for the database environment. By default, the current working directory is used.                                     |
| <b>-N</b>          | Prevents acquiring shared region locks while running, intended for debugging errors only, and should not be used under any other circumstances. |
| <b>-o</b>          | Ignores database sort or hash ordering and allows <b>cnrdb_verify</b> to be used on nondefault comparison or hashing configurations.            |
| <b>-P password</b> | User password, if the file is protected.                                                                                                        |

| Option | Description                                                                    |
|--------|--------------------------------------------------------------------------------|
| -q     | Suppresses printing any error descriptions other than exit success or failure. |
| -V     | Writes the library version number to the standard output, and exits.           |

## Using the cnrdb\_checkpoint Utility

The **cnrdb\_checkpoint** utility is useful in setting a checkpoint for the database files so as to keep them current. The utility is located in the installation bin directory. The syntax is described in the usage information when you run the command:

```
C:\Program Files\Cisco Prime IP Express\Local\bin>cnrdb_checkpoint ?usage: db_checkpoint
[-lVv] [-h home]
[-k kbytes] [-L file] [-P password] [-p min]
```

## Using the cnrdb\_util Utility

The **cnrdb\_util** utility is useful for dumping and loading CNRDB databases. In addition, you can use this utility to shadow backup and recover the CNRDB database, as well as to clear the log files.

The utility is located on the following directory:

- **Window** — *(installation directory)\bin\cnrdb\_util.bat*
- **Linux** — *(installation directory)/userbin/cnrdb\_util*



### Important

You must take a backup prior to performing any operation on CNRDB databases. If existing backup files are to be retained, they must be backed up before you run this utility.

The **cnrdb\_util** utility runs in two modes.

- **Interactive mode** - Prompts the user for input as data or commands.
- **Batch mode** - Requires information (both operation and options) as arguments while executing this utility.

The syntax is described in the usage information when you run the command:

```
nrcmd> cnrdb_util -h
```

The following tables describe all of the qualifying operations and options.

**Table 28: cnrdb\_util Operations**

| Operation | Description                       |
|-----------|-----------------------------------|
| -d        | Dumps one or all CNRDB databases. |
| -l        | Loads one or all CNRDB databases. |

| Operation | Description                                                  |
|-----------|--------------------------------------------------------------|
| -b        | Creates shadow backup of all CNRDB databases.                |
| -r        | Recovers one or all CNRDB databases from shadow backup.      |
| -c        | Cleans-up sleepycat log files in one or all CNRDB databases. |
| -h        | Displays help text for the supported options.                |



**Important** You can perform only one operation at a time.

**Table 29: cnrdb\_util Options**

| Option                                                                                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|----------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>-m</b><br>{ local   regional }                                                      | Specifies the CNRDB installation mode. If not specified, this utility gets this information from cnr.conf file. If this file is not found, local mode is used by default.                                                                                                                                                                                                                                                                                                                             |
| <b>-prog</b><br>path                                                                   | Specifies the path to dump, load, or shadow backup executable. If not specified, this utility derives the path based on CNRDB installation path. This option is not applicable for '-r' operation.                                                                                                                                                                                                                                                                                                    |
| <b>-db</b><br>db-path                                                                  | Specifies the path to databases to dump, load, or recover (includes subdirectories). If not specified, this utility derives the path based on CNRDB installation path. For backup operation, CNRDB installation path is used. This option is not applicable for '-b' operation.                                                                                                                                                                                                                       |
| <b>-n</b><br>{ ccm   dhcp   dns   mcd<br>  leasehist   replica  <br>subnetutil   all } | Specifies the name of the database to dump, load, or recover. If not specified, specific operation is performed on all databases present in the database path. Backup operation must not be performed on specific database, hence this option is not applicable for '-b' operation. <ul style="list-style-type: none"> <li>Valid options for local mode are { ccm   dhcp   dns   mcd   all }</li> <li>Valid options for regional mode are { ccm   leasehist   replica   subnetutil   all }</li> </ul> |
| <b>-s</b>                                                                              | Specifies that this utility needs to stop CNRDB Server Agent, if it is running, before performing any operations.                                                                                                                                                                                                                                                                                                                                                                                     |
| <b>-out</b><br>path                                                                    | Specifies the destination path for output database files. If not specified, this utility stores the output database files at the original database location. This option is not applicable for '-b' and '-c' operations.                                                                                                                                                                                                                                                                              |

The dump operation ensures the following:

- Each CNRBD database file is dumped to the specified location and the file name is appended with .dbdump.
- Skips CNRDB database files with file extension \*.bak (shadow backup).

## Restoring DHCP Data from a Failover Server

You can restore DHCP data from a failover server that is more current than the result of a shadow backup. Be sure that the failover partner configurations are synchronized, then, on the failover partner:

### On Windows

- 1 Set the default path; for example:  
`SET PATH=%PATH%;.;C:\PROGRA~1\NETWOR~1\LOCAL\BIN`
- 2 Stop the server agent:  
`net stop "IExpress Local Server Agent"`
- 3 Delete the eventstore, ndb, and logs directories:  
`del C:\IExpress\Local\data\dhcpeventstore\*.*`  
`del C:\IExpress\Local\data\dhcp\ndb\dhcp.ndb`  
`del C:\IExpress\Local\data\dhcp\ndb\logs\*.*`
- 4 Restart the server agent:  
`net start "IExpress Local Server Agent"`

### On Linux

- 1 Stop the server agent:
  - RHEL/CentOS 6.x:  
`/etc/init.d/nwreglocal stop`
  - RHEL/CentOS 7.x:  
`systemctl stop nwreglocal`
- 2 Determine the processes running:  
`/opt/nwreg2/local/usrbin/cnr_status`
- 3 Kill the remaining processes:  
`kill -9 pid`
- 4 Delete the eventstore, ndb, and logs directories:  
`rm /var/nwreg2/data/dhcpeventstore/*.*`  
  
`rm -r /var/nwreg2/data/dhcp/ndb/*`
- 5 Restart the server agent:
  - RHEL/CentOS 6.x:  
`/etc/init.d/nwreglocal start`
  - RHEL/CentOS 7.x:  
`systemctl start nwreglocal`







## Managing Reports

---

This chapter explains how to manage the Cisco Prime IP Express address space reporting tool, which is available from a regional cluster by using the web UI. Before you proceed with this chapter, become familiar with the concepts in the previous chapters of this part of the User's Guide.

- [ARIN Reports and Allocation Reports, page 177](#)
- [Managing ARIN Reports, page 178](#)
- [Managing IPv4 Address Space Utilization Reports, page 181](#)
- [Managing Shared WHOIS Project Allocation and Assignment Reports, page 182](#)
- [Managing BYOD Reports, page 183](#)
- [Registered Devices, page 183](#)
- [Scopes/Prefix , page 183](#)

### ARIN Reports and Allocation Reports

Using the Cisco Prime IP Express web UI, you can generate:

- American Registry of Internet Numbers (ARIN) reports, including:
  - Organization and point of contact (POC) reports
  - IPv4 address space utilization reports
  - Shared WHOIS project (SWIP) allocation and assignment reports
- Allocation reports that show how addresses are deployed across the routers and router interfaces of your network, including:
  - Allocation by owner reports
  - Allocation by router interface or by network reports

## Managing ARIN Reports

ARIN, which is one of the five Regional Internet Registries (RIRs), manages IP resources in Canada, the United States of America, and many Caribbean and North Atlantic islands.

ARIN allocates blocks of IP addresses to Internet Service Providers (ISPs), which, in turn, reassign blocks of address space to their customers. ARIN distinguishes between *allocating* IP address space and *assigning* IP address space. It allocates address space to smaller IRs for subsequent distribution to the IRs' members and customers. It assigns address space to an ISP, or other organization, for use only within the network of that organization and only for the purposes documented in its requests and reports to ARIN.



### Note

ARIN manages IP address resources under the auspices of the Internet Corporation for Assigned Names and Numbers (ICANN). In other geographies, ICANN has delegated authority for IP resources to different regional Internet Registries. Cisco Prime IP Express does not currently support the reports that these registries might require, nor does it now support IPv6 reports or autonomous system (AS) numbers.

ARIN maintains detailed documentation about its policies and guidelines on its website.

<http://www.arin.net>

Be sure that you are familiar with these policies and guidelines before proceeding with ARIN reports.

The three options that you can specify for ARIN reports are:

- **New**—For a newly added POC or organization.
- **Modify**—Includes changed POC or organization data, such as phone numbers and addresses.
- **Remove**—Signals that you want to remove the POC or organization from the ARIN database.

## Related Topics

[Managing Point of Contact and Organization Reports, on page 178](#)

[Managing IPv4 Address Space Utilization Reports, on page 181](#)

[Managing Shared WHOIS Project Allocation and Assignment Reports, on page 182](#)

## Managing Point of Contact and Organization Reports

Cisco Prime IP Express provides reports that can submit Points of Contact (POC) and organizational information to ARIN. After you fill in these reports, you need to e-mail the information to ARIN. Submit the POC report (also called a template) to ARIN before preparing other reports.

Each POC is uniquely identified by a name called a POC handle and is associated with one or more Organization Identifiers (Org IDs) or resource delegations, such as an IP address space allocation or assignment. A POC handle, which ARIN assigns, can represent either an individual or a role.

The Organization report creates an Org ID and associates POC records with it. Create the Organization report after you create the POC report.

To manage POC and organization reports, log into the Cisco Prime IP Express regional web UI as a member of an administrator group assigned to the regional-addr-admin role.

## Related Topics

[Creating a Point of Contact Report, on page 179](#)

[Registering a Point of Contact, on page 179](#)

[Editing a Point of Contact Report, on page 180](#)

[Creating an Organization Report, on page 180](#)

[Registering an Organization, on page 181](#)

[Editing an Organization Report, on page 181](#)

## Creating a Point of Contact Report

You create POCs so that managers can interact with ARIN to request and administer IP resources and so that network professionals can manage network operation issues.

### *Regional Web UI*

- 
- Step 1** From the **Administration** menu, choose **Contacts** under the **Settings** submenu to open the List ARIN Points of Contact page.
- Step 2** Click the **Add Contact** icon in the Contacts pane on the left, to open the Add Point of Contact page.
- Step 3** Enter data in the fields on the page:
- **Name**—A unique identifier for the POC (required).
  - **First Name**—The first name of the point of contact (required).
  - **Last Name**—The last name of the point of contact (required).
  - **Type**—From the drop-down list, choose Person or Role (optional, with preset value Person).
- Step 4** Click **Add Point of Contact**.
- 

## Registering a Point of Contact

You must register the POC with ARIN to receive a POC handle.

### *Regional Web UI*

- 
- Step 1** From the **Administration** menu, choose **Contacts** under the **Settings** submenu to open the List ARIN Points of Contact page.
- Step 2** Click the required contact in the Contacts pane on the left.
- Step 3** Click the **Register Report** tab to view the ARIN template file.
- Step 4** Copy and paste the template file into an e-mail and send the file to ARIN.
-

## Editing a Point of Contact Report

Edit a POC report after ARIN returns a POC handle to your organization or if your POC has changed.

### Regional Web UI

- 
- Step 1** From the **Administration** menu, choose **Contacts** under the **Settings** submenu to open the List ARIN Points of Contact page.
- Step 2** Click the required contact in the Contacts pane on the left. The Edit Point of Contact page opens.
- Step 3** Enter values for Middle Name, Handle, and Description (optional)
- Step 4** In the Poc Emails field:
- a) Enter the e-mail address for the POC.
  - b) Click **Add Email Address** to add additional e-mail addresses.
- Step 5** In the Poc Phones field:
- a) Enter a phone number and extension, if applicable, then choose a type (Office, Mobile, Fax, or Pager) from the drop-down list,
  - b) Click **Add Phone** to add additional telephones.
- Step 6** Miscellaneous Settings. Add these additional attributes as strings or lists of text.
- Step 7** After making the changes, click **Save**.
- 

## Creating an Organization Report

Each organization is represented in the ARIN WHOIS database by a unique Org ID, consisting of an organization name, its postal address, and its POCs. While organizations may have more than one Org ID, ARIN recommends consolidating IP address resources under a single Org ID.

If you do not have an Org ID with ARIN, or you are establishing an additional Org ID, you must first create and submit a POC report. When ARIN confirms it has received your POC information, use Cisco Prime IP Express to complete an Organization form and submit that information.

### Regional Web UI

- 
- Step 1** From the **Administration** menu, choose **Organizations** under the **Settings** submenu to open the List/Add ARIN Organizations page.
- Step 2** Click the **Add Organization** icon in the Organizations pane on the left, to open the Add Organization page.
- Step 3** Enter data in the fields on the page:
- **Organization Name**—Name of the organization that you want to register with ARIN.
  - **Description**—A text description of the organization.
  - **Organization Admin POC**—From the drop-down list, choose the POC who administers IP resources from the drop-down list.
  - **Organization Technical Points Of Contact**—From the drop-down list, choose one or more POCs who manage network operations, or click **Add Point of Contact** to add new contact information.

**Step 4** Click **Add Organization**. This opens the Edit Organization page where you can add more details.

---

### Registering an Organization

You must register your Organization with ARIN to receive an Organization ID.

*Regional Web UI*

- 
- Step 1** From the **Administration** menu, choose **Organizations** under the **Settings** submenu to open the List ARIN Organizations page.
- Step 2** Click the required organization in the Organizations pane on the left.
- Step 3** Click the **Register Report** tab to view the ARIN template file.
- Step 4** Copy and paste the template file into an e-mail and send the file to ARIN.
- 

### Editing an Organization Report

You might need to change organizational information that you have registered with ARIN.

*Regional Web UI*

- 
- Step 1** From the **Administration** menu, choose **Organizations** under the **Settings** submenu to open the List ARIN Organizations page.
- Step 2** Click the required organization in the Organizations pane on the left.
- Step 3** Enter or change data in the fields.
- **Miscellaneous Settings**—Add these additional attributes as strings or lists of text.
  - **Organization Abuse Points of Contact**—From the drop-down list, choose one or more POCs who handle network abuse complaints, or click **Add Point of Contact** to add new contact information.
  - **Organization NOC Points of Contact**—From the drop-down list, choose one or more POCs in network operations centers, or click **Add Point of Contact** to add new contact information.
- Step 4** Click **Save**.
- Step 5** Submit the updated report to ARIN as described in [Registering an Organization](#), on page 181.
- 

## Managing IPv4 Address Space Utilization Reports

Address space utilization reports serve two purposes:

- To make an initial request for IPv4 address space after you receive a POC handle and an Org ID.

- To support a request for an additional allocation of IPv4 addresses when your business projections show that you are running out of IP addresses.

**Note**

The ARIN website contains extensive information about how it initially allocates address space and its threshold criteria for requesting additional address space. In general, for a single-homed organization, the minimum allocation from ARIN is a /20 block of addresses. For a multihomed organization, the minimum allocation is a /22 block of addresses. ARIN recommends that an organization requiring a smaller block of addresses contact an upstream ISP to obtain addresses.

The Cisco Prime IP Express utilization report corresponds to the ARIN ISP Network Request template (ARIN-NET-ISP-3.2.2).

## Regional Web UI

- 
- |               |                                                                                                                                                                                                                                                                                               |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Step 1</b> | From the <b>Operate</b> menu, choose <b>ARIN Address Space Usage</b> under the <b>Reports</b> submenu to open the Select Address Space Report page.                                                                                                                                           |
| <b>Step 2</b> | In the Select the Report Type field, choose <b>Utilization</b> from the drop-down list. The Select the Filter Type field is updated with the value, <i>by-owner</i> . The browser redisplay the Select Address Space Report page with two new fields: Network Name and Network Prefix Length. |
| <b>Step 3</b> | In the Select Owner field, choose the owner of this address block from the drop-down list.                                                                                                                                                                                                    |
| <b>Step 4</b> | Enter values for the Network Name and Network Prefix Length.                                                                                                                                                                                                                                  |
| <b>Step 5</b> | Click <b>Generate Report</b> . The browser displays an ARIN template file (ARIN-NET-ISP-3.2.2). Several sections of the report require that you manually enter data because the information is generated and maintained outside the Cisco Prime IP Express application.                       |
| <b>Step 6</b> | Click <b>Save Report</b> . The browser displays the Address Space Utilization Report as an unformatted text file.                                                                                                                                                                             |
| <b>Step 7</b> | Copy the Address Space Utilization Report to a text editor to manually enter the data that Cisco Prime IP Express does not generate.                                                                                                                                                          |
| <b>Step 8</b> | Copy and paste the edited report into an e-mail and send the file to ARIN.                                                                                                                                                                                                                    |
- 

## Managing Shared WHOIS Project Allocation and Assignment Reports

The ARIN shared WHOIS project (SWIP) provides a mechanism for finding contact and registration information for resources registered with ARIN. The ARIN database contains IP addresses, autonomous system numbers, organizations or customers that are associated with these resources, and related POCs.

The ARIN WHOIS does not locate any domain- or military-related information. Use [whois.internic.net](http://whois.internic.net) to locate domain information, and [whois.nic.mil](http://whois.nic.mil) for military network information.

The regional web UI also provides two allocation and assignment report pages:

- View ARIN SWIP Reallocated Report
- View ARIN SWIP Reassigned Report

## Managing BYOD Reports

There are two types of BYOD reports:

- Registered Devices
- Scopes

## Registered Devices

Registered Device report displays the list of devices that are registered through BYOD web server. The report can be exported in the csv format. Only an admin user is allowed to delete a device using the Registered Device Report page.

### Registered Devices Report

To access the Registered Devices Report:

#### Regional Advanced or Expert Web UI

From the **Operate** menu choose **Registered Devices** in BYOD under **Reports** submenu to access the report in the List BYOD Registered Devices page.

LDAP server(s) configured to the BYOD web server or local DHCP server(s) or failover pairs, associated with the regional server will be listed in the clusters pane. All the registered devices in the LDAP server or devices registered in the local DHCP servers or failover pairs through the BYOD web server will be displayed in the List BYOD Registered Devices page.



#### Note

You must select the desired server from the cluster pane to view the corresponding registered devices report in the List BYOD Registered Devices page.

## Scopes/Prefix

Scope/Prefix report displays the list of scopes and prefixes that are used for BYOD. The report can be exported in the csv format.

### Scope/Prefix Report

To view the Scope/Prefix Report:

#### Regional Advanced or Expert Web UI

From the **Operate** menu choose **Scopes/Prefix** in BYOD under **Reports** submenu to view the report in the List BYOD Scope/Prefix page.

Local DHCP server(s) or failover pairs associated with the regional server will be listed in the clusters pane. All the scopes and prefixes created in the local DHCP servers or failover pairs for the BYOD web server will be displayed in the List BYOD Scope/Prefix page.

**Note**

You must select the desired server from the cluster pane to view the corresponding scopes and prefixes created during BYOD setup in the List BYOD Scope/Prefix page.





## PART

# Virtual Appliance

- [Introduction to Cisco Prime IP Express Virtual Appliance, page 187](#)





## Introduction to Cisco Prime IP Express Virtual Appliance

---

The Cisco Prime IP Express virtual appliance aims at eliminating the installation, configuration and maintenance costs associated with running Cisco Prime IP Express on a local system. It also guarantees portability and thus reduces the risk in moving Cisco Prime IP Express from one machine to another.

You must get a license of Cisco Prime IP Express virtual appliance, and download the virtual appliance from Cisco.com. Upon initializing the virtual appliance, you have to add the license file. Cisco Prime IP Express will then be up and running, available to be configured. This is applicable for both the local and regional appliance.

This is different from just downloading a copy of Cisco Prime IP Express and installing it on a server or virtual machine provided by the customer, in that the operating system on which Cisco Prime IP Express runs is also provided in the virtual appliance.

The Cisco Prime IP Express virtual appliance supports VMware ESXi 5.0 or later platforms.

To know about the difference between vApp and a virtual appliance, see the *User's Guide to Deploying vApps and Virtual Appliances*.

- [How the Cisco Prime IP Express Virtual Appliance Works, page 187](#)
- [Invoking Cisco Prime IP Express on the Virtual Appliance, page 188](#)
- [Monitoring Disk Space Availability, page 188](#)
- [Increasing the Size of Disk, page 189](#)
- [Troubleshooting, page 190](#)

## How the Cisco Prime IP Express Virtual Appliance Works

The virtual appliance consists of a virtual machine in the OVF format, which contains a runnable guest OS (CentOS 7.4 in CPIPE 8.3.6 and CentOS 6.x in pre-8.3.6 releases) and Cisco Prime IP Express installed on that OS. When the virtual appliance is installed, Cisco Prime IP Express is already installed and is started by the virtual machine power-up like in the case of any regular server power-up.

## How to Download the Cisco Prime IP Express Virtual Appliance

Do the following to download the Cisco Prime IP Express virtual appliance:

- 
- Step 1** You have to point the ESXi systems at a Cisco web-site and download an OVF format virtual appliance containing the guest operating system and a running version of Cisco PrimeIP Express and power up the virtual machine/appliance.
- Step 2** Set a root password for the virtual appliance when you are prompted to. There is no default password. For more details on deployment the virtual appliance and configuration on first boot, see *Cisco Prime IP Express Installation Guide* . Two virtual appliances will be created, one for a local Cisco Prime IP Express cluster and one for a regional cluster. Each of these will have the security kit installed.
- 

## Invoking Cisco Prime IP Express on the Virtual Appliance

You can invoke the Cisco Prime IP Express application directly by using the URL **http://hostname:8080**. The secure **https** connection is also available via the URL **https://hostname:8443**.

## Monitoring Disk Space Availability

To view the disk space availability, do the following:

- 
- Step 1** In the vSphere Client window, select the host/server on which the virtual Cisco Prime IP Express appliance resides.
- Step 2** Click **Storage Views** to see the list of the machines hosted by the server and the details about the space currently used by each machine.  
Also, you can go to the Virtual Machines tab to view both the **Provisioned Space** and the **Used Space** by machine.
- Step 3** Click **Summary**.  
The **Resources** area of the Summary tab, displays the capacity of the disk and the CPU and memory used.
- Step 4** Select the virtual machine and click the **Summary** tab.  
The **Resources** area of the Summary tab displays the disk space details for the machine.
-

## Monitoring Disk Space Availability (Using the Console)

To monitor the disk space availability using the console, do the following:

- 
- Step 1** Select the virtual machine in the vSphere Client window and either click the **Console** tab on the right pane or right-click the virtual machine name and choose **Open Console**.
- Step 2** Log in as root and type `df -k`. The disk space details are displayed.  
If the disk space on the disk mounted on `/var/nwreg2` is not enough, then you should increase the size of the disk (see [Increasing the Size of Disk](#), on page 189).
- 

## Increasing the Size of Disk

The `cnr_growfilesystem` script causes the data partition, `/dev/sdb1` to grow to be the size of the entire data disk. It is trivial to expand the size of the data disk that the operating system sees, using VMware. To ensure that the operating system recognizes the bigger disk, you have to restart the VM and run the `cnr_growfilesystem` after increasing the size of the disk.



### Note

Before running the `cnr_growfilesystem` script, ensure that you backup the entire `/var/nwreg2/` data and that it is not stored anywhere in the file system under `/var/nwreg2`. Running the `cnr_growfilesystem` script after restarting the VM ensures that the filesystem uses all the space in the partition.

If you need a bigger disk, do the following:

- 
- Step 1** Stop the VM.
- Step 2** Increase the size of the disk by changing the size in the Virtual Machine Properties window. To open the Virtual Machine Properties window, you have to select the host name, right-click, and choose Edit Settings.
- Step 3** Restart the VM. This ensures that the partition for the Cisco Prime IP Express data covers the entire disk.
- Step 4** After the VM is up and running, log in as the root user and run the `cnr_growfilesystem` script:

```
/opt/nwreg2/local/usrbin/cnr_growfilesystem
```

This script will:

- Stop Cisco PrimeIP Express
- Unmount the data partition
- Increase the size of the partition to be the size of the disk
- Turn the ext3 filesystem into an ext2 filesystem
- Expand the filesystem to be the size of the partition (which is now the size of the disk)
- Turn the ext2 filesystem back into an ext3 filesystem
- Remount the disk

## Troubleshooting

If you experience any issues while working with the Cisco Prime IP Express virtual appliance, we recommend you to do the following:

Examine the log files in `/var/nwreg2/{local | regional}/logs`. Look particularly for errors in the log files as these signal exceptional conditions. If you are unable to resolve the problem and you have purchased Cisco support, then submit a case to Cisco Technical Assistance Center (TAC) regarding the problem.



## Glossary

|                                         |                                                                                                                                                                                                                                                               |
|-----------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>A</b>                                |                                                                                                                                                                                                                                                               |
| <b>A record</b>                         | DNS Address resource record (RR). Maps a hostname to its address and specifies the Internet Protocol address (in dotted decimal form) of the host. There should be one A record for each host address.                                                        |
| <b>access control list (ACL)</b>        | DHCP mechanism whereby the server can allow or disallow the request or action defined in a packet. <i>See also</i> <a href="#">transaction signature (TSIG)</a> .                                                                                             |
| <b>address block</b>                    | Block of IP addresses to use with DHCP subnet allocation that uses on-demand address pools.                                                                                                                                                                   |
| <b>admin</b>                            | Default name of the superuser or global administrator.                                                                                                                                                                                                        |
| <b>administrator</b>                    | User account to adopt certain functionality, be it defined by role, constrained role, or group.                                                                                                                                                               |
| <b>alias</b>                            | Pointer from one domain name to the official (canonical) domain name.                                                                                                                                                                                         |
| <b>allocation priority</b>              | An alternate method of control over allocating addresses among scopes other than the default round-robin method.                                                                                                                                              |
| <b>ARIN</b>                             | American Registry of Internet Numbers, one of several regional Internet Registries (IRs), manages IP resources in North America, parts of the Caribbean, and subequatorial Africa. Cisco Prime IP Express provides an address space report for this registry. |
| <b>Asynchronous Transfer Mode (ATM)</b> | International standard for cell relay in which multiple service types (such as voice, video, or data) are conveyed in fixed-length (53-byte) cells.                                                                                                           |
| <b>authoritative name server</b>        | DNS name server that possesses complete information about a zone.                                                                                                                                                                                             |
| <b>AXFR</b>                             | Full DNS zone transfer. <i>See also</i> <a href="#">zone transfer</a> and <a href="#">IXFR</a> .                                                                                                                                                              |

|                                             |                                                                                                                                                                                                                                                                              |
|---------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>B</b>                                    |                                                                                                                                                                                                                                                                              |
| <b>Berkeley Internet Name Domain (BIND)</b> | Implementation of the Domain Name System (DNS) protocols. <i>See also</i> <a href="#">DNS</a> .                                                                                                                                                                              |
| <b>binding</b>                              | Collection of DHCP client options and lease information, managed by the main and backup DHCP servers. A binding database is a collection of configuration parameters associated with all DHCP clients. This database holds configuration information about all the datasets. |
| <b>BOOTP</b>                                | Bootstrap Protocol. Used by a network node to determine the IP address of its Ethernet interfaces, so that it can affect network booting.                                                                                                                                    |

|                                                        |                                                                                                                                                                                                                         |
|--------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>C</b>                                               |                                                                                                                                                                                                                         |
| <b>cable modem termination system (CMTS)</b>           | Cable modem termination system. Either a router or bridge, typically at the cable head end.                                                                                                                             |
| <b>cache</b>                                           | Data stored in indexed disk files to reduce the amount of physical memory.                                                                                                                                              |
| <b>caching name server</b>                             | Type of DNS server that caches information learned from other name servers so that it can answer requests quickly, without having to query other servers for each transaction.                                          |
| <b>canonical name</b>                                  | Another name for an alias DNS host, inherent in a CNAME resource record (RR).                                                                                                                                           |
| <b>case sensitivity</b>                                | Values in Cisco Prime IP Express are not case-sensitive, with the exception of passwords.                                                                                                                               |
| <b>Central Configuration Management (CCM) database</b> | Main database for the Cisco Prime IP Express web-based user interface (web UI).                                                                                                                                         |
| <b>chaddr</b>                                          | DHCP client hardware (MAC) address. Sent in an RFC 2131 packet between the client and server.                                                                                                                           |
| <b>change logs, changesets</b>                         | A change log is a group of changesets made to the Cisco Prime IP Express databases due to additions, modifications or deletions in the web UI. A changeset is a set of changes made to a single object in the database. |
| <b>ciaddr</b>                                          | DHCP client IP address. Sent in an RFC 2131 packet between the client and server.                                                                                                                                       |



|                         |                                                                                                                                                                                                                                                                                                    |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>class of address</b> | Category of an IP address that determines the location of the boundary between network prefix and host suffix. Internet addresses can be A, B, C, D, or E level addresses. Class D addresses are used for multicasting and are not used on hosts. Class E addresses are for experimental use only. |
| <b>client-class</b>     | Cisco PrimeIP Express feature that provides differentiated services to users that are connected to a common network. You can thereby group your user community based on administrative criteria, and then ensure that each user receives the appropriate class of service.                         |
| <b>cluster</b>          | In Cisco Prime IP Express, a group of DNS, and DHCP servers that share the same database.                                                                                                                                                                                                          |
| <b>CNAME record</b>     | DNS Canonical Name resource record (RR). Used for nicknames or aliases. The name associated with the resource record is the nickname. The data portion is the official or canonical name.                                                                                                          |
| <b>CNRDB</b>            | Name of one of the Cisco Prime IP Express internal databases. The other is changeset database.                                                                                                                                                                                                     |
| <b>constraint</b>       | Assigned limitation on the role or allowable functionality of an administrator.                                                                                                                                                                                                                    |

|                                                                 |                                                                                                                                                                                                                                                                                                                                                            |
|-----------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>D</b>                                                        |                                                                                                                                                                                                                                                                                                                                                            |
| <b>Data Over Cable Service Interface Specification (DOCSIS)</b> | Data Over Cable Service Interface Specification. Standard created by cable companies in 1995 to work toward an open cable system standard and that resulted in specifications for connection points, called interfaces.                                                                                                                                    |
| <b>delegation</b>                                               | Act of assigning responsibility for managing a DNS subzone to another server, or of assigning DHCP address blocks to local clusters.                                                                                                                                                                                                                       |
| <b>DHCP</b>                                                     | Dynamic Host Configuration Protocol. Designed by the Internet Engineering Task Force (IETF) to reduce the amount of configuration that is required when using TCP/IP. DHCP allocates IP addresses to hosts. It also provides all the parameters that hosts require to operate and exchange information on the Internet network to which they are attached. |
| <b>Digital Subscriber Line (DSL)</b>                            | Public network technology that delivers high bandwidth over conventional copper wiring at limited distances.                                                                                                                                                                                                                                               |

|                                |                                                                                                                                                                                                                                                                                |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>DNS</b>                     | Domain Name System. Handles the growing number of Internet users. DNS translates names, such as www.cisco.com, into Internet Protocol (IP) addresses, such as 192.168.40.0, so that computers can communicate with each other.                                                 |
| <b>DNS update</b>              | Protocol ( RFC 2136) that integrates DNS with DHCP.                                                                                                                                                                                                                            |
| <b>domain</b>                  | Portion of the DNS naming hierarchy tree that refers to general groupings of networks based on organization type or geography. The hierarchy is root, top- or first-level, and second-level domain.                                                                            |
| <b>domain name</b>             | DNS name that can be either absolute or relative. An absolute name is the fully qualified domain name (FQDN) and is terminated with a period. A relative name is relative to the current domain and does not end with a period.                                                |
| <b>dotted decimal notation</b> | Syntactic representation of a 32-bit integer that consists of four eight-bit numbers written in base 10 with dots separating them for a representation of IP addresses. Many TCP/IP application programs accept dotted decimal notation in place of destination machine names. |

|                                      |                                                                                                                                                                                                                |
|--------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>E</b>                             |                                                                                                                                                                                                                |
| <b>expression</b>                    | Construct commonly used in the Cisco Prime IP Express DHCP implementation to create client identities or look up clients. For example, an expression can be used to construct a scope from a template.         |
| <b>extension and extension point</b> | In Cisco Prime IP Express, element of a script written in TCP, C, or C++ that customizes handling DHCP packets as the server processes them, and which supports additional levels of customizing DHCP clients. |

|                 |                                                                                                                                                                                                                                                                                                            |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>F</b>        |                                                                                                                                                                                                                                                                                                            |
| <b>failover</b> | Cisco PrimeIP Express feature (as described in RFC 2131) that provides for multiple, redundant DHCP servers, whereby one server can take over in case of a failure. DHCP clients can continue to keep and renew their leases without needing to know or care which server is responding to their requests. |

|                         |                                                                                                                                                                 |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>forwarder</b>        | DNS server designated to handle all offsite queries. Using forwarders relieves other DNS servers from having to send packets offsite.                           |
| <b>forwarding, DHCP</b> | Mechanism of forwarding DHCP packets to another DHCP server on a per-client basis. You can achieve this in Cisco Prime IP Express by using extension scripting. |
| <b>FQDN</b>             | Fully qualified domain name. Absolute domain name that unambiguously specifies a host location in the DNS hierarchy.                                            |

|                    |                                                                                                                                                                                          |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>G</b>           |                                                                                                                                                                                          |
| <b>giaddr</b>      | DHCP gateway (relay agent) IP address. Sent in an RFC 2131 packet between the client and server.                                                                                         |
| <b>glue record</b> | DNS Address resource record that specifies the address of a subdomain authoritative name server. You only need glue records in the server delegating a domain, not in the domain itself. |
| <b>group</b>       | Associative entity that combines administrators so that they can be assigned roles and constrained roles.                                                                                |

|                                   |                                                                                                                                 |
|-----------------------------------|---------------------------------------------------------------------------------------------------------------------------------|
| <b>H</b>                          |                                                                                                                                 |
| <b>High-Availability (HA) DNS</b> | DNS configuration in which a second primary server can be made available as a hot standby that shadows the main primary server. |
| <b>HINFO record</b>               | DNS Host Information resource record (RR). Provides information about the hardware and software of the host machine.            |
| <b>hint server</b>                | See <a href="#">root hint server</a> .                                                                                          |
| <b>host</b>                       | Any network device with a TCP/IP network address.                                                                               |

|             |                                                                                                                                                        |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>I</b>    |                                                                                                                                                        |
| <b>IEEE</b> | Institute of Electrical and Electronics Engineers. Professional organization whose activities include developing communications and network standards. |

|                        |                                                                                                                                                                                        |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>in-addr.arpa</b>    | DNS address mapping domain with which you can index host addresses and names. The Internet can thereby convert IP addresses back to hostnames. See also <a href="#">reverse zone</a> . |
| <b>IP address</b>      | Internet Protocol address. For example, 192.168.40.123.                                                                                                                                |
| <b>IP history</b>      | Cisco PrimeIP Express tool that records the lease history of IP addresses in a database.                                                                                               |
| <b>IPv6</b>            | New IP standard involving 128-bit addresses. Cisco Prime IP Express provides a DHCPv6 implementation.                                                                                  |
| <b>ISP</b>             | Internet Service Provider. Company that provides leased line, dialup, and DSL (Point-to-Point over Ethernet and DHCP) access to customers.                                             |
| <b>iterative query</b> | Type of DNS query whereby the name server returns the closest answer to the querying server.                                                                                           |
| <b>IXFR</b>            | Incremental zone transfer. Standard that allows Cisco Prime IP Express to update a slave (secondary) server by transferring only the changed data from the primary server.             |

|                           |                                                                                                                                                                                                                                                                           |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>L</b>                  |                                                                                                                                                                                                                                                                           |
| <b>lame delegation</b>    | Condition when DNS servers listed in a zone are not configured to be authoritative for the zone.                                                                                                                                                                          |
| <b>LDAP</b>               | Lightweight Directory Access Protocol. Method that provides directory services to integrate Cisco Prime IP Express client and lease information.                                                                                                                          |
| <b>lease</b>              | IP address assignment to a DHCP client that also specifies how long the client can use the address. When the lease expires, the client must negotiate a new one with the DHCP server.                                                                                     |
| <b>lease grace period</b> | Length of time the lease is retained in the DHCP server database after it expires. This protects a client lease in case the client and server are in different time zones, their clocks are not synchronized, or the client is not on the network when the lease expires. |

|                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>link group</b>    | Groups the links to accommodate CMTS Prefix Stability. The <i>group-name</i> attribute is used to specify the name of the group to which the link should belong.                                                                                                                                                                                                                                                                                                              |
| <b>lease history</b> | A report that can be generated to provide a historical view of when a client was issued a lease, for how long, when the client or server released the lease before it expired, and if and when the server renewed the lease and for how long.                                                                                                                                                                                                                                 |
| <b>lease query</b>   | Process by which a relay agent can request lease (and reservation) data directly from a DHCP server in addition to gleaning it from client/server transactions.                                                                                                                                                                                                                                                                                                               |
| <b>link type</b>     | There are three different link types: topological, location-independent, and universal. Topological links means a client is allocated leases based on the network segment it is connected to. While the location-independent link type lets a subscriber, that is moved from one CMTS to another within a central office, to retain a delegated prefix, the universal link type lets the subscriber moving from one central office to another to retain the delegated prefix. |
| <b>local cluster</b> | Location of the local Cisco Prime IP Express servers. <i>See also</i> <a href="#">regional cluster</a> .                                                                                                                                                                                                                                                                                                                                                                      |
| <b>localhost</b>     | Distinguished name referring to the name of the current machine. Localhost is useful for applications requiring a hostname.                                                                                                                                                                                                                                                                                                                                                   |
| <b>loopback zone</b> | DNS zone that enables the server to direct traffic to itself. The host number is almost always 127.0.0.1.                                                                                                                                                                                                                                                                                                                                                                     |

|                       |                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>M</b>              |                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <b>MAC address</b>    | Standardized data link layer address. Required for every port or device that connects to a LAN. Other devices in the network use these addresses to locate specific ports on the network and to create and update routing tables and data structures. MAC addresses are six bytes long and are controlled by the IEEE. Also known as a hardware address, MAC layer address, and physical address. A typical MAC address is 1,6,00:d0:ba:d3:bd:3b. |
| <b>mail exchanger</b> | Host that accepts electronic mail, some of which act as mail forwarders. <i>See also</i> <a href="#">MX record</a> .                                                                                                                                                                                                                                                                                                                              |

|                                        |                                                                                                                                                                                             |
|----------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>master name server</b>              | Authoritative DNS name server that transfers zone data to secondary servers through zone transfers.                                                                                         |
| <b>maximum client lead time (MCLT)</b> | In DHCP failover, a type of lease insurance that controls how much ahead of the backup server lease expiration the client lease expiration should be.                                       |
| <b>multinetting</b>                    | State of having multiple DHCP scopes on one subnet or several LAN segments.                                                                                                                 |
| <b>Multiple Service Operator (MSO)</b> | Provides subscribers Internet access using cable or wireless technologies.                                                                                                                  |
| <b>multithreading</b>                  | Process of performing multiple server tasks.                                                                                                                                                |
| <b>MX record</b>                       | DNS Mail Exchanger resource record (RR). Specifies where mail for a domain name should be delivered. You can have multiple MX records for a single domain name, ranked in preference order. |

|                            |                                                                                                                                                                                                                    |
|----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>N</b>                   |                                                                                                                                                                                                                    |
| <b>nameserver</b>          | DNS host that stores data and RRs for a domain.                                                                                                                                                                    |
| <b>NAPTR</b>               | DNS Naming Authority Pointer resource record (RR). Helps with name resolution in a particular namespace and is processed to get to a resolution service. Based on proposed standard RFC 2915.                      |
| <b>negative cache time</b> | Memory cache the DNS server maintains for a quick response to repeated requests for negative information, such as "no such name" or "no such data." Cisco Prime IP Express discards this information at intervals. |
| <b>network ID</b>          | Portion of the 32-bit IP address that identifies which network a particular system is on, determined by performing an AND operation of the subnet mask and the IP address.                                         |
| <b>NOTIFY</b>              | Standard (RFC 1996) whereby DNS master servers can inform their slaves that changes were made to their zones, and which initiates a zone transfer.                                                                 |
| <b>nrcmd</b>               | Cisco PrimeIP Express command line interface (CLI).                                                                                                                                                                |

|          |  |
|----------|--|
| <b>O</b> |  |
|----------|--|

|                                                 |                                                                                                                                                                                                                                                                                                       |
|-------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>on-demand address pool</b>                   | Wholesale IP address pool issued to a client (usually a VPN router or other provisioning device), from which it can draw for lease assignments. Also known as DHCP subnet allocation.                                                                                                                 |
| <b>option, DHCP</b>                             | DHCP configuration parameter and other control information stored in the options field of a DHCP message. DHCP clients determine what options get requested and sent in a DHCP packet. Cisco Prime IP Express allows for creating option definitions as well as the option sets to which they belong. |
| <b>Organization report</b>                      | One of the reports to be submitted to ARIN, POC being the other report. <i>See also</i> <a href="#">ARIN</a> and <a href="#">POC report</a> .                                                                                                                                                         |
| <b>Organizationally Unique Identifier (OUI)</b> | Assigned by the IEEE to identify the owner or ISP of a VPN. <i>See also</i> <a href="#">IEEE</a> and <a href="#">virtual private network (VPN)</a> .                                                                                                                                                  |
| owner                                           | Owners can be created as distinguishing factors for address blocks, subnets, and zones. In the context of DNS RRs, an owner is the name of the RR.                                                                                                                                                    |

|                                 |                                                                                                                                                                                                                                                                                 |
|---------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>P</b>                        |                                                                                                                                                                                                                                                                                 |
| <b>ping</b>                     | Packet Internetwork Groper. A common method for troubleshooting device accessibility that uses a series of Internet Control Message Protocol (ICMP) Echo messages to determine if a remote host is active or inactive, and the round-trip delay in communicating with the host. |
| <b>POC report</b>               | Point of Contact report. One of the reports to be submitted to ARIN, Organization being the other report. <i>See also</i> <a href="#">ARIN</a> and <a href="#">Organization report</a> .                                                                                        |
| <b>policy</b>                   | Group of DHCP attributes or options applied to a single scope or group of scopes. Embedded policies can be created for scopes and other DHCP objects.                                                                                                                           |
| <b>polling</b>                  | Collection of subnet utilization or lease history data over a certain regular period.                                                                                                                                                                                           |
| <b>prefix allocation groups</b> | Groups prefixes in order to facilitate the prioritization of prefix allocation.                                                                                                                                                                                                 |

|                                    |                                                                                                                                                                                                                          |
|------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>prefix stability</b>            | Clients can retain the delegated prefix when they change their location, that is even when they move from one CMTS to another (CMTS Prefix Stability) or move within an address space (Universal Prefix Stability).      |
| <b>primary master</b>              | DNS server from which a secondary server receive data through a zone transfer request.                                                                                                                                   |
| <b>provisional address</b>         | Address allocated by the DHCP server to unknown clients for a short time, one-shot basis.                                                                                                                                |
| <b>PTR record</b>                  | DNS Pointer resource record. Used to enable special names to point to some other location in the domain tree. Should refer to official (canonical) names and not aliases. <i>See also</i> <a href="#">in-addr.arpa</a> . |
| <b>pulling and pushing objects</b> | The Cisco PrimeIP Express regional cluster provides functions to pull network objects from the replica database of local cluster data, and push objects directly to the local clusters.                                  |

|                         |                                                                                                                                                                                                           |
|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>R</b>                |                                                                                                                                                                                                           |
| <b>recursive query</b>  | DNS query where the name server asks other DNS server for any nonauthoritative data not in its own cache. Recursive queries continue to query all name servers until receiving an answer or an error.     |
| <b>refresh interval</b> | Time interval in which a secondary DNS server checks the accuracy of its data by sending an AXFR packet to the primary server.                                                                            |
| <b>region</b>           | Regions can be created as distinguishing factors for address blocks, subnets, and zones. A region is distinct from the regional cluster.                                                                  |
| <b>regional cluster</b> | Location of the regional Cisco Prime IP Express CCM server. <i>See also</i> <a href="#">local cluster</a> .                                                                                               |
| <b>relay agent</b>      | Device that connects two or more networks or network systems. In DHCP, a router on a virtual private network that is the IP helper for the DHCP server.                                                   |
| <b>replica database</b> | CCM database that captures copies of local cluster configurations at the regional cluster. These configurations can be pulled to the regional cluster so that they can be pushed to other local clusters. |



|                                   |                                                                                                                                                                                                                                                                                                                                                                                                                   |
|-----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Request for Comments (RFC)</b> | TCP/IP set of standards.                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>reservation</b>                | IP address or lease that is reserved for a specific DHCP client.                                                                                                                                                                                                                                                                                                                                                  |
| <b>resolution exception</b>       | Selectively forwarding DNS queries for specified domains to internal servers rather than recursively querying Internet root name and external servers.                                                                                                                                                                                                                                                            |
| <b>resolver</b>                   | Client part of the DNS client/server mechanism. A resolver creates queries sent across a network to a name server, interprets responses, and returns information to the requesting programs.                                                                                                                                                                                                                      |
| <b>resource record (RR)</b>       | DNS configuration record, such as SOA, NS, A, CNAME, HINFO, WKS, MX, and PTR that comprises the data within a DNS zone. Mostly abbreviated as RR.<br><br><i>See the "Resource Records" section in Cisco PrimeIP Express 8.3 Authoritative and Caching DNS User Guide</i>                                                                                                                                          |
| <b>reverse zone</b>               | DNS zone that uses names as addresses to support address queries.<br><br><i>See also <a href="#">in-addr.arpa</a>.</i>                                                                                                                                                                                                                                                                                            |
| <b>role, constrained role</b>     | Administrators can be assigned one or more roles to determine what functionality they have in the application. A constrained role is a role constrained by further limitations. There are general roles for DNS, host, address block, DHCP, and CCM database administration. You can further constrain roles for specific hosts and zones. Some roles have distinguishing subroles, such as the database subrole. |
| <b>root hint server</b>           | DNS name server at the top of the hierarchy for all root name queries. A root name server knows the addresses of the authoritative name servers for all the top-level domains. Resolution of nonauthoritative or uncached data must start at the root servers. Sometimes called a hint server.                                                                                                                    |
| <b>round-robin</b>                | Action when a DNS server rearranges the order of its multiple same-type records each time it is queried.                                                                                                                                                                                                                                                                                                          |

|                                          |                                                                                                                                                                                                                                                                 |
|------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>routed bridge encapsulation (RBE)</b> | Process by which a stub-bridged segment is terminated on a point-to-point routed interface. Specifically, the router is routing on an IEEE 802.3 or Ethernet header carried over a point-to-point protocol, such as PPP, RFC 1483 ATM, or RFC 1490 Frame Relay. |
|------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                          |                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>S</b>                 |                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>scavenging</b>        | Action of periodically scanning dynamic updates to the DNS server for stale resource records and purging these records.                                                                                                                                                                                                                                                                   |
| <b>scope</b>             | Administrative grouping of TCP/IP addresses on a DHCP server. Required for lease assignments.                                                                                                                                                                                                                                                                                             |
| <b>secondary master</b>  | DNS name server that gets its zone data from another name server authoritative for the zone. When a secondary master server starts up, it contacts the primary master, from which it receives updates.                                                                                                                                                                                    |
| <b>secondary subnet</b>  | A single LAN might have more than one subnet number applicable to the same LAN or network segment in a router. Typically, one subnet is designated as primary, the others as secondary. A site might support addresses on more than one subnet number associated with a single interface. You must configure the DHCP server with the necessary information about your secondary subnets. |
| <b>selection tags</b>    | Mechanisms that help select DHCPv4 scopes and DHCPv6 prefixes for clients and client-classes.                                                                                                                                                                                                                                                                                             |
| <b>siaddr</b>            | IP address of the server to use in the next step of the DHCP boot process. Sent in an RFC 2131 packet between the client and server.                                                                                                                                                                                                                                                      |
| <b>slave forwarder</b>   | DNS server that behaves like a stub resolver and passes most queries on to another name server for resolution. <i>See also</i> <a href="#">stub resolver</a> .                                                                                                                                                                                                                            |
| <b>slave servers</b>     | DNS server that always forwards queries it cannot answer from its cache to a fixed list of forwarding servers instead of querying the root name servers for answers.                                                                                                                                                                                                                      |
| <b>SNMP notification</b> | Simple Network Management Protocol messages that warn of server error conditions and problems. <i>See also</i> <a href="#">trap</a> .                                                                                                                                                                                                                                                     |

|                                |                                                                                                                                                                                                                                                                                                                              |
|--------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>SOA record</b>              | DNS Start of Authority resource record (RR). Designates the start of a zone.                                                                                                                                                                                                                                                 |
| <b>SRV record</b>              | Type of DNS resource record (RR) that allows administrators to use several servers for a single host domain, to move services from host to host with little difficulty, and to designate some hosts as primary servers for a service and others as backups.                                                                  |
| <b>staged edit mode</b>        | dhcp or dns edit mode in which the data is stored on the CCM server, but not live on the protocol server. <i>See also</i> <a href="#">synchronous edit mode</a> .                                                                                                                                                            |
| <b>stub resolver</b>           | DNS server that hands off queries to another server instead of performing the full resolution itself.                                                                                                                                                                                                                        |
| <b>subnet allocation, DHCP</b> | Cisco PrimeIP Express use of on-demand address pools for entire subnet allocation of IP addresses to provisioning devices.                                                                                                                                                                                                   |
| <b>subnet mask</b>             | Separate IP address, or part of a host IP address, that determines the host address subnet. For example, 192.168.40.0 255.255.255.0 (or 192.168.40.0/24) indicates that the first 24 bits of the IP address are its subnet, 192.168.40. In this way, addresses do not need to be divided strictly along network class lines. |
| <b>subnet pool</b>             | Set of IP addresses associated with a network number and subnet mask, including secondary subnets.                                                                                                                                                                                                                           |
| <b>subnet sorting</b>          | Attribute of the Cisco Prime IP Express DNS server. By enabling it, the server checks the network address of the client before responding to a query.                                                                                                                                                                        |
| <b>subnet utilization</b>      | A report that can be generated to determine how many addresses in the subnet were allocated and what the free address space is.                                                                                                                                                                                              |
| <b>subnetting</b>              | Action of dividing any network class into multiple subnetworks.                                                                                                                                                                                                                                                              |
| <b>subscriber limitation</b>   | Limitation to the number of addresses service providers can determine for the DHCP server to give out to devices on customer premises, handled in Cisco Prime IP Express by DHCP option 82 definitions.                                                                                                                      |
| <b>subzones</b>                | Partition of a delegated domain, represented as a child of the parent node. A subzone always ends with the name of its parent. For example, boston.example.com. can be a subzone of example.com.                                                                                                                             |

|                              |                                                                                                                                                                                |
|------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>subzone delegation</b>    | Dividing a zone into subzones. You can delegate administrative authority for these subzones, and have them managed by people within those zones or served by separate servers. |
| <b>supernet</b>              | Aggregation of IP network addresses advertised as a single classless network address.                                                                                          |
| <b>synchronization</b>       | Synchronization can occur between the regional cluster and local clusters, the CCM and other protocol servers, failover servers, HA DNS servers, and routers.                  |
| <b>synchronous edit mode</b> | dhcp or dns edit mode in which the data is live on the protocol server. <i>See also</i> <a href="#">staged edit mode</a> .                                                     |

|                                     |                                                                                                                                                                                                                              |
|-------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>T</b>                            |                                                                                                                                                                                                                              |
| <b>TAC</b>                          | Cisco Technical Assistance Center. Cisco Prime IP Express provide a <b>cnr_tactool</b> utility to use in reporting issues to the TAC.                                                                                        |
| <b>TCP/IP</b>                       | Suite of data communication protocols. Its name comes from two of the more important protocols in the suite: the Transmission Control Protocol (TCP) and the Internet Protocol (IP). It forms the basis of Internet traffic. |
| <b>template</b>                     | DNS zones and DHCP scopes can have templates to create multiple objects with similar properties.                                                                                                                             |
| <b>transaction signature (TSIG)</b> | DHCP mechanism that ensures that DNS messages come from a trusted source and are not tampered with. <i>See also</i> <a href="#">access control list (ACL)</a> .                                                              |
| <b>trap</b>                         | Criteria set to detect certain SNMP events, such as to determine free addresses on the network. <i>See also</i> <a href="#">SNMP notification</a> .                                                                          |
| <b>trimming and compacting</b>      | Trimming is periodic elimination of old historical data to regulate the size of log and other files. Compacting is reducing data older than a certain age to subsets of the records.                                         |

|                            |                                                                                                                                         |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------|
| <b>U</b>                   |                                                                                                                                         |
| <b>Universal Time (UT)</b> | International standard time reference that was formerly called Greenwich Mean Time (GMT), also called Universal Coordinated Time (UCT). |

|                                     |                                                                                                  |
|-------------------------------------|--------------------------------------------------------------------------------------------------|
| <b>update configuration, DNS</b>    | Defines the relationship of a zone with its main and backup DNS servers for DNS update purposes. |
| <b>update map, DNS</b>              | Defines an update relationship between a DHCP policy and a list of DNS zones.                    |
| <b>update policy, DNS</b>           | Provide a mechanism in DHCP for managing update authorization at the DNS RR level.               |
| <b>User Datagram Protocol (UDP)</b> | Connectionless TCP/IP transport layer protocol.                                                  |

|                                                                           |                                                                                                                                                                                                                                                                                                                                                                                                                 |
|---------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>V</b>                                                                  |                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <b>virtual channel identifier (VCI) and virtual path identifier (VPI)</b> | 16-bit field in the header of an ATM cell. The VCI, together with the VPI, identifies the next destination of a cell as it passes through a series of ATM switches on its way to its destination. ATM switches use the VPI/VCI fields to identify the next network VCL that a cell needs to transit on its way to its final destination. The function of the VCI is similar to that of the DLCI in Frame Relay. |
| <b>virtual private network (VPN)</b>                                      | Protocol over which IP traffic of private address space can travel securely over a public TCP/IP network. A VPN uses tunneling to encrypt all information at the IP level. <i>See also</i> <a href="#">VRF</a> .                                                                                                                                                                                                |
| <b>VRF</b>                                                                | VPN Routing and Forwarding instance. Routing table and forwarding information base table, populated by routing protocol contexts. <i>See also</i> <a href="#">virtual private network (VPN)</a> .                                                                                                                                                                                                               |

|                        |                                                                                                                                                                                              |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>W</b>               |                                                                                                                                                                                              |
| <b>well-known port</b> | Any set of IP protocol port numbers preassigned for specific uses by transport level protocols, for example, TCP and UDP. Each server listens at a well-known port so clients can locate it. |
| <b>WKS record</b>      | DNS Well Known Service resource record (RR). Used to list the services provided by the hosts in a zone. Common protocols are TCP and UDP.                                                    |

|          |  |
|----------|--|
| <b>Y</b> |  |
|----------|--|

|               |                                                                                                                                                                 |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>yiaddr</b> | "Your" client IP address, or address that the DHCP server offers (and ultimately assigns) the client. Sent in an RFC 2131 packet between the client and server. |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|

|                          |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|--------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Z</b>                 |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| <b>zone</b>              | Delegation point in the DNS tree hierarchy that contains all the names from a certain point downward, except for those names that were delegated to other zones. A zone defines the contents of a contiguous section of the domain space, usually bounded by administrative boundaries. Each zone has configuration data composed of entries called resource records. A zone can map exactly to a single domain, but can also include only part of a domain, with the remainder delegated to another subzone. |
| <b>zone distribution</b> | Configuration that simplifies creating multiple zones that share the same secondary zone attributes. The zone distribution requires adding one or more predefined secondary servers.                                                                                                                                                                                                                                                                                                                          |
| <b>zone of authority</b> | Group of DNS domains for which a given name server is an authority.                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>zone transfer</b>     | Action that occurs when a secondary DNS server starts up and updates itself from the primary server. A secondary DNS server queries a primary name server with a specific packet type called AXFR (transfer all) or IXFR (incrementally transfer) and initiates a transfer of a copy of the database.                                                                                                                                                                                                         |