

# **DHCP Extension Dictionary**

This appendix describes the DHCP extension dictionary entries and the application program interface (API) to the extension dictionary. It describes the data items available in the request and response dictionaries, and the calls to use when accessing dictionaries from Tcl extensions and shared libraries.

The appendix contains the following sections:

- Extension Dictionary Entries, on page 1
- Extension Dictionary API, on page 37
- Handling Objects and Options, on page 53
- Examples of Option and Object Method Calls, on page 55

# **Extension Dictionary Entries**

A dictionary is a data structure that contains key-value pairs. There are two types of dictionaries: the attribute dictionaries that the request and response dictionaries use, and the environment dictionary. This section describes the request and response dictionaries; the environment dictionary entries are described in Tcl Environment Dictionary Methods, on page 41.

## **Decoded DHCP Packet Data Items**

The decoded DHCPv4 packet data items represent the information in the DHCP packet, and are available in both the request and response dictionaries. These dictionaries provide access to considerably more internal server data structures than just the decoded request and decoded response.

All of the options followed by an asterisk (\*) are multiple, which means that there can be more than one value associated with each option. In the DHCP/BOOTP packet, all of these data items appear in the same option. However, in the extension interface, these multiple data items are accessible through indexing.

You can access options that do not have names in Table 3: DHCPv4 and BOOTP Options, on page 2 as option–*n*, where *n* is the option number. All fields are read/write. Table 1: DHCPv4 and BOOTP Fields, on page 1 describes the field values for the DHCPv4 packets; Table 2: DHCPv6 Fields, on page 2 describes the field values for the DHCPv6 messages.

#### Table 1: DHCPv4 and BOOTP Fields

Name	Value
chaddr	blob (sequence of bytes)

Name	Value
ciaddr	IP address
file	string
flags	16-bit unsigned integer
giaddr	IP address
hlen	8-bit unsigned integer
hops	8-bit unsigned integer
htype	8-bit unsigned integer
ор	8-bit unsigned integer
secs	16-bit unsigned integer
siaddr	IP address
sname	string
xid	32-bit unsigned integer
yiaddr	IP address

### Table 2: DHCPv6 Fields

Name	Value
hop-count	8-bit unsigned integer
link-address	IPv6 address
msg-type	8-bit unsigned integer
peer-address	IPv6 address
xid	32-bit unsigned integer

The table below lists the DHCP and BOOTP options for DHCPv4.

### Table 3: DHCPv4 and BOOTP Options

Name (*=multivalue)	Number	Value
6rd	212	binary
access-domain	213	DNS name
all-subnets-local	27	byte-valued boolean
andsf-v4	142	IP address

Name (*=multivalue)	Number	Value
arp-cache-timeout	35	unsigned time
authentication	90	blob (sequence of bytes); 5 fields
auto-configure	116	8-bit unsigned integer
base-time	152	date
bcmcs-servers-a*	89	IP address
bcmcs-servers-d*	88	DNS name
boot-file	67	string
boot-size	13	16-bit unsigned integer
broadcast-address	28	IP address
cablelabs-125(v-i-vendor-info ID:	125	binary
4491)	suboptions:	
oro	1	Option request, 8-bit unsigned integer (8-bit unsigned integers)
tftp-servers	2	IP addresses of TFTP servers
erouter-container	3	Erouter container options (binary; TLV encoded options)
packetcable-mib-env	4	MIB environment indicator (8-bit enumeration)
modem-capabilities	5	Modem capabilities encoding (binary; TLV5 encoded data)
acs-server	6	ACS Server suboptions (binary)
radius-server	7	RADIUS Server suboptions (binary)
dhcpv6-servers	123	DHCPv6 server suboptions (binary)
ip-pref	124	IPv4 or IPv6 preference (8-bit enumeration)
cablelabs-client- configuration	122	blob (sequence of bytes)
	suboptions:	
primary-dhcp- server	1	IP address
secondary-dhcp- server	2	IP address

I

Name (*=multivalue)	Number	Value
provisioning- server	3	blob (the first byte must be the type byte, with 0 for RFC 1035 encoding, and 1 for IP address encoding, for which the address must be in network order)
as-backoff-retry- blob	4	12-byte blob (3 unsigned 4-byte integers, which must be in network order); configures the Kerberos AS-REQ/AS-REP timeout, back-off, and retry mechanism
ap-backoff-retry- blob	5	12-byte blob (3 unsigned 4-byte integers, which must be in network order); configures the Kerberos AP-REQ/AP-REP timeout, back-off, and retry mechanism
kerberos-realm	6	variable-length blob (an RFC 1035 style name); a Kerberos realm name is required
use-tgt	7	1-byte unsigned integer boolean; indicates whether to use a Ticket Granting Ticket (TGT) when obtaining a service ticket for one of the application servers
provisioning-timer	8	1-byte unsigned integer; defines the maximum time allowed for the provisioning process to finish
ticket-control- mask	9	2-byte unsigned integer, in host order
kdc-addresses- blob	10	variable-length (multiple of 4) IP address, in network order
captive-portal	114	string
captive-portal-old	160	string
capwap-ac-v4*	138	IP address
cisco-autoconfigure	251	bounded byte
cisco-client-last-transaction- time	163	unsigned 32-bit integer
cisco-client-requested-host- name	162	string
cisco-vpn-id	221	blob (structured)
classless-static-route	121	blob (structured)
client-fqdn	81	blob (sequence of bytes); 4 fields: flags, rcode-1, rcode-2, and domain-name
cookie-servers*	8	IP address

Name (*=multivalue)	Number	Value
data-source	157	8-bit unsigned integer
default-ip-ttl	23	8-bit unsigned integer
default-tcp-ttl	37	8-bit unsigned integer
dhcp4o6-s46-saddr	109	IPv6 address
dhcp-class-identifier	60	string
dhcp-client-identifier	61	blob (sequence of bytes)
dhcp-lease-time	51	unsigned time
dhcp-max-message-size	57	16-bit unsigned integer
dhcp-message	56	string
dhcp-message-type	53	8-bit unsigned integer
dhcp-option-overload	52	8-bit unsigned integer
dhcp-parameter-request-list*	55	8-bit unsigned integer
dhcp-parameter-request- list-blob*	55	blob (sequence of bytes)
dhcp-rebinding-time	59	unsigned time
dhcp-renewal-time	58	unsigned time
dhcp-requested-address	50	IP address
dhcp-server-identifier	54	IP address
dhcp-state	156	8-bit unsigned integer
dhcp-user-class-id	77	set of counted len byte arrays; 2 fields: typcnt-size and user-data
domain-name	15	string
domain-name-servers*	6	IP address
domain-search	119	blob (sequence of bytes)
dots-address*	148	IP address
dots-ri	147	DNS name
end	255	No length
extensions-path	18	string
finger-servers*	73	IP address

Name (*=multivalue)	Number	Value
font-servers*	48	IP address
forcerenew-nonce-capable*	145	8-bit unsigned integer
geo-conf	123	blob (sequence of bytes)
geoconf-civic	99	blob (sequence of bytes)
geoloc	144	binary
host-name	12	string
ieee802.3-encapsulation	36	byte-valued boolean
impress-servers*	10	IP address
interface-mtu	26	16-bit unsigned integer
ip-forwarding	19	byte-valued boolean
ipv6-only-preferred	108	unsigned 32-bit integer
irc-servers*	74	IP address
iSNS	83	blob (sequence of bytes); 7 fields
ldap-url	95	string
log-servers*	7	IP address
lost-server	137	DNS Name (see RFC 5223)
lpr-servers*	9	IP address
lq-associated-ip*	92	IP address
lq-client-last-transaction- time	91	unsigned time
mask-supplier	30	byte-valued boolean
max-dgram-reassembly	22	16-bit unsigned integer
mcns-security-server	128	IP address
merit-dump	14	string
mobile-ip-home-agents*	68	IP address
mos-address	139	binary; 3 suboptions
	suboptions:	
is	1	IP address
cs	2	IP address

Name (*=multivalue)	Number	Value
es	3	IP address
mos-fqdn	140 suboptions:	binary; 3 suboptions
is	1	DNS name
cs	2	DNS name
es	3	DNS name
mud-url	161	string
name-servers*	5	IP address
name-service-search*	117	16-bit unsigned integer
nds-context	87	string
nds-servers*	85	IP address
nds-tree	86	string
netbios-dd-servers*	45	IP address
netbios-name-servers*	44	IP address
netbios-node-type	46	8-bit unsigned integer
netbios-scope	47	string
netinfo-parent-server-addr	112	IP address
netinfo-parent-server-tag	113	string
netwareip-domain	62	string
netwareip-information	63	blob (sequence of bytes)
nis+-domain	64	string
nis+-servers*	65	IP address
nis-domain	40	string
nis-servers*	41	IP address
nntp-servers*	71	IP address
non-local-source-routing	20	byte-valued boolean
ntp-servers*	42	IP address
pad	0	No length

Name (*=multivalue)	Number	Value
pana-agent	136	IP address(es) (see RFC 5192)
path-mtu-aging-timeout	24	unsigned time
path-mtu-plateau-tables*	25	16-bit unsigned integer
perform-mask-discovery	29	byte-valued boolean
policy-filters*	21	IP address (there can be two policy filters, each one having its own IP address)
pop3-servers*	70	IP address
posix-timezone	100	string (see RFC 4833)
pxe-client-arch	93	16-bit unsigned integer
pxe-client-machine-id	97	blob (sequence of bytes); 2 fields: type-flag and uuid
pxe-client-network-id	94	blob (sequence of bytes); 2 fields: type-flag and version
pxelinux-config-file	209	string
pxelinux-path-prefix	210	string
pxelinux-reboot-time	211	unsigned time
query-end-time	155	date
query-start-time	154	date
rapid-commit	80	null-length
rdnss-selection	146	binary; 4 fields: reserved-prf, primary-recursive-name-server, secondary-recursive-name-server, and domains-and-networks
relay-agent-info suboptions:	82 suboptions:	blob (sequence of bytes)
relay-agent-circuit-id- data	1	blob (sequence of bytes)
relay-agent-remote-id- data	2	blob (sequence of bytes)
relay-agent-device- class-data	4	4-byte unsigned integer
relay-agent-subnet- selection-data	5	IP address
subscriber-id	6	string identifying the network client or subscriber

Name (*=multivalue)	Number	Value
radius-attributes	7	supported attributes are user, class, and framed-pool
authentication	8	binary
v-i-vendor-opts	9	vendor options
cisco-subnet-selection	150	IP address
cisco-vpn-id	151	binary
cisco-server-id-override	152	IP address
	suboption code and data leng	d relay-agent-device-class suboptions, which gth) preceding the suboption data, are
resource-location-servers*	11	IP address
root-path	17	string
router-discovery	31	byte-valued boolean
router-solicitation-address	32	IP address
routers*	3	IP address
sip-servers	120	blob (sequence of bytes); 2 fields: flag and sip-server-list
sip-ua-cs-domains	141	DNS name
slp-directory-agent*	78	blob (sequence of bytes); 2 fields: mandatory and agent-ip-list
slp-service-scope*	79	blob (sequence of bytes); 2 fields: mandatory and slp-scope-list
smtp-servers*	69	IP address
start-time-of-state	153	unsigned time
static-routes*	33	IP address
status-code	151	binary; 2 fields: status-code and status-message
streettalk-directory- assistance-servers*	76	IP address
streettalk-servers*	75	IP address

Name (*=multivalue)	Number	Value
subnet-alloc	220	blob (sequence of bytes); 5 fields: flags, subnet-request, subnet-info, subnet-name, and subnet-suggested-lease-time
subnet-mask	1	IP address
subnet-selection	118	IP address
swap-server	16	IP address
sztp-redirect	143	set of counted len byte arrays; 2 fields: typcnt-size and url
tcp-keepalive-garbage	39	byte-valued boolean
tcp-keepalive-internal	38	unsigned time
tftp-server	66	string
tftp-server-address*	150	IP address
time-offset	2	signed time
time-servers*	4	IP address
trailer-encapsulation	34	byte-valued boolean
tzdb-timezone	101	string (see RFC 4833)
user-auth	98	string
v4-pcp-server*	158	binary
v4-portparams	159	binary; 3 fields: offset, psid-len, and psid
v-i-vendor-class	124	blob (sequence of bytes)
v-i-vendor-info	125	blob (sequence of bytes)
vendor-encapsulated-options	43	blob (sequence of bytes)
vpn-id	185	blob (structured); 2 fields: flag and vpn-id
www-servers*	72	IP address
x-display-managers*	49	IP address

The table below lists the DHCPv6 options.



Note

Access to these options is available using the **putOption**, **getOption**, and **removeOption** methods only.

### Table 4: DHCPv6 Options

Name (*=multivalue)	Number	Value
4rd	97	container (of options)
4rd-map-rule	98	binary; 6 fields: prefix4-len, prefix6-len, ea-len, flags, rule-ipv4-prefix, and rule-ipv6-prefix
4rd-non-map-rule	99	binary; 3 fields: flags, traffic-class, and domain-pmtu
access-domain	57	DNS name
addrsel	84	binary; 1 field: reserved-AP
addrsel-table	85	binary; 3 fields: label, precedence, and prefix
aftr-name	64	DNS name
ani-ap-bssid	108	blob (sequence of bytes)
ani-ap-name	107	string
ani-att	105	binary; 2 fields: reserved and att
ani-network-name	106	string
ani-operator-id	109	blob (sequence of bytes)
ani-operator-realm	110	string
auth	11	binary; 5 fields: protocol, algorithm, replay-detection-method, replay-detection, and auth-info
bcmcs-server-a*	34	IPv6 address
bcmcs-server-d*	33	DNS name
bootfile-param	60	counted-type; 2 fields: typecnt-size and parameter
bootfile-url	59	string
cablelabs-17 (vendor-opts ID: 4491)	17	vendor-opts; 27 suboptions
	suboptions:	
oro	1	16-bit unsigned integer
device-type	2	string
embedded-components-list	3	string
device-serial-number	4	string
hardware-version-number	5	string
software-version-number	6	string

I

Name (*=multivalue)	Number	Value
boot-rom-version	7	string
vendor-oui	8	string
model-number	9	string
vendor-name	10	string
ecm-cfg-encaps	15	string
tftp-servers	32	IPv6 address
config-file-name	33	string
syslog-servers	34	IPv6 address
modem-capabilities	35	binary
device-id	36	binary
rfc868-servers	37	IPv6 address
time-offset	38	signed time
ip-pref	39	8-bit unsigned integer
acs-server	40	binary; 2 suboptions
	suboptions:	
flag	0	8-bit unsigned integer
server	0	
radius-server	41	binary; 2 suboptions
	suboptions:	
flag	0	8-bit unsigned integer
server	0	
cer-id	42	IPv6 address
ccap-cores	61	IPv6 address
cmts-capabilities	1025	binary
cm-mac-address	1026	binary
erouter-container	1027	binary
cablelabs-client-configuration	2170	binary; 2 suboptions (various data types)
	suboptions:	

	Number	Value
rimary-dhcp-server	1	IP address
econdary-dhcp-server	2	IP address
ablelabs-client-configuration-v6	2171	binary; 9 suboptions (various data types)
	suboptions:	
rimary-dhcpv6-server- selector-id	1	binary
econdary-dhcpv6-server- selector-i	d 2	binary
rovisioning-server	3	binary
s-backoff-retry	4	binary
p-backoff-retry	5	binary
erberos-realm	6	DNS name
se-tgt	7	unsigned 8-bit
rovisioning-timer	8	unsigned 8-bit
icket-control-mask	9	unsigned 16-bit
ablelabs-correlation-id	2172	unsigned 32-bit
aptive-portal	103	string
apwap-ac-v6*	52	IPv6 address
lient-arch-type*	61	unsigned 16-bit
lient-data	45	container (of options)
lient-fqdn	39	binary; 2 fields: flags and domain-name
lient-identifier	1	blob (sequence of bytes)
lient-linklayer-address	79	binary; 2 fields: link-layer-type and link-layer-address
lt-time	46	unsigned time (see RFC 5007)
hcp4-o-dhcp6-server	88	IPv6 address
hcpv4-msg	87	blob (sequence of bytes)
ns-servers*	23	IPv6 address
omain-list	24	DNS name
ots-address*	142	IPv6 address
ots-ri	141	DNS name

Name (*=multivalue)	Number	Value
elapsed-time	8	unsigned 16-bit
ero	43	unsigned 16-bit (see RFC 4994)
erp-local-domain-name	65	DNS name
geoconf-civic	36	binary
geoloc	63	blob (sequence of bytes)
ia-na	3	binary; 3 fields: iaid, t1, and t2
ia-pd	25	binary; 3 fields: iaid, t1, and t2
ia-ta	4	binary; 1 field: iaid
iaaddr	5	binary; 3 fields: address, preferred-lifetime, and valid-lifetime
iaprefix	26	binary; 4 fields: preferred-lifetime, valid-lifetime, prefix-length, and prefix
inf-max-rt	83	unsigned time
info-refresh-time	32	unsigned time
interface-id	18	blob (sequence of bytes)
ipv6-adddress-andsf*	143	IPv6 address
krb-default-realm-name	77	string
krb-kdc	78	binary; 5 fields: priority, weight, transport-type, kdc-ipv6-address, and realm-name
krb-principal-name	75	binary; 2 fields: name-type and name-string
krb-realm-name	76	string
link-address	80	IPv6 address
lost-server	51	DNS Name (see RFC 5223)
lq-base-time	100	unsigned 32-bit
lq-client-links*	48	IPv6 address(es) (see RFC 5007)
lq-end-time	102	unsigned 32-bit
lq-query	44	binary structured (see RFC 5007)
lq-relay-data	47	binary (DHCPv6 message) (see RFC 5007)
lq-start-time	101	unsigned 32-bit

Name (*=multivalue)	Number	Value
mip6-haa	72	IPv6 address
mip6-haf	73	DNS name
mip6-hnidf	49	DNS name
mip6-hnp	71	binary; 2 fields: prefix-length and prefix
mip6-idinf	69	container (of options)
mip6-udinf	70	container (of options)
mip6-vdinf	50	container (of options)
mos-address	54	binary; 3 suboptions
	suboptions:	
is	1	IPv6 address
cs	2	IPv6 address
es	3	IPv6 address
mos-fqdn	55	binary; 3 suboptions
	suboptions:	
is	1	DNS name
CS	2	DNS name
es	3	DNS name
mpl-parameters	104	blob (sequence of bytes)
mud-url	112	string
new-posix-timezone	41	string (RFC 4833)
new-tzdb-timezone	42	string (RFC 4833)
nii	62	binary; 3 fields: type, major, and minor
nis-domain-name*	29	DNS name
nis-servers*	27	IP address
nisp-domain-name*	30	DNS name
nisp-servers*	28	IP address
ntp-server	56	binary; 3 suboptions (various data types)
oro	6	unsigned 16-bit

Name (*=multivalue)	Number	Value
pana-agent*	40	IPv6 address(es) (see RFC 5192)
pd-exclude	67	binary; 2 fields: prefix-length and subnet-id
preference	7	unsigned 8-bit
prefix64	113	binary; 3 fields: ASM-mPrefix64, SSM-mPrefix64, and uPrefix64
radius	81	blob (sequence of bytes)
rapid-commit	14	zero size
rdnss-selection	74	binary; 3 fields: recursive-name-server, reserved-and-prf, and domains-and-networks
reconfigure-accept	20	zero size
reconfigure-message	19	unsigned 8-bit
relay-agent-subscriber-id	38	binary
relay-id	53	blob (sequence of bytes)
relay-message	9	binary
relay-port	135	unsigned 16-bit
remote-id	37	binary; 2 fields: enterprise-id and remote-id
rsoo	66	container (of options)
s46-br	90	IPv6 address
s46-cont-lw	96	container (of options)
s46-cont-mape	94	container (of options)
s46-cont-mapt	95	container (of options)
s46-dmr	91	IPv6 variable-length prefix
s46-portparams	93	binary; 3 fields: offset, psid-len, and psid
s46-priority*	111	unsigned 16-bit
s46-rule	89	binary; 5 fields: flags, ea-len, prefix4-len, ipv4-prefix, and prefix6
s46-v4v6bind	92	binary; 2 fields: ipv4-address and bind-ipv6-prefix
server-identifier	2	blob (sequence of bytes)
server-unicast	12	IPv6 address

Name (*=multivalue)	Number	Value
sip-servers-address	22	IPv6 address
sip-servers-name	21	DNS name
sip-ua-cs-domains	58	DNS name
sntp-servers*	31	IPv6 address
sol-max-rt	82	unsigned time
status-code	13	binary; 2 fields: status-code and status-message
sztp-redirect	136	counted-type; 2 fields: typecnt-size and url
user-class	15	counted-type; 2 fields: typecnt-size and user-data
v6-pcp-server*	86	IPv6 address
vendor-class	16	vendor-class
vendor-opts	17	vendor-opts (see also cablelabs-17)
vpn-id	68	binary; 2 fields: flags and vpn-id



**Note** There are also multiple instance options (that is, you may configure more than one instance of the option - not just multiple values in a single option). The options that can have multiple instances are:

- ia-na
- ia-pd
- ia-ta
- iaaddr
- iaprefix
- rdnss-selection
- s46-br
- s46-cont-mape
- v6-pcp-server

## **Request Dictionary**

The table below lists the data items that you can set in the request dictionary at any time. The DHCP server reads them at various times. Unless indicated otherwise, all operations are read/write.

#### Table 5: Request Dictionary Specific Data Items

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
active-leasequery-control	int (v4,v6)	
Controls the sending of a lease (such as only on specific state changes). Values are: 0—unspecified (the server determines whether to send the notification), 1—send (the server will send the notification), and 2—do not send (the server will not send the notification). The <i>active-leasequery-control</i> is initialized as 0, that is, unspecified.		
allow-bootp	int (v4)	
If set to 1, allows BOOTP for any scope for this reque for lease acceptability.	est. Read during scope selection and while checking	
allow-dhcp	int (v4)	
If set to a 1, allows DHCP for any scope for this requ for lease acceptability.	est. Read during scope selection and while checking	
allow-dynamic-bootp	int (v4)	
If set to a 1, allows dynamic BOOTP for any scope for checking for lease acceptability.	or this request. Read during scope selection and while	
bootp-reply-options	blob (v4)	
Overrides any <i>v4-bootp-reply-options</i> in any policy; read when gathering data for the output packet. (There are no IPv6 bootp-reply-options.)		
client-class-name	string (v4, v6)	
Name of the client-class used to complete the client in	nformation (if any). Read-only.	
<i>client-class-policy</i> string (v4, v6)		
Name of the policy that is associated with the client-class. If set, it must be with the name of a policy that was already configured in the server.		
client-domain-name	string (v4, v6)	
Domain name that the client wants to use. If it does not exist, in which case the DHCP server uses the domain name specified in the scope. Read when queuing the request for DNS update just prior to the update of stable storage. For DHCPv6, overrides the client-fqdn value and used for DNS updates.		
client-host-name	string (v4, v6)	
Hostname for the client in DNS; read when queuing in the request for a DNS update just before updating stable storage. Places the actual name in DNS when that operation finishes. For DHCPv6, overrides the client-fqdn value and used for DNS updates.		
client-id	blob (v4, v6)	

	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
	lient. Can be the client-id sent with a request or internally <i>ted-from-mac-address</i> . For DHCPv6, the Client Identifier
nt-id-created-from-mac-address int (v4)	
If set to 1, the <i>client-id</i> must be created for internal not be used in reporting.	use from the client-supplied MAC address and should
client-ipaddress	IP address (v4)
IP address from which the client sent its packet. No IP address.	te that it could be zero if the client does not yet have an
client-limitation-id	blob (v4, v6)
Limitation ID for the client.	
client-lookup-id	blob (v4, v6)
Client lookup ID calculated by the client-lookup-id	expression of the client-class.
client-mac-address	blob (v4)
MAC address stored in the client object associated was created from) the <i>mac-address</i> .	with the request dictionary. Has the same format (and
client-os-type	int (v4)
• • • • • •	ting this at the <b>pre-client-lookup</b> or <b>post-client-lookup cceptable</b> , but cannot be set there. To set the value, you e request dictionary.
client-packet	blob (v4, v6, read-only)
The client portion of the received packet. For DHC the client message. (See packet to obtain the full pa	Pv4, this is the complete packet. For DHCPv6, this is cket.)
client-policy	string (v4, v6)
Name of the policy that is associated with the client in the DHCP server.	entry. If set, must be the name of a preconfigured policy
client-port	int (v4, v6)
Port from which the client sent its request.	
client-requested-host-name	string (v4)
Hostname that the client requested be used for the I so that a change can be detected.	DNS update. The DHCP server saves this information
client-unicast	boolean (v6, read-only)

I

	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
True if the received packet was unicast by	y the client to the server.	
client-wants-nulls-in-strings	int (v4)	
server terminates strings with a null. If se	turns strings to the client terminated with a null. If set to 1, the et to 0, it does not terminate strings with a null. Set before before the response packet after <b>pre-packet-encode</b> .	
derived-vpn-id	int (v4, v6, read-only)	
VPN identifier. See vpn-name for details.	· · · · · · · · · · · · · · · · · · ·	
destination-ipaddress	IP address (v6, read-only)	
Destination IPv6 address of the packet.		
dhcp-reply-options	blob (v4, v6)	
Overrides any <i>v4-reply-options</i> or <i>v6-reply-options</i> specified in a policy; read when gathering data for the output packet.		
dump-packet	int (v4, v6, write-only)	
	istrar dumps the current decoded DHCP/BOOTP packet to the log o this data item at multiple points in its execution. This might be	
failover-role	int (v4, v6, read only)	
• • None—Failover is not configur	failover server role can be one of three values: red. figured and the role of the failover server.	
failover-state	int (v4, v6, read only)	
	ver state can be normal, partner-down, communications-interrupted, startup, or paused. If failover is not configured the value is none.	
	ver state can be normal, partner-down, communications-interrupted,	
recover, potential-conflict, recover-done, <i>import-packet</i> Determines whether the server treats the treats the client as an import client and po	ver state can be normal, partner-down, communications-interrupted, startup, or paused. If failover is not configured the value is none.	
recover, potential-conflict, recover-done, <i>import-packet</i> Determines whether the server treats the treats the client as an import client and per when checking the server import mode (reference)	ver state can be normal, partner-down, communications-interrupted, startup, or paused. If failover is not configured the value is none. int (v4) packet as if it came from an import client. If set to 1, the server erforms all DNS operations on it before sending an ACK. Read	
recover, potential-conflict, recover-done, <i>import-packet</i> Determines whether the server treats the treats the client as an import client and po when checking the server import mode (ri and when setting the reply address.	ver state can be normal, partner-down, communications-interrupted, startup, or paused. If failover is not configured the value is none. int (v4) packet as if it came from an import client. If set to 1, the server erforms all DNS operations on it before sending an ACK. Read ight after <b>post-packet-decode</b> ), getting ready for DNS processing, int (v4)	
recover, potential-conflict, recover-done, <i>import-packet</i> Determines whether the server treats the treats the client as an import client and po when checking the server import mode (ri and when setting the reply address. <i>limitation-count</i>	ver state can be normal, partner-down, communications-interrupted, startup, or paused. If failover is not configured the value is none. int (v4) packet as if it came from an import client. If set to 1, the server erforms all DNS operations on it before sending an ACK. Read ight after <b>post-packet-decode</b> ), getting ready for DNS processing, int (v4)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
limitation-id-null	int (v4, v6)	
Set to 1(TRUE) if the <i>limitation-id</i> is null, 0 (FALSE) if another value.		
log-client-criteria-processing	int (v4, v6)	
If set to a 1, logs the criteria processing for the client for this request. Read when trying to acquire a new lease for a client that does not have one, and when checking for lease acceptability.		
log-client-detail	int (v4, v6)	
If set to a 1, logs the client-class processing for this re <b>post-client-lookup</b> .	equest. Read at the end of client-class processing, after	
log-dns-update-detail	int (v4, v6)	
If set to a 1, logs DNS update details for this request		
log-dropped-bootp-packets	int (v4)	
If set to a 1, logs dropped BOOTP packets for this re	quest.	
log-dropped-dhcp-packets	int (v4, v6)	
If set to a 1, logs dropped DHCP packets for this req	uest.	
log-dropped-waiting-packets	int (v4, v6)	
If set to a 1, logs dropped waiting packets for this red	quest.	
log-failover-detail	int (v4)	
If set to a 1, logs a more detailed level of failover activity, such as all failover state changes.		
log-incoming-packet-detail	int (v4, v6)	
If set to a 1, checks whether detailed incoming packet tracing occurred for this request, so that you do not need to put a separate trace on it. Read before packet decoding and the first extension point.		
log-incoming-packets	int (v4, v6)	
If set to a 1, logs the incoming packets for this request. Read after <b>post-decode-packet</b> .		
log-ldap-create-detail	int (v4)	
If set to a 1, logs messages whenever the DHCP server initiates a lease state entry creation to, receives a response from, or retrieves a result or error message from an LDAP server.		
log-ldap-query-detail	int (v4, v6)	
If set to a 1, logs messages whenever the DHCP server initiates a query to, receives a response from, or retrieves a query result or an error message from an LDAP server.		
log-ldap-update-detail	int (v4)	
	1	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
If set to a 1, logs messages whenever the DHCP server initiates an update lease state to, receives a response from, or a retrieves a result or error message from an LDAP server.		
log-leasequery	int (v4, v6)	
If set to a 1, logs messages when leasequery packets are processed without internal errors and result in an ACK or a NAK.		
log-missing-options	int (v4, v6)	
If set to a 1, logs missing options (those a client requirement of a set of the response.	uests but the DHCP server cannot return). Read while	
log-outgoing-packet-detail	int (v4, v6)	
If set to a 1, logs a detailed dump of the outgoing pac- just before sending the packet to the DHCP client.	ket for this request. Read after <b>pre-packet-encode</b> and	
log-success-messages	int (v4, v6)	
If set to a 1, logs the success messages.		
log-unknown-criteria	int (v4, v6)	
If set to a 1, logs any unknown criteria specified in the Read when acquiring a new client lease or checking	ne client inclusion or exclusion criteria for this request. lease acceptability for an existing client.	
log-v6-lease-detail	int (v6)	
If set to 1, logs individual messages about DHCPv6 leasing activity.		
mac-address	blob (v4)	
MAC address that came in the client packet. The first byte is the hardware type, the second is the hardware length, and the remaining (up to 16) is the information from the <i>chaddr</i> read just after <b>post-packet-decode</b> . This is a useful aggregation of the <i>htype</i> , <i>hlen</i> , and <i>chaddr</i> fields of the DHCP packet. When read it is constructed from these fields; when written it is placed into these fields.		
max-client-lookups	integer (v4, v6)	
Maximum number of client database lookups allowed. Usually a small integer such as 2; the preset value is 1.		
override-client-id	blob (v4, v6)	
Blob used for the current client-id value. Replaces any client-id from the incoming packet (although both values are kept in the lease state database).		
override-client-id-data-type	string (v4, v6, read-only)	
Returns the data type of the override-client-id, eithe	r "nstr" for string or "blob" for blob.	
override-client-id-string	string (v4, v6)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
e	replaces any client-id from the incoming packet (although both For a <i>get</i> , if the <i>override-client-id</i> is not a string, the binary data rned as the "string."	
packet blob (v4, v6)		
relayed or the same as <i>client-packet</i> if not re-	he same as <i>client-packet</i> . For DHCPv6, this is the full packet if clayed. It should only be written from the pre-packet-decode is new packet instead of the packet received from the client.	
ping-clients	int (v4)	
If set to a 1, performs a ping before offering a lease for this request. Read just before determining if a lea is acceptable for a client.		
relay-agent-circuit-id	blob (v4, v6)	
Contents of the circuit-id suboption of option 82.		
relay-agent-circuit-id-data	blob (v4, v6)	
Contents of just the data part of the circuit-id suboption of option 82.		
relay-agent-device-class-data	blob (v4, v6)	
Contents of the device-class suboption of option 82.		
relay-agent-radius-attributes	blob (v4)	
Contents of the radius suboption of option 82.		
relay-agent-radius-class	string (v4)	
Encapsulated <i>class</i> attribute of the radius suboption of option 82.		
relay-agent-radius-pool-name	string (v4)	
Encapsulated <i>framed-pool</i> attribute of the ra	dius suboption of option 82.	
relay-agent-radius-user	string (v4)	
Encapsulated <i>user</i> attribute of the radius suboption of option 82.		
relay-agent-remote-id	blob (v4, v6)	
Contents of the remote-id suboption of option	on 82.	
relay-agent-remote-id	blob (v4, v6)	
Contents of just the data part of the remote-	id suboption of option 82.	
relay-agent-server-id-override-data	IPv6 address (v4, v6)	
	I	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Contents of the server-id suboption of option 82. If the IANA suboption 182 is in the packet, that value appears; otherwise, the Cisco suboption 152 value appears.		
relay-agent-subscriber-id	string (v4)	
Contents of the subscriber-id suboption of opt	ion 82.	
relay-count	int (v6, read-only)	
Number of DHCPv6 relay hops.		
reply-options	blob	
Overrides any DHCPv4 reply options specified in any policy. Read when gathering data for the output packet.		
reply-to-client-address	int (v4, v6)	
	e packet to the client-ipaddress and the client-port. For v6, if ck to the address and port of the sender (client or relay agent). FC mandated algorithm.	
reserved-addresses	IP address (v4, read/write)	
List of addresses reserved for the client. The finance <i>restrict-to-reservations</i> enabled) will be a	irst available address to match a usable Scope (which must assigned to the client.	
reserved-ip6addresses	IP address (v6, read/write)	
List of addresses reserved for the client. All available addresses to match a usable Prefix (which must hav <i>restrict-to-reservations</i> enabled) will be assigned to the client.		
reserved-prefixes	IP address (v6, read/write)	
List of prefixes reserved for the client. All ava restrict-to-reservations enabled) will be assign	ilable prefixes to match a usable Prefix (which must have ned to the client.	
selection-criteria	string (v4, v6)	
Comma-separated string that contains the scop	be selection criteria.	
selection-criteria-excluded	string (v4, v6)	
Comma-separated string that contains the scope exclusion criteria.		
send-ack-first	int (v4, v6)	
This data item is ignored by the server. Howev ignored. It defaults to 0 (false).	ver, for backward compatibility, it can be read or set but is	
source-ipaddress	IPv6 address (v6, read-only)	
IPv6 source address of the packet.	1	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
trace-id	string (v4, v6, read-only)	
ID used by the system to trace the packet.		
transaction-time	int (v4, v6)	
Time, in seconds since 1970, that the input packet was decoded.		
update-dns	string (v4, v6)	
Requests partial, full, or no dynamic DNS updates on a per-request packet basis. Input and output values are: 1=update-all, 2=update-fwd-only, 3=update-rev-only, and 0=update-none.		
update-dns-for-bootp	int (v4)	
If set to a 1, updates DNS for BOOTP requests for this request. Read just before initializing the DNS operation for BOOTP.		
verbose-logging	int (v4, v6)	
If set to a 1, logs verbose messages for this request. Read at various times during processing.		
vpn-description	string (v4, v6, read-only)	
Description for the VPN. See <i>vpn-name</i> for details.		
vpn-name	string (v4, v6, read-only)	
Name of the VPN. The request dictionary does not have valid values for these items at <b>post-packet-decode</b> , but does at all other extension points, because the VPN has not yet been determined. This is so that a script can change the <i>derived-vpn-id</i> option or suboption at <b>post-packet-decode</b> and thereby affect the VPN used for a lease.		
vpn-vpn-id	blob, typically 7 bytes (v4, v6, read-only)	
Virtual private network identifier. See <i>vpn-name</i> for details.		
vpn-vrf-name	string (v4, v6, read-only)	
Virtual routing and forwarding table identifier for the VPN. See <i>vpn-name</i> for details.		

# **Response Dictionary**

The table below lists the data items you can set in the response dictionary at any time. The DHCP server reads them at various times. Unless indicated otherwise, the operation is read/write.

Table 6: Response Dictionary Specific Data Items

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
active-leasequery-control	int (v4,v6)

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
server determines whether to send the notificati	n specific state changes). Values are: 0—unspecified (the ion), 1—send (the server will send the notification), and tification). The <i>active-leasequery-control</i> is initialized as 0,
client-active-lease-count	int (v6, read-only)
Number of active leases on the DHCPv6 client.	
client-creation-time	int (v4, v6, read-only)
Creation time of the client.	
client-domain-name	string (v4, read-only)
	main name that the client wants to use. It might not exist, in ame specified in the scope. Read when queuing the request e storage.
client-expiration-time	int (v4, v6, read-only)
The highest lease expiration time given to the c	lient by this server (in seconds, since 1970).
client-host-name	string (v4, read-only)
From the client information in the lease, the ho queueing the request for a DNS update just bef	stname that the DHCP server puts into DNS. Read when ore updating stable storage.
client-id	blob (v4, v6, read-only)
	ent identification that the server used to keep track of the equest or internally generated from the MAC address. For e client's DUID).
client-id-created-from-mac-address	int (v4, read-only)
From the client information in the lease. If set to should not be used in reporting.	o 1, the <i>client-id</i> must be created from the MAC address and
client-last-transaction-time	int (v4, v6, read-only)
Time, in seconds, since 1970, that the DHCP se	erver last heard from this client.
client-limitation-id	blob (v4, read-only)
Limitation identifier of the client associated with	th the current lease.
client-mac-address	blob (v4, read-only)
From the client information in the lease, the M. request dictionary. Has the same format as (and	AC address stored in the client object associated with the I was created from) the <i>mac-address</i> .
client-os-type	int (v4)

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
	setting this at the <b>pre-client-lookup</b> or <b>post-client-lookup</b> e-acceptable, but cannot be set there. To set the value, you ode request dictionary.
client-override-client-id	blob (v4, v6, read-only)
Blob used for the current client-id value. Replace values are kept in the lease state database).	es any client-id from the incoming packet (although both
client-override-client-id-data-type	string (v4, v6, read-only)
Returns the data type of the <i>client-override-clien</i>	<i>ut-id</i> , either nstr for string or <i>blob</i> for blob.
client-override-client-id-string	string (v4, v6, read-only)
	aces any client-id from the incoming packet (although both get, if the <i>client-override-client-id</i> is not a string, the binary rned as the "string."
client-packet	blob (v4, v6, read-only)
1 1 1	HCPv4, this is the complete packet. For DHCPv6, this is packet.) Only available from the post-packet-encode
client-reconfigure-key	string (v6)
Returns the <i>client-reconfigure-key</i> attribute value	e of the DHCPv6 lease.
client-reconfigure-key- generation-time	string (v6)
Returns the <i>client-reconfigure-key-generation-tim</i>	<i>ne</i> attribute value of the DHCPv6 lease.
client-relay-address	IPv6 address (v6, read-only)
Source IPv6 address for the (last) relay.	
client-relay-message	string (v6, read-only)
Last relayed DHCPv6 message, excluding the cl	ient message.
client-requested-host-name	string (v4)
From the client information in the lease, the host	tname that the client requested for the DNS update.
client-user-defined-data	string (v4, v6, read-only)
environment dictionary data item. It returns the p	extension point. It returns the current value if requested in
client-vendor-class	string (v4, v6)

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Returns the <i>client-vendor-class</i> attribute value of the DHCPv4 or DHCPv6 lease.		
client-vendor-info	string (v4, v6)	
Returns the <i>client-vendor-info</i> attribute value of the DHCPv4 or DHCPv6 lease.		
client-write-sequence	int (v6, read-only)	
Write sequence of the client IPv6 request.		
client-write-time	int (v6, read-only)	
Time of the client IPv6 write request.		
derived-vpn-id	int (v4, v6, read-only)	
VPN identifier.		
domain-name-changed	int (v4)	
If set to 1, the domain name in the current packet differs from the domain name used in the DNS update. Read after <b>check-lease-acceptable</b> and before <b>pre-packet-encode</b> .		
dump-packet	int (v4, v6, write-only)	
When set to 1, Cisco Prime Network Registrar dumps the current decoded DHCP/BOOTP packet to the log file. An extension can put the value 1 into this data item at multiple points in its execution. This might be useful when debugging extensions.		
failover-role	int (v4, v6, read only)	
<ul> <li>Determines the failover server role. The failover server role can be one of three values:</li> <li>• None—Failover is not configured.</li> </ul>		
• Main/Backup—Failover is configured and the role of the failover server		
failover-state	int (v4, v6, read only)	
Determines failover server state. The failover state can be normal, partner-down, communications-interrupted, recover, potential-conflict, recover-done, startup, or paused. If failover is not configured the value is none.		
host-name-changed	int (v4)	
If set to 1, the hostname in the current packet differs from that used in the DNS update. Read after <b>check-lease-acceptable</b> and before <b>pre-packet-encode</b> .		
host-name-in-dns	int (v4, v6)	
If set to 1, the hostname is in DNS. Read after <b>check-lease-acceptable</b> and before <b>pre-packet-encode</b> . Written after the hostname goes into DNS.		
lease-binding-iaid	int (v6, read-only)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
IPv6 lease binding IAID.		
lease-binding-rebinding-time	int (v6, read-only)	
IPv6 lease binding rebinding time.		
lease-binding-renewal-time	int (v6, read-only)	
IPv6 lease binding renewal time.		
lease-binding-type	string (v6, read-only)	
IPv6 lease binding type: "IA_NA", "IA_TA", or "IA_PD".		
lease-client-reserved	int (v4, v6, read-only)	
Returns 1 if the lease is client reserved and 0 if not.		
lease-creation-time	string (v6, read-only)	
IPv6 lease creation time.		
lease-deactivated	int (v4, v6, read-only)	
If set to 1, reports that the lease is deactivated.		
lease-dns-forward-backup-server-address	IP address (v4, v6, read-only)	
Address of the backup DNS server that receives DNS updates for the DHCPv4 and DHCPv6 lease, if the server specified in <i>lease-dns-forward-server-address</i> is down.		
lease-dns-forward-server-address	IP address (v4, v6, read-only)	
Address of the DNS server that receives dynamic DNS updates for the DHCPv4 and DHCPv6 lease.		
lease-dns-forward-update	string (v4, v6, read-only)	
Name of the update configuration that determines the forward zones to be included in DNS updates for the DHCPv4 and DHCPv6 lease. Returns TRUE if <i>update-all</i> or <i>update-fwd-only</i> is set.		
lease-dns-forward-zone-name	string (v4, v6, read-only)	
Name of an optional forward zone for DNS updates.		
lease-dns-reverse-backup-server-address	IP address (v4, v6, read-only)	
Address of the backup DNS server that receives DNS updates for a DHCPv4 and DHCPv6 lease, if the server specified in <i>lease-dns-reverse-server-address</i> is down.		
lease-dns-reverse-host-bytes	int (v4, read-only)	
The number of bytes in a lease IP address to use for	a reverse zone.	
lease-dns-reverse-prefix-length	int (v6, read-only)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Prefix length of the reverse zone for ip6.arpa updates.		
lease-dns-reverse-server-address	IP address (v4, v6, read-only)	
Address of the DNS server address that receives dynamic DNS updates for the DHCPv4 and DHCPv6 lease.		
lease-dns-reverse-update	string (v4, v6, read-only)	
Name of the update configuration that determines which reverse zones to include in a DNS update for the DHCPv4 and DHCPv6 lease. Returns TRUE if <i>update-all</i> or <i>update-fwd-only</i> is set.		
lease-dns-reverse-zone-name	string (v4, v6, read-only)	
DNS reverse (in-addr.arpa and ip6.arpa) zone that is u	updated with PTR records.	
lease-fqdn	string (v6, read-only)	
Fully qualified domain name assigned to the DHCPv6 into DNS).	lease by the server (and possibly successfully entered	
The <i>lease-fqdn</i> may be the name that is expected to be added to DNS for the lease or the actual name added. If <i>host-name-in-dns</i> is equal to true, the actual <i>lease-fqdn</i> is in DNS.		
lease-giaddr	IP address (v4, read-only)	
Lease giaddr.		
lease-ipaddress	IPv4 or IPv6 address or prefix (v4, v6, read-only)	
For DHCPv4, the address of the lease associated with the client. For DHCPv6, the IPv6 address or IPv6 prefix (address and prefix-length) of the lease for the current context (See setObject method).		
lease-preferred-lifetime	int (v6, read-only)	
Preferred lifetime of the IPv6 lease.		
lease-prefix-name	string (v6, read-only)	
Prefix name of the IPv6 lease.		
lease-relay-agent-info	blob (v4)	
Entire contents of option 82.		
lease-relay-agent-circuit-id	blob (v4)	
Accesses and manipulates the relay agent circuit ID as stored with the lease of a response. Requires the suboption number 1 as the first byte. Deprecated in favor of the <i>lease-relay-agent-circuit-id-data</i> item.		
lease-relay-agent-circuit-id-data	blob (v4, use instead of deprecated <i>lease-relay-agent-circuit-id</i> )	
Accesses and manipulates the <i>relay-agent-circuit-id-data</i> as stored with the lease of a response.		
lease-relay-agent-device-class-data	blob (v4)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Contents of the device-class suboption of option 82.		
lease-relay-agent-radius-attributes	blob (v4)	
Contents of the radius suboption of option 82.		
lease-relay-agent-radius-class	string (v4)	
Encapsulated <i>class</i> attribute of the radius suboption of option 82.		
lease-relay-agent-radius-pool-name	string (v4)	
Encapsulated <i>framed-pool</i> attribute of the radius subo	option of option 82.	
lease-relay-agent-radius-user	string (v4)	
Encapsulated <i>user</i> attribute of the radius suboption of option 82.		
lease-relay-agent-remote-id	blob (v4)	
Accesses and manipulates the <i>relay-agent-remote-id</i> data as stored with the lease of a response. Requires suboption number 2 as the first byte. Deprecated in favor of the <i>lease-relay-agent-remote-id-data</i> item.		
lease-relay-agent-remote-id-data	blob (v4, use instead of <i>lease-relay-agent-remote-id</i> item)	
Accesses and manipulates the relay-agent-remote-id-	<i>data</i> as stored with the lease of a response.	
lease-relay-agent-server-id- override-data	IP address (v4)	
Accesses and manipulates the <i>relay-agent-server-id-override-data</i> as stored with the lease of a response.		
lease-relay-agent-subnet- selection-data	IP address (v4)	
Accesses and manipulates the <i>relay-agent-subnet-selection-data</i> as stored with the lease of a response.		
lease-relay-agent-subscriber-id	string (v4)	
Contents of the subscriber-id suboption of option 82.		
lease-relay-agent-vpn-id-data	blob (v4)	
Accesses and manipulates the <i>relay-agent-vpn-id</i> data as stored with the lease of a response.		
lease-requested-fqdn	string (v6, read-only)	
Partial or fully qualified domain name most recently requested by the client for the DHCPv6 lease.		
lease-requested-prefix-length	int (v6, read-only)	
The recorded client's requested prefix length, if provi did not send in a request for a specific prefix length.	ded, for a IA_PD binding. This may be 0 if the client	
lease-reserved	int (v4, v6, read-only)	

I

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Returns 1 if the lease is lease reserved and 0 if not.		
lease-start-time-of-state	int (v4, v6, read-only)	
Time, in seconds since 1970, that this lease was first placed into its current state.		
lease-state	string (v4, v6, read-only)	
State of the lease, which can be available, offered, leased, expired, unavailable, released, other-available (DHCPv4 only), pending-available (DHCPv4 only), or revoked (DHCPv6 only).		
lease-state-expiration-time	int (v4, v6, read-only)	
Expiration time of the lease state.		
lease-status	string (v4, v6, read-only)	
Returns "nonexistent," "owned-by-client," or "exists." Used to determine if a lease exists and if the current client owns it. If "exists" is returned, the lease exists but the current owner does not own it (limited information on the lease is available).		
lease-valid-lifetime	int (v6, read-only)	
Valid lifetime of the IPv6 lease.		
lease-vpn-description	string (v4, v6, read-only)	
Description for the VPN stored with the lease of a response.		
lease-vpn-id	int (v4, v6, read-only)	
Identifier for the VPN stored with the lease of a response.		
lease-vpn-name	string (v4, v6, read-only)	
Name of the VPN stored with the lease of a response.		
lease-vpn-vpn-id	blob, typically 7 bytes (v4, v6, read-only)	
Virtual private network (VPN) identifier stored with the lease of a response.		
lease-vpn-vrf-name	string (v4, v6, read-only)	
Virtual routing and forwarding table identifier for the VPN stored with the lease of a response.		
mac-address	blob (v4)	
MAC address that came in the client packet. The first byte is the hardware type, the second is the hardware length, and the remaining (up to 16) is the information from the <i>chaddr</i> . This is a useful aggregation of the <i>htype</i> , <i>hlen</i> , and <i>chaddr</i> fields of the DHCP packet. When read it is constructed from these fields; when written it is placed into these fields.		
override-client-id	blob (v4, v6, read-only)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
Blob used for the current client-id value. Replace values are kept in the lease state database).	ces any client-id from the incoming packet (although both	
override-client-id-data-type	string (v4, v6, read-only)	
Returns the data type of the <i>override-client-id</i> , either "nstr" for string or "blob" for blob.		
override-client-id-string	string (v4, v6, read-only)	
Current client-ID value in string format that repl values are kept in the lease state database).	aces any client-id from the incoming packet (although both	
For a <i>get</i> , if the <i>override-client-id</i> is not a string returned as the "string."	, the binary data is formatted as blob data, which is then	
packet	blob (v4, v6, use only at <b>post-packet-decode</b> )	
relayed or the same as client-packet if not relayed	ame as client-packet. For DHCPv6, this is the full packet if ed. It should only be read or written from the he server will then send the new packet to the client.	
ping-clients	int (v4)	
If set to 1, performs a ping before offering a lease acceptability.	se for this request. Read just before determining a client	
prefix-address	IPv6 prefix (v6, read-only)	
Prefix address (17 bytes—IPv6 address and prefix length).		
prefix-allocate-random	int (v6, read-only)	
Prefix randomly allocated.		
prefix-allocate-via-best-fit	int (v6, read-only)	
Prefix allocated via the best fit.		
prefix-allocate-via-client-request	int (v6, read-only)	
Prefix allocated via client request.		
prefix-allocate-via-extension	int (v6, read-only)	
Prefix allocated via an extension.	I	
prefix-allocate-via-interface- identifier	int (v6, read-only)	
Prefix allocated via an interface identifier.	I	
prefix-allocate-via-reservation	int (v6, read-only)	
Prefix allocated via a reservation.	1	

I

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
prefix-allocation-group	string (v6, read-only)	
Allocation group name for the prefix.		
prefix-allocation-group-priority	int (v6, read-only)	
Allocation group priority for the prefix.		
prefix-deactivated	int (v6, read-only)	
Indicates if the prefix is deactivated.		
prefix-dhcp-type	string (v6, read-only)	
Prefix DHCP type.		
prefix-expiration-time	string (v6, read-only)	
Expiration time of the prefix.		
prefix-link-group-name	string (v6, read-only)	
Link group name for the link.		
prefix-link-name	string (v6, read-only)	
Link of the prefix.		
prefix-link-type	string (v6, read-only)	
Link type (topological, location-independent, or universal).		
prefix-name	string (v6, read-only)	
Name of the prefix.		
prefix-range	IPv6 address (v6, read-only)	
IPv6 address range of the prefix.		
prefix-range-end	IPv6 address (v6, read-only)	
Prefix's range-end (if either range-start or range-end is configured).		
prefix-range-start	IPv6 address (v6, read-only)	
Prefix's range-start (if either <i>range-start</i> or <i>range-end</i> is configured).		
prefix-restrict-to-reservations	int (v6, read-only)	
If set to 1, the prefix has <i>restrict-to-reservations</i> enabled.		
prefix-selection-tags	string (v6, read-only)	
Selection tags of the prefix.		

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
relay-count	int (v6, read-only)
Number of DHCPv6 relay hops.	
reply-ipaddress	IPv4 or IPv6 address (v4, v6)
value in a <b>pre-packet-encode</b> , the IP addr queries (unless it is a broadcast address).	ICP client. Read just after <b>pre-packet-encode</b> . If you change its ess you place in it should be for a system that can respond to ARP Even if unicast is enabled and the broadcast flag is not set in the t set with a mapping from a new <i>reply-ipaddress</i> in the n the DHCP request.
reply-port	int (v4, v6)
Port to use when replying to the DHCP cl	ient. Read just after <b>pre-packet encode</b> .
response-source	string (v4, v6, read-only)
client packet), failover (Received binding grace period end), operator (Request from	ity that invoked the extension). Output values are: client (Received update from the failover partner), timeout (Lease expiration or a user interface), one-lease-per-client (One lease per client se of a new one), unknown (None of the above).
-	mine what processing it should do whether a request dictionary is so be used to determine whether a dictionary is valid.)
reverse-name-in-dns	int (v4, v6)
If equal to 1, the reverse name is in DNS.	Read before initializing a DNS operation.
scope-allow-bootp	int (v4, read-only)
If set to 1, the scope allows BOOTP. Written after a DNS operation finishes.	
scope-allow-dhcp	int (v4, read-only)
If set to 1, the scope allows DHCP.	
scope-allow-dynamic-bootp	int (v4, read-only)
If set to 1, the scope allows dynamic BOC	)TP.
scope-available-leases	int (v4, read-only)
Number of available leases on the current	scope.
scope-deactivated	int (v4, read-only)
If set to 1, the scope is deactivated.	
scope-dns-forward-server-address	IP address (v4, read-only)

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)	
scope-dns-forward-zone-name	string (v4, read-only)	
Forward zone name configured in the scope.		
scope-dns-number-of-host-bytes	int (v4, read-only)	
Number of host bytes used by the DHCP server code that handles DNS updates.		
scope-dns-reverse-server-address	IP address (v4, read-only)	
DNS server to use for the DNS reverse address.		
scope-dns-reverse-zone-name	string (v4, read-only)	
Reverse zone name configured in the scope.		
scope-name	string (v4, read-only)	
Name of the scope that contains the lease the DHCP server is processing.		
scope-network-number	IP address (v4, read-only)	
Network number of the scope that contains the lease the DHCP server is processing.		
scope-ping-clients	int (v4, read-only)	
If set to 1, the scope associated with the current lease offering a lease.	e was configured to support a ping operation prior to	
scope-primary-network-number	IP address (v4, read-only)	
Network number of this primary scope.		
scope-primary-subnet-mask	IP address (v4, read-only)	
Subnet mask of this primary scope.		
scope-renew-only	int (v4, read-only)	
If set to 1, the scope is renew-only.		
scope-renew-only-expire-time	int (v4, read-only)	
Absolute time, in seconds since January 1, 1970, at which a renew-only scope should cease to be renew-only		
scope-restrict-to-reservations	int (v4, read-only)	
If set to 1, the scope has restrict-to-reservations enab	bled.	
scope-selection-tags	string (v4, read-only)	
Comma-separated string that contains the scope selection criteria. Use this data item for decisions based of scopes.		
scope-send-ack-first	int (v4, read-only)	

Data Item	Value (Protocol: v4=DHCPv4, v6=DHCPv6)
If set to 1, the scope sends an ACK before performin	ng the rest of the processing.
scope-subnet-mask	IP address (v4, read-only)
Subnet mask of the scope that contains the lease the	DHCP server is processing.
scope-update-dns	string (v4, read-only)
DNS updates for forward or reverse zones. Output v 3=update-rev-only, and 0=update-none.	alues are: 1=update-all, 2=update-fwd-only,
scope-update-dns-enabled	boolean (v4, read-only)
If set to 1, the scope has update DNS enabled for for <i>scope-update-dns</i> .	rward and reverse zones. Deprecated in favor of
scope-update-dns-for-bootp	int (v4, read-only)
If set to 1, the scope has update DNS enabled for BC	DOTP.
trace-id	string (v4, v6, read-only)
ID used by the system to trace the packet.	
transaction-time	int (v4, v6, read-only)
Time, in seconds since 1970, that the request was de	ecoded.
vpn-description	string (v4, v6, read-only)
Description for the VPN.	
vpn-name	string (v4, v6, read-only)
Name of the VPN.	
vpn-vpn-id	blob, typically 7 bytes (v4, v6, read-only)
Virtual private network (VPN) identifier.	1
vpn-vrf-name	string (v4, v6, read-only)
Virtual routing and forwarding table (VRF) identified	er for the VPN.

# **Extension Dictionary API**

This section contains the dictionary method calls to use when accessing dictionaries from Tcl extensions and shared libraries.

## **Tcl Attribute Dictionary API**

In an attribute dictionary, the keys are constrained to be the names of attributes as defined in the Cisco Prime Network Registrar DHCP server configuration. The values are the string representation of the legal values for that particular attribute. For example, IP addresses are specified by the dotted-decimal string representation of the address, and enumerated values are specified by the name of the enumeration. This means that numbers are specified by the string representation of the number.

Attribute dictionaries are unusual in that they can contain more than one instance of a key. These instances are ordered, with the first instance at index zero. Some of the attribute dictionary methods allow an index to indicate a particular instance or position in the list of instances to be referenced.

### **Tcl Request and Response Dictionary Methods**

Attribute dictionaries use commands with which you can change and access the values in the dictionaries. The table below lists the commands to use with the request and response dictionaries. In this case, you can define the *dict* variable as **request** or **response**.

See the *install-path*/examples/dhcp/tcl/tclextension.tcl file for examples.

#### Table 7: Tcl Request and Response Dictionary Methods

Method	Syntax
get	\$dict get attribute [index [bMore ]]

Returns the value of the attribute from the dictionary, represented as a string. If the dictionary does not contain the attribute, the empty string is returned instead. If you include the index value, this returns the *index* th instance of the attribute. Some attributes can appear more than once in the request or response packet. The index selects which instance to return.

If you include the *bMore*, the **get** method sets *bMore* to TRUE if there are more attributes after the one returned, otherwise to FALSE. Use this to determine whether to make another call to **get** to retrieve other instances of the attribute.

getOption	\$dict getOption arg-type [arg-data]
arg-type values. If the next argument is a numeric	Tcl arg-type and obj-type Values, on page 40 for the value, it is assumed to be a number, otherwise a name. a string, which can be zero length if the option does not Handling Vendor Class Option Data, on page 55.
isValid isV4 isV6	\$dict isValid \$dict isV4 \$dict isV6
The <b>isValid</b> method returns TRUE if there is a requ FALSE otherwise. Extensions such as <b>lease-state-</b>	test or response (depending on the dictionary passed in);

dictionary is available.

The **isV4** method returns TRUE if this extension is being called for a DHCPv4 packet; FALSE otherwise. Calling this method from an **init-entry** routine returns FALSE.

The **isV6** method returns TRUE if this extension is being called for a DHCPv6 packet; FALSE otherwise. Calling this method from an **init-entry** routine returns FALSE.

log	\$dict log level message
-----	--------------------------

Method		Syntax
		m. The level should be LOG_ERROR, LOG_WARNING, catenated and sent to the logging system at the specified
Note	file with messages logged at these levels	NING levels sparingly, because the server flushes its log . Using these levels for messages that are likely to occur have severe impact on disk I/O performance.
moveTe	oOption	\$dict moveToOption arg-type [arg-data]
obj-typ		<b>ove</b> option operations. See Table 8: Tcl arg-type and es. Note that the context can become invalid if the option
put		\$dict <b>put</b> attribute value [index ]
REPLA index va of insta attribute	CE, this replaces any existing instances of alue as the special value APPEND, this app nces of the attribute. If you include the inde	ary. If you omit the index or set it to the special value the attribute with the single value. If you include the pends a new instance of the attribute to the end of the list ex value as a number, this inserts a new instance of the dex value to the special value AUGMENT, this puts the
auroun	e only if there is not one uncady.	
putOpt		\$dict putOption data arg-type [arg-data ]
<b>putOpt</b> Adds ar	ion n option and its data or modifies the data for ge 40 for the <i>arg-type</i> values. For sample us	\$ <i>dict</i> <b>putOption</b> <i>data arg-type</i> [ <i>arg-data</i> ] an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on
putOpt Adds ar , on pag	tion n option and its data or modifies the data for ge 40 for the <i>arg-type</i> values. For sample us	an option. See Table 8: Tcl arg-type and obj-type Values
putOpt Adds ar , on pag page 55 remove Remove this rem instance	ion n option and its data or modifies the data for ge 40 for the <i>arg-type</i> values. For sample us is, es the attribute from the dictionary. If you or noves any existing instances of the attribute	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on
putOpt Adds ar , on pag page 55 remove Remove this rem instance	ion n option and its data or modifies the data for ge 40 for the <i>arg-type</i> values. For sample us the set the attribute from the dictionary. If you or noves any existing instances of the attribute e of the attribute at the position indicated. T tain that attribute at that index.	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on <i>\$dict</i> remove <i>attribute</i> [ <i>index</i> ] nit the index or set it to the special value REMOVE_ALL, e. If you include the index as a number, this removes the
putOpt Adds ar , on pag page 55 remove this rem instance not con remove Remove	ion n option and its data or modifies the data for the 40 for the <i>arg-type</i> values. For sample us the attribute from the dictionary. If you or noves any existing instances of the attribute the of the attribute at the position indicated. The tain that attribute at that index.	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on <i>\$dict</i> remove <i>attribute</i> [ <i>index</i> ] mit the index or set it to the special value REMOVE_ALL, the
putOpt Adds ar , on pag page 55 remove this rem instance not con remove Remove	ion n option and its data or modifies the data for the 40 for the <i>arg-type</i> values. For sample us is es the attribute from the dictionary. If you or hoves any existing instances of the attribute the of the attribute at the position indicated. The tain that attribute at the position indicated. The tain that attribute at that index. Coption es an option. See Table 8: Tcl arg-type and usage, see the Handling Vendor Class Option	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on <i>\$dict</i> remove <i>attribute</i> [ <i>index</i> ] mit the index or set it to the special value REMOVE_ALL, the index or set it to the special value REMOVE_ALL, fyou include the index as a number, this removes the This method always returns 1, even if the dictionary does <i>\$dict</i> removeOption <i>arg-type</i> [ <i>arg-data</i> ] obj-type Values , on page 40 for the <i>arg-type</i> values. For
putOpt Adds ar , on pag page 55 remove Remove this rem instance not con remove Remove sample setObje (DHCPv link, or scope a	ion a option and its data or modifies the data for the 40 for the <i>arg-type</i> values. For sample us is es the attribute from the dictionary. If you or hoves any existing instances of the attribute the of the attribute at the position indicated. The tain that attribute at the position indicated. The tain that attribute at that index. <b>Option</b> es an option. See Table 8: Tcl arg-type and usage, see the Handling Vendor Class Option ect v6 only.) Sets the object for <b>get</b> , <b>put</b> , and <b>re</b> nethods operate. See Table 8: Tcl arg-type fo extensions primarily use this method to a to get message header fields or options from re associated with a response, a DHCPv6 r	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on <i>\$dict</i> remove <i>attribute</i> [ <i>index</i> ] mit the index or set it to the special value REMOVE_ALL, e. If you include the index as a number, this removes the This method always returns 1, even if the dictionary does <i>\$dict</i> removeOption <i>arg-type</i> [ <i>arg-data</i> ] obj-type Values , on page 40 for the <i>arg-type</i> values. For ion Data, on page 55.
putOpt Adds ar , on pag page 55 remove Remove this rem instance not con remove Remove sample setObje (DHCP option r DHCPv link, or scope a	ion a option and its data or modifies the data for the 40 for the <i>arg-type</i> values. For sample us i. es the attribute from the dictionary. If you or hoves any existing instances of the attribute the of the attribute at the position indicated. The tain that attribute at the position indicated. The tain that attribute at that index. <b>Option</b> es an option. See Table 8: Tcl arg-type and usage, see the Handling Vendor Class Option est v6 only.) Sets the object for <b>get</b> , <b>put</b> , and <b>re</b> methods operate. See Table 8: Tcl arg-type v6 extensions primarily use this method to a to get message header fields or options from re associated with a response, a DHCPv6 r f the object exists; FALSE otherwise. For s	an option. See Table 8: Tcl arg-type and obj-type Values sage, see the Handling Vendor Class Option Data, on \$dict remove attribute [index ] nit the index or set it to the special value REMOVE_ALL, and the index or set it to the special value REMOVE_ALL, and the index or set it to the special value REMOVE_ALL, and the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, and the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, but the index or set it to the special value REMOVE_ALL, access the leases and prefixes available for the client and an relay packets. Unlike in DHCPv4, where one lease and esponse can involve several leases and prefixes. Returns

Method	Syntax
Returns a message in the DHCP server packet tracing system. At level 0, no tracing occurs. At level 1, it	
traces only that the server received the packet and sent a reply. At level $\Lambda$ it traces everything. The remaining	

traces only that the server received the packet and sent a reply. At level 4, it traces everything. The remaining arguments are concatenated and sent to the tracing system at the specified level. The default tracing is set using the DHCP server *extension-trace-level* attribute.

#### Table 8: Tcl arg-type and obj-type Values

arg-type or obj-type	Description
enterprise number/name	Enterprise-id number or name for the option definition set for the option or suboption.
home	Requests that the context is reset to the "top" of the current client or relay message.
index number/keyword	Number or keyword (replace, append, augment, raw, or remove_all) for the array index on which to operate.
index-count	Returns the number of array index entries in the option.
instance number	Instance number of the option (primarily used for DHCPv6).
instance-count	Returns the number of times the option appears (if 0, the option is not present).
<b>more</b> tcl-variable-name	Name of a Tcl variable that is set to TRUE or FALSE, depending on whether more array index entries exist in the option data.
move-to	Requests that the context be set to the option.
option number/name	Option number or name to operate on.
parent	Requests that the context is moved up one option.
suboption number/name	Suboption number or name to operate on.
vendor name	Vendor name for the option definition set for the option or suboption.
<b>lease initial</b>   <i>index</i>   <i>address</i>   <i>prefix</i>	Used with <b>setObject</b> , sets the context for the lease, binding, and prefix data items in the response dictionary to the indicated lease. The <b>initial</b> keyword requests that the original context for when the extension was called is restored. The <i>index</i> requests that the numbered lease (starting at 0) is set and can be used to iterate through all of the leases for the client. The <i>address</i> or <i>prefix</i> requests that the lease with that address or prefix is set (if it exists).
message initial   number	Used with <b>setObject</b> , sets the context for the message data items and options in the request or response dictionary to the indicated message. The <b>initial</b> keyword sets the context to the client message. The <i>number</i> sets the context to the relay message, with 0 specifying the relay closest to the client.

arg-type or obj-type	Description
<b>prefix initial</b>   <i>index</i>   <i>address</i>   <i>prefix</i>   <i>name</i>	Used with <b>setObject</b> , sets the context for the prefix data items in the response dictionary to the indicated prefix. The <b>initial</b> keyword requests that the original context for when the extension was called is restored. The <i>index</i> requests the numbered prefix (starting at 0) is set and can be used to iterate through all of the prefixes for the client on the link. The <i>address</i> or <i>prefix</i> requests that the prefix for the address or prefix is set (if found). The <i>name</i> requests that the named prefix is found. Note that only prefixes on the current link can be used.

### **Tcl Environment Dictionary Methods**

The table below describes the commands to use with the environment dictionary. In this case, you can define the *dict* variable as **environ**, as in the following procedure example:

```
proc tclhelloworld2 { request response environ } {
$environ put trace-level 4
$environ log LOG_INFO "Environment hello world"
}
```

Table 9: Tcl Environment Dictionary Methods

Method		Syntax
clear		\$dict clear
Removes al	l entries from the dictionary.	
containsKe	У	\$dict containsKey key
Returns 1 if	the dictionary contains the key, otherwise	e 0.
firstKey		\$dict firstKey
	name of the first key in the dictionary. No ist, returns the empty string.	te that the keys are not stored sorted by name. If a key
get		\$dict get key
Returns the	value of the key from the dictionary. If a	key does not exist, returns the empty string.
isEmpty		\$dict isEmpty
Returns 1 if	the dictionary has no entries, otherwise (	).
log		\$dict log level message
LOG_WAR		m. The <i>level</i> should be one of LOG_ERROR, guments are concatenated and sent to the logging
fi	Use the LOG_ERROR and LOG_WARNING levels sparingly, because the server flushes its log file with messages logged at these levels. Using these levels for messages that are likely to occur frequently (such as client requests) can have severe impact on disk I/O performance.	

Method	Syntax
nextKey	\$dict nextKey
Returns the name of the next key in the or <b>nextKey</b> . If a key does not exist, retu	dictionary that follows the key returned in the last call to <b>firstKey</b> urns the empty string.
put	\$dict put key value
Associates a value with the key, replaci	ng an existing instance of the key with the new value.
remove	\$dict remove key
Removes the key from the dictionary. A	Always returns 1, even if the dictionary did not contain the key.
size	\$dict size
Returns the number of entries in the dic	ctionary.
trace	\$dict trace level message
	packet tracing system. At level 0, no tracing occurs. At level 1, it acket and sent a reply. At level 4, it traces everything. The remaining

### **DEX Attribute Dictionary API**

When writing DEX extensions for C/C++, you can specify keys as the attribute name string representation or by type (a byte sequence defining the attribute). This mean that some of these access methods have four different variations that are the combinations of string or type for the key or value.

arguments are concatenated and sent to the tracing system at the specified level. The default tracing is set

A basic DEX extension example might be:

using the DHCP server extension-trace-level attribute.

```
int DEXAPI dexhelloworld( int iExtensionPoint,
dex_AttributeDictionary_t *pRequest,
dex_AttributeDictionary_t *pResponse,
dex_EnvironmentDictionary_t *pEnviron )
{
    pEnviron->log( pEnviron, DEX_LOG_INFO, "hello world" );
    return DEX_OK;
  }
```

See the *install-path*/examples/dhcp/dex/dexextension.c file or other files in that directory for examples.

#### **DEX Request and Response Dictionary Methods**

DEX attribute dictionaries use active commands, called methods, with which you can change and access values. The table below lists the methods to use with the request and response dictionaries. In this case, you can define the *pDict* variable as **pRequest** or **pResponse**, as in:

```
pRequest->get( pRequest, "host-name", 0, 0 );
```

The *pszAttribute* is the **const char** \* pointer to the attribute name that the application wants to access. The *pszValue* is the pointer to the **const char** \* string that represents the data (returned for a **get** method, and stored in a **put** method). See the corresponding *iObjectType*, *iObjArgType*, and *iArgType* tables, respectively.

 $\mathcal{P}$ 

**Tip** See also the Differences in get, put, Option, Bytes, and OptionBytes Methods, on page 48 and the Differences in get, put, remove, and ByType Methods, on page 49.

Table 10: DEX Request and Response Dictionary Methods

Method	Syntax
allocateMemory	<pre>void *pDict-&gt;allocateMemory(     dex_AttributeDictionary_t *pDict, unsigned int     iSize )</pre>
Allocates memory in extensions that persists only fo	r the lifetime of this request.
get	<pre>const char *pDict-&gt;get( dex_AttributeDictionary_t *pDict, const char *pszAttribute, int iIndex, abool_t *pbMore)</pre>
dictionary does not contain the attribute (or that man If <i>pbMore</i> is nonzero, the <b>get</b> method sets <i>pbMore</i> to	ibute from the dictionary, represented as a string. If the y instances of it), the empty string is returned instead. TRUE if there are more instances of the attribute after termine whether to make another call to <b>get</b> to retrieve
getBytes	<pre>const abytes_t *pDict-&gt;getBytes( dex_AttributeDictionary_t *pDict, const char *pszAttribute, int iIndex, abool_t *pbMore )</pre>
getBytesByType	<pre>const abytes_t *pDict-&gt; getBytesByType( dex_AttributeDictionary_t *pDict,const abytes_t *pszAttribute, int iIndex, abool_t *pbMore )</pre>
dictionary does not contain the attribute (or that man nonzero, sets the variable pointed to TRUE if there are	ibute from the dictionary as a sequence of bytes. If the y instances of it), 0 is returned instead. If <i>pbMore</i> is re more instances of the attribute after the one returned, to make another call to <b>get</b> to retrieve other instances
getByType	<pre>const char *pDict-&gt;getByType( dex_AttributeDictionary_t *pDict, const abytes_t *pszAttribute, int iIndex, abool_t *pbMore )</pre>

I

Method	Syntax
dictionary does not contain the attribute (or the <i>pbMore</i> is nonzero, the <b>getByType</b> method set	the attribute from the dictionary, represented as a string. If the hat many instances of it), returns the empty string instead. If ets <i>pbMore</i> to TRUE if there are more instances of the attribute se this to determine whether to make another call to <b>getByType</b>
getOption	<b>const char * getOption( dex_AttributeDictionary_t</b> *pDict, <b>int</b> <i>iArgType</i> , )
	hat this function always returns a pointer to a string, which can has length zero. To find out if the option exists, use E_COUNT.
getOptionBytes	<pre>const abytes_t * getOptionBytes(     dex_AttributeDictionary_t *pDict, int iArgType, )</pre>
	ytes. Note that this function returns a null pointer if the option ength buffer if the option exists but is zero bytes long.
getType	<pre>const abytes_t * pDict-&gt;getType( dex_AttributeDictionary_t* pDict, const char* pszAttribute )</pre>
Returns a pointer to the byte sequence definit attribute, otherwise 0.	ng the attribute, if the attribute name matches a configured
isValidisV4isV6	abool_t isValid( dex_AttributeDictionary_t *pDict )abool_t isV4( dex_AttributeDictionary_t *pDict )abool_t isV6( dex_AttributeDictionary_t *pDict )
	a request or response (depending on the dictionary passed in); state-change can use this method to determine whether a
The <b>isV4</b> method returns TRUE if this extens Calling this method from an <b>init-entry</b> routin	sion is being called for a DHCPv4 packet; FALSE otherwise. he returns FALSE.
The <b>isV6</b> method returns TRUE if this extens Calling this method from an <b>init-entry</b> routin	tion is being called for a DHCPv6 packet; FALSE otherwise. ne returns FALSE.
log	<b>abool_t</b> <i>pDict</i> ->log( dex_AttributeDictionary_t * <i>pDict</i> , int <i>eLevel</i> , const char * <i>pszFormat</i> , )
DEX_LOG_WARNING, or DEX_LOG_INF	ng system. The <i>eLevel</i> should be one of DEX_LOG_ERROR, O. The <i>pszFormat</i> is treated as a printf style format string, and prmatted and sent to the logging system at the specified level.
flushes its log file with messages lo	DEX_LOG_WARNING levels sparingly, because the server gged at these levels. Using these levels for messages that are ient requests) can have severe impact on disk I/O performance.

Method	Syntax
moveToOption	abool_t moveToOption( dex_AttributeDictionary_t *pDict, int iArgType, )
Sets the context for subsequent <b>get</b> , <b>put</b> invalid if the option is removed (such as	<b>t</b> , and <b>remove</b> option operations. Note that the context can become s with <b>removeOption</b> ).
put	<b>abool_t</b> <i>pDict-&gt;</i> <b>put( dex_AttributeDictionary_t</b> * <i>pDict</i> , <b>const char</b> * <i>pszAttribute</i> , <b>const char</b> * <i>pszValue</i> , <b>int</b> <i>iIndex</i> )
configuration. Associates that sequence value DEX_REPLACE, replaces any ex value DEX_APPEND, it appends a new DEX_AUGMENT, puts the attribute or	es, according to the definition of <i>pszAttribute</i> in the server e of bytes with the attribute in the dictionary. If <i>iIndex</i> is the special xisting instances of the attribute with a single value. If the special v instance of the attribute to its list. If the special value ally if there is not one already. Otherwise, inserts a new instance at inless the attribute name does not match any configured attributes or gal value.
putBytes	<pre>abool_t pDict-&gt;putBytes(     dex_AttributeDictionary_t *pDict, const char     *pszAttribute, const abytes_t *pszValue, int iIndex )</pre>
replaces any existing instances of the att appends a new instance of the attribute	<i>tte</i> in the dictionary. If <i>iIndex</i> is the special value DEX_REPLACE, tribute with a single new value. If the special value DEX_APPEND, to its list. If the special value DEX_AUGMENT, puts the attribute ise, inserts a new instance at the position indicated. Returns TRUE th a configured one.
putBytesByType	<pre>abool_t pDict-&gt;putBytesByType( dex_AttributeDictionary_t *pDict, const abytes_t *pszAttribute, const abytes_t *pszValue, int iIndex )</pre>
replaces any existing instances of the at appends a new instance of the attribute	<i>tte</i> in the dictionary. If <i>iIndex</i> is the special value DEX_REPLACE, ttribute with the new value. If the special value DEX_APPEND, to its list. If the special value DEX_AUGMENT, puts the attribute ise, inserts a new instance of the attribute at the position indicated.
putByType	<pre>abool_t pDict-&gt;putByType(     dex_AttributeDictionary_t *pDict, const abytes_t  *pszAttribute, const char *pszValue, int iIndex )</pre>
configuration. Associates that sequence value DEX_REPLACE, replaces any ex	es, according to the definition of <i>pszAttribute</i> in the server e of bytes with the attribute in the dictionary. If <i>iIndex</i> is the special isting instances of the attribute with a single new value. If the special instance of the attribute to its list. If the special value

Method	Syntax
putOption	<b>abool_t putOption( dex_AttributeDictionary_t</b> *pDict, <b>const char</b> *pszValue, <b>int</b> iArgType, )
Adds an option and its data or modifies the da	ata for an option.
putOptionBytes	<b>abool_t putOptionBytes</b> ( <b>dex_AttributeDictionary_t</b> * <i>pDict</i> , <b>const abytes_t</b> * <i>pValue</i> , <b>int</b> <i>iArgType</i> , )
Adds an option and its data or modifies the da	ata for an option.
remove	<b>abool_t</b> <i>pDict</i> -> <b>remove</b> ( <b>dex_AttributeDictionary_t</b> * <i>pDict</i> , <b>const char</b> * <i>pszAttribute</i> , <b>int</b> <i>iIndex</i> )
any existing instances of the attribute. Otherw	<i>iIndex</i> is the special value DEX_REMOVE_ALL, removes vise, removes the instance at the position indicated. Returns that attribute at that index, unless the attribute name does not
removeByType	<pre>abool_t pDict-&gt;removeByType(     dex_AttributeDictionary_t *pDict, const abytes_t     *pszAttribute, int iIndex )</pre>
	<i>index</i> is the value DEX_REMOVE_ALL, removes any existing the instance at the position indicated. Always returns TRUE, tribute at that index.
removeOption	<b>abool_t removeOption</b> ( dex_AttributeDictionary *pDict, int <i>iArgType</i> , )
Removes an option. Note that if you omit DE assumed (this removes the entire option).	X_INDEX, a DEX_INDEX of DEX_REMOVE_ALL is
setObject	<b>abool_t setObject</b> ( dex_AttributeDictionary_t *pDict, int iObjectType, int iObjArgType, )
operate. DHCPv6 extensions primarily use th client and link, or to get message header field one lease and scope are associated with a resp	ods, and alters the message on which the new option methods is method to access the leases and prefixes available for the s or options from relay packets. Unlike in DHCPv4, where ponse, a DHCPv6 response can involve several leases and ALSE otherwise. For sample usage, see the Handling Object
<b>Note</b> For leases not associated with the c	urrent client, only minimal information is available.
trace	<b>abool_t</b> <i>pDict</i> -> <b>trace</b> ( <b>dex_AttributeDictionary_t</b> * <i>pDict</i> , <b>int</b> <i>iLevel</i> , <b>const char</b> * <i>pszFormat</i> , )
traces only that the server received the packet a	t tracing system. At level 0, no tracing occurs. At level 1, it and sent a reply. At level 4, it traces everything. The remaining acing system at the specified level. The default tracing is set attribute.

### **DEX Environment Dictionary Methods**

The environment dictionary uses active commands, called *methods*, with which you can change and access the dictionary values. The table below lists the methods to use with the environment dictionary. In this case, you can define the *pDict* variable as **pEnviron**, as in:

pEnviron->log( pEnviron, DEX\_LOG\_INFO, "Environment hello world");

#### Table 11: DEX Environment Dictionary Methods

Method	Syntax
allocateMemory	<pre>void *pDict-&gt;allocateMemory(   dex_EnvironmentDictionary_t *pDict, unsigned   int iSize )</pre>
Allocates memory for extensions that persists only	for the lifetime of this request.
clear	<pre>void pDict-&gt;clear( dex_EnvironmentDictionary_t *pDict )</pre>
Removes all entries from the dictionary.	
containsKey	<pre>abool_t pDict-&gt;containsKey( dex_EnvironmentDictionary_t *pDict, const char *pszKey )</pre>
Returns TRUE if the dictionary contains the key, ot	herwise FALSE.
firstKey	<pre>const char *pDict-&gt;firstKey( dex_EnvironmentDictionary_t *pDict )</pre>
Returns the name of the first key in the dictionary. N does not exist, returns zero.	ote that the keys are not stored sorted by name. If a key
get	<pre>const char *pDict-&gt;get( dex_EnvironmentDictionary_t *pDict, const char *pszKey )</pre>
Returns the value of the key from the dictionary. If	a key does not exist, returns the empty string.
isEmpty	<pre>abool_t pDict-&gt;isEmpty( dex_EnvironmentDictionary_t *pDict )</pre>
Returns TRUE if the dictionary has 0 entries, otherw	vise FALSE.
log	<b>abool_t</b> <i>pDict</i> ->log( dex_EnvironmentDictionary_t * <i>pDict</i> , int <i>eLevel</i> , const char * <i>pszFormat</i> , )

Method	Syntax
DEX_LOG_WARNING, or DEX_LOG_INFO. The	m. The <i>eLevel</i> should be one of DEX_LOG_ERROR, <i>pszFormat</i> is treated as a printf style format string, and d and sent to the logging system at the specified level.
flushes its log file with messages logged at	DG_WARNING levels sparingly, because the server these levels. Using these levels for messages that are uests) can have severe impact on disk I/O performance.
nextKey	<pre>const char *pDict-&gt;nextKey( dex_EnvironmentDictionary_t *pDict )</pre>
Returns the name of the next key in the dictionary th or <b>nextKey</b> . If a key does not exist, returns zero.	at follows the key returned in the last call to <b>firstKey</b>
put	<b>abool_t</b> pDict->put( dex_EnvironmentDictionary_t *pDict, const char *pszKey, const char* pszValue )
Associates a value with the key, replacing an existing	g instance of the key with the new value.
remove	<pre>abool_t pDict-&gt;remove( dex_EnvironmentDictionary_t *pDict, const char *pszKey )</pre>
Removes the key and the associated value from the did did not contain the key.	actionary. Always returns TRUE, even if the dictionary
size	<pre>int pDict-&gt;size( dex_EnvironmentDictionary_t *pDict )</pre>
Returns the number of entries in the dictionary.	
trace	<b>abool_t</b> <i>pDict</i> -> <b>trace</b> ( <b>dex_EnvironmentDictionary_t</b> * <i>pDict</i> , <b>int</b> <i>iLevel</i> , <b>const char</b> * <i>pszFormat</i> , )
Returns a message in the DHCP server packet tracing traces only that the server received the packet and sen arguments are concatenated and sent to the tracing sy using the DHCP server <i>extension-trace-level</i> attribute	t a reply. At level 4, it traces everything. The remaining ystem at the specified level. The default tracing is set

#### Differences in get, put, Option, Bytes, and OptionBytes Methods

There are differences among the following DEX extension methods:

- get and put
- getOption and putOption
- getBytes and putBytes
- getOptionBytes and putOptionBytes

The **get** and **getOption** methods return the requested information formatted as a string. The server converts the data to the string depending on the expected data type for the dictionary item. If the data type is unknown, the server returns the data in blob string format.

The **getBytes** and **getOptionBytes** methods return the requested information as the raw bytes (a pointer to a buffer and the size of that buffer). The server should have to read this buffer only, and it contains only the data from the option (no null terminator has been added, for example).

The **put** and **putOption** methods expect the data to be written as a formatted string. The server converts the data from the string depending on the expected data type for the dictionary item. If the data type is unknown, it is expected to be in blob string format.

The server passes raw bytes to the **putBytes** and **putOptionBytes** methods (a pointer to a buffer and the size of that buffer). The server only reads these bytes.

#### Differences in get, put, remove, and ByType Methods

There are differences among the following DEX extension methods:

- get, put, and remove
- getByType, putByType, and removeByType

The server passes the **get**, **put**, and **remove** methods the name of the desired data item as a string. This requires that the server map the string to its internal data tables.

The server passes the **getByType**, **putByType**, and **removeByType** methods an internal data table reference, which the server must have previously obtained (such as in the extension init-entry) by calling the **getType** method on the string. This speeds processing for extensions, which can be important in applications requiring high performance.



Note

The internal data table that the **getType** method references is the same whether requested for the Request or Response dictionary. There is no need for separate **getType** calls on each dictionary for the same data item name.

iObjectType	Description
General definition: Object for which the co	ontext is to be changed.
DEX_LEASE	Changes the lease (and prefix) context. Response dictionary only. Allows <i>iObjArgType</i> :
	DEX_BY_IPV6ADDRESS
	DEX_BY_IPV6PREFIX
	DEX_BY_INSTANCE
	DEX_INITIAL
DEX_MESSAGE	Changes the message context to a relay message or the client message. Request and response dictionaries. Allows <i>iObjArgType</i> :
	DEX_INITIAL
	DEX_RELAY
	DEX_BY_NUMBER

#### Table 12: DEX iObjectType Values

iObjectType	Description
DEX_PREFIX	Changes the prefix context, but does not change the lease context. Response dictionary only. Allows <i>iObjArgType</i> :
	DEX_BY_IPV6ADDRESS
	DEX_BY_IPV6PREFIX
	DEX_BY_INSTANCE
	DEX_BY_NAME
	DEX_INITIAL

#### Table 13: DEX iObjArgType Values

iObjArgType	Description
General definition: By what means the context is to be changed.	
DEX_BY_INSTANCE	Used with DEX_LEASE or DEX_PREFIX <i>iObjectType</i> . Requires that <b>int</b> follows to specify the instance number (starting with 0). Used to walk through the list of all available objects, but only through the list of objects applicable to the current request or response: for DEX_LEASE, the leases for that client (if any); for DEX_PREFIX, the prefixes on the current link (if any). Used with DEX_MESSAGE, a synonym for DEX_RELAY.
DEX_BY_IPV6ADDRESS	Used with DEX_LEASE and DEX_PREFIX <i>iObjectType</i> only. Requires that <b>const unsigned char</b> * follows to specify the 16-byte address.
DEX_BY_IPV6PREFIX	Used with DEX_LEASE or DEX_PREFIX <i>iObjectType</i> . Requires that <b>const unsigned char</b> * follows to specify a 17-byte prefix buffer (16-byte address followed by a 1-byte prefix length).
DEX_BY_NAME	Used with the DEX_PREFIX <i>iObjectType</i> only. Requires that a <b>const char</b> * follows to specify the name of the desired object.
DEX_INITIAL	Resets the context back to the original for the request or response, and has no additional argument. Sets the lease and prefix (DEX_LEASE), prefix (DEX_PREFIX), or message (DEX_MESSAGE) to what it was when the extension was originally called (which can be none).

iObjArgType	Description
DEX_RELAY	Used with DEX_MESSAGE <i>iObjectType</i> only. Requires that <b>int</b> follows to specify the relay (0 specifies the relay closest to the client). To set the message context back to the client, use <b>setObject(</b> <b>pDict, DEX_MESSAGE, DEX_INITIAL</b> ).
iArgType	Description
General definition: Action and argument that follow instances in the calls.	s the context. There can be any number of <i>iArgType</i>
DEX_ARG_ARRAY	Requires that a pointer to an array of dex_OptionsArgs_t follow, and is an alternative to specifying the argument list. Each dex_OptionsArgs_t structure has two fields:
	<ul> <li><i>iArgType</i> —One of the <i>iArgType</i> DEX values in this table.</li> <li><i>pData</i> —Data (integer), pointer to the data (for strings and other data types), or ignored (if the <i>iArgType</i> takes no arguments).</li> </ul>
	Note that once the server encounters the DEX_ARG_ARRAY (in an argument list or in an array of <b>dex_OptionsArgs_t</b> ), it ignores any subsequent arguments in the original list.
DEX_END	<b>Note</b> Required, has no additional argument, and marks the end of the argument list.
DEX_ENTERPRISE_NAME	Requires that <b>const char</b> * follow to specify the option definition set name, from which the server extracts the enterprise-id to get the vendor option data. Valid only for vendor-identifying options. Requires that the vendor option definition set exists.
DEX_ENTERPRISE_ID	Requires that <b>int</b> follow to specify the enterprise-id for the vendor.
DEX_HOME	Moves the context back to the client or relay message options. Has no additional argument. Always returns success. If used, must be the first <i>iArgType</i> . Valid only for <b>getOption</b> , <b>getOptionBytes</b> , and <b>moveToOption</b> methods.

I

iArgType	Description
DEX_INDEX	Requires that <b>int</b> follow with the index of the option data (if any array of data is to be acted on). If omitted, index 0 is assumed, except for <b>removeOption</b> , in which case DEX_REMOVE_ALL is assumed. Use the special value DEX_RAW to get, put, or remove the entire option data. However, for the DHCPv4 Vendor-Identifying Vendor Options (RFC 3925 and RFC 4243), DEX_RAW returns the data for only one vendor (based on the instance or enterprise-id) and not that for the entire option.
	The DEX_RAW special value accesses the entire option (or suboption) data. It provides consistent access to the data, regardless of what the option definitions might specify in terms of the data type and repeat counts of the data type. It is recommended for general-purpose extensions that decode the data.
	Use the special values DEX_REPLACE (replace a value), DEX_APPEND (add to end), and DEX_AUGMENT (add if no value currently exists) with <b>putOption</b> and <b>putOptionBytes</b> methods, which operate the same as the <b>put</b> , <b>putByType</b> , <b>putBytes</b> , and <b>putBytesByType</b> methods. Use DEX_REMOVE_ALL for <b>removeOption</b> to remove the option completely.
DEX_INDEX_COUNT	Results in an <b>int</b> value returned with the count of the number of indexed entries of the option, rather than the option data. Has no additional argument, and cannot be used with DEX_INDEX or DEX_INSTANCE_COUNT. DEX_END must follow. Valid only for <b>getOption</b> and <b>getOptionBytes</b> .
DEX_INSTANCE	Requires that <b>int</b> follow to specify the instance of the option (valid only for DHCPv6 options, which can have more than one instance). 0 specifies the first instance.
DEX_INSTANCE_COUNT	Results in an <b>int</b> value returned with the count of the number of instances of the option, rather than the option data. Has no additional argument and cannot be used with DEX_INSTANCE. DEX_END must follow. Valid only for <b>getOption</b> and <b>getOptionBytes</b> .
DEX_MORE	Requires that <b>abool_t</b> * follow to specify the location at which a <b>more</b> flag is to be written. This location is set to TRUE if more array items exist beyond the index that DEX_INDEX specified. Valid only for <b>getOption</b> and <b>getOptionBytes</b> methods.

iArgType	Description
DEX_MOVE_TO	Leaves the context at the option or suboption immediately preceding DEX_MOVE_TO. Has no additional argument. If omitted, the context does not change. Use <b>moveToOption</b> to move the context without getting any data. Valid only for <b>getOption</b> and <b>getOptionBytes</b> methods.
	Note An attempt to move to an option or suboption that does not exist logs an error. Use <b>moveToOption</b> if your extension did not previously confirm that the option exists.
DEX_OPTION_NAME	Requires that <b>const char</b> * follow to specify the desired option name. Option names should be in the <b>dhcpv4-config</b> or <b>dhcpv6-config</b> option definition set.
DEX_OPTION_NUMBER	Requires that <b>const char</b> * follow to specify the desired option name. Option names should be in the <b>dhcpv4-config</b> or <b>dhcpv6-config</b> option definition set.
DEX_PARENT	Moves the context to the parent option. Has no additional argument. It does not move beyond the client or relay message and returns FALSE if the context does not change. If used, must be the first <i>iArgType</i> . Valid only for <b>getOption</b> , <b>getOptionBytes</b> , and <b>moveToOption</b> methods.
DEX_SUBOPTION_NAME	Requires that <b>const char</b> * follow to specify the name of the desired suboption. Suboptions must be in the current option definition.
DEX_SUBOPTION_NUMBER	Requires that <b>int</b> follow to specify the desired suboption number. Suboption numbers should be in the current option definition, although there is no requirement that a definition exists. However, if the suboption does not exist, it is assumed to be a byte blob of data.
DEX_VENDOR_NAME	Requires that <b>const char</b> * follow to specify the vendor string. The string serves only to find the appropriate option definition set.

# **Handling Objects and Options**

The following sections describe specialized ways of handling DHCP objects and options in extensions.

## **Using Object and Option Handling Methods**

Extensions can call methods to set DHCP objects, and get, move to, put, and remove DHCP options. The methods are **setObject**, **getOption**, **moveToOption**, **putOption**, and **removeOption** methods in Tcl and C/C++.

These new callback methods were introduced primarily to provide support for DHCPv6. However, you can use the option-related functions for DHCPv4. In fact, it is recommended to use these methods for DHCPv4, because they provide richer access to options than the original get[Bytes], get[Bytes]ByType, put[Bytes], put[Bytes]ByType, and remove[ByType] methods.

**Tip** See DEX Request and Response Dictionary Methods, on page 42 for the different usages of some of these methods in C/C++.

For DHCPv6, you must use the **setObject**, **getOption**, **moveToOption**, **putOption**, and **removeOption** methods to access options. The **setObject** method was introduced for DHCPv6, because there can be many leases, prefixes, and messages (client or multiple relay) that an extension might want to access. So, **setObject** serves to set the context for subsequent calls to get request and response dictionary data items and options. When the server calls an extension, the context is set to the current lease (if applicable), prefix (if applicable), and client message. For example, when the server calls the **pre-packet-encode** extension point, only the request and response dictionary message context is valid, and set to the corresponding client message, because there is no lease or prefix associated with this extension point. However, when the server calls the **lease-state-change** extension point, it sets the response dictionary lease context to the lease on which the state has changed, sets the response dictionary prefix context to the prefix for the lease, and sets the request and response dictionary message context to the corresponding client message.

### **Options and Suboptions in C/C++**

Some C/C++ extensions provide specialized argument type values to handle DHCP options and suboptions. The DEX\_OPTION\_\* argument type specifies to use the standard DHCPv4 or DHCPv6 option definition set and not the definitions under an option (or suboption). So, DEX\_OPTION\_\* means that the server looks up the option name or number in the standard DHCPv4 or DHCPv6 option definition set, whereas DEX\_SUBOPTION\_\* means that the server looks up the suboption name or number of the current option definition (if any).

Thus, when you access options in DHCPv6, you often use DEX\_OPTION\_\* followed by DEX\_OPTION\_\* when options are encapsulated. You would use DEX\_SUBOPTION when looking at vendor options. For DHCPv4, you would use DEX\_OPTION at the client packet level, and then DEX\_SUBOPTION perhaps one or more times, depending on the nesting level. Generally, only options have enterprise numbers or vendor names, but there is no prohibition on this. The option definition sets determine what is valid (although one can walk off definitions, at which point everything is treated as binary bytes and thus it limits what is possible, and you cannot use the option or suboption names, but must use numbers).

The option ordering rules for the **getOption**, **moveToOption**, **putOption**, and **removeOption** methods are similar to the **request** expression syntax. The ordering generally consists of:

- Preamble clause ([parent | home])
- Option clause (option [vendor | enterprise] [instance])
- Suboption clause (suboption [vendor | enterprise] [instance])
- End clause ([instance-count | index-count | [index] [more] end)

You can construct calls by using a preamble clause, followed by zero or more option clauses, followed by zero or more suboption clauses (which may themselves be followed by option and suboption clauses), followed by an end clause. Note that some things are possible only through a **get** method (such as **instance-count**, **index-count**, and **move-to** can appear anywhere to move the context to the current option or suboption.

The option definition determines its data format, which can differ from what the older functions return for a specific option. To handle specific options:

- For the vendor class options (*v-i-vendor-class* [124] for DHCPv4 and *vendor-class* [16] for DHCPv6), if you ask for a specific instance of the option (instead of by enterprise-id or name), the only way to get the enterprise-id is to ask for the raw data (DEX\_INDEX with DEX\_RAW).
- For the DHCPv4 vendor options (*v-i-vendor-class* [124] and *v-i-vendor-opts* [125]), operating on the raw data (DEX\_INDEX with DEX\_RAW) only applies to an instance (preset value 0) of that option, not the entire option. There is no way to get the entire data for this option, which means that you cannot use **putOption** for the entire data. This is not an issue with the DHCPv6 vendor options, because these are separate options.
- If one of the DHCPv4 vendor options (124 or 125) is not formatted properly, the entire data is returned as a blob (if you asked for instance 0 and did not specify a particular enterprise-id). However, if an extension tries to use **putOption**, depending on the operation, that data might be appended to the existing data, and the result will be formatted incorrectly.
- For the vendor options, if there is no option, **putOption( pDict, ''01:02'', DEX\_OPTION\_NUMBER, 124, DEX\_END )** fails because no enterprise-id is available. However, **putOption( pDict, ''00:00:00:09:04:03:65:66:67'', DEX\_OPTION\_NUMBER, 124, DEX\_END )** will work because it is assumed that 00:00:00:09 is the enterprise-id and the bytes following it starting with 04 are the length of the option data of that enterprise-id. Note that the length byte is validated in this case, and **putOption( pDict, ''65:66:67'', DEX\_OPTION\_NUMBER, 124, DEX\_ENTERPRISE\_ID, 9, DEX\_END )**.

# Examples of Option and Object Method Calls

These sections include some examples of how to use methods to handle DHCP option and object data.

## Handling Vendor Class Option Data

For DHCPv4, to include the Vendor-Identifying Vendor Class option (124) data for two enterprise-ids in the response to the client, here is some sample Tcl code that uses the **putOption** method:

```
$response putOption 65:66:67 option 124 enterprise 999998
#adds "abc" (65:66:67) under enterprise-id 999998
$response putOption 68:69:6a:6b option v-i-vendor-class enterprise 999998 index append
#appends "defg" (68:69:6a:6b) under the same enterprise-id
$response putOption 01:02:03:04 option 124 enterprise 999999
#adds 01:02:03:04 under enterprise-id 999999
```

To get the options, use the getOption method:

```
$response getOption option v-i-vendor-class instance-count
#returns 2 because there were two instances added (enterprise id 999998 and enterprise id
999999)
$response getOption option 124
#returns index 0 of instance 0, which is 65:66:67
```

\$response getOption option 124 index-count
#returns 2 because there were two vendor classes added for the first enterprise id (9999998)
\$response getOption option 124 index raw
#returns 00:0f:42:3e:09:03:65:66:67:04:68:69:6a:6b for the complete encoding of the
enterprise-id 999998 data (see RFC 3925)
\$response getOption option 124 index 1
#returns 68:69:6a:6b
\$response getOption option 124 instance 1 index-count
#returns 1 because there is only one vendor class
\$response getOption option 124 instance 1 index raw
#returns 00:0f:42:3f:05:04:01:02:03:04 for the complete encoding of the enterprise-id
999999 data (see RFC 3925)
\$response getOption option 124 enterprise 999999
#returns 01:02:03:04

To remove the data, two **removeOption** calls are necessary because of the two separate enterprise-ids:

```
$response removeOption option 124
$response removeOption option 124
```

### Handling Object Data

Suppose that at the **pre-packet-encode** extension point you want to extract data for all of the leases for the client. Here is sample Tcl code that uses the **setObject** method:

```
proc logleasesinit { request response environ } {
   if { [$environ get "extension-point"] == "initialize" } {
     # Set up for DHCPv6 only]
     $environ put dhcp-support "v6"
     $environ put extension-extensionapi-version 2
  }
3
proc logleases { request response environ } {
   for { set i 0 } { 1 } { incr i } {
     # Set context to next lease
     if { ![$response setObject lease $i] } {
     # Lease does not exist, so done
    break
  }
  # Log the lease address, prefix name, and prefix address
  $environ log LOG_INFO "Lease [$response get lease-ipaddress], Prefix\
     [$response get lease-prefix-name] - [$response get prefix-address]"
  # Restore the lease context to where we started
    Sresponse setObject lease initial
    # Do other things...
}
```

The C++ equivalent code for this might be:

```
// Print the current leases for the client
for( int i=0; ; i++ ) {
    if( !pRes->setObject( pRes, DEX_LEASE, DEX_BY_INSTANCE, i ) )
        break;
    const char *pszLeaseAddress =
        pRes->get( pRes, "lease-ipaddress", 0, 0 );
    if( pszLeaseAddress == 0 )
        pszLeaseAddress == columnation ();
    const char *pszPrefixName =
        pRes->get( pRes, "prefix-name", 0, 0 );
    if( pszPrefixName == 0 )
```

```
pszPrefixName = "<error>";
pEnv->log(pEnv, DEX_LOG_INFO,
    "Lease %s, Prefix %s",
    pszLeaseAddress, pszPrefixName );
}
```

I