



WAE Design GUI Installation

This section contains the following topics:

- [Overview, on page 1](#)
- [Prerequisites, on page 1](#)
- [Linux Installation, on page 2](#)
- [Verification of Digitally Signed Images, on page 2](#)
- [Start WAE Design, on page 3](#)

Overview

This section provides instructions for installing the WAE Design GUI. You additionally need to install the WAE Design license and if applicable, install the floating license server.

- [License Installation](#)—Information on how to install dedicated and floating licenses.
- [WAE Design Floating License Server](#)—Procedure for installing and setting up the FlexNet Publisher license server. This is needed only if administering floating licenses.

The installation process does not explain how to install any drivers or require any changes to the operating system. You can download and install the files to any folder or directory.

Prerequisites

The following are WAE design GUI installation prerequisites:

- A license is required for all features except for the example plan files. If you have questions about obtaining a license, contact your support representative or system administrator.
- Meet the necessary system requirements and package dependencies. For a list of these, see the “Installation Requirements” chapter in the *Cisco WAE Installation Guide*.
- If you are using the WAE Design GUI and the Parse Configs tool (File > Get Plan from > Configs), Java environment variables must be configured correctly, and JAVA_HOME or JRE_HOME must point to a valid JDK/JRE-11 installation.

For example:

- Linux—Enter the following command:

```
admin@system1 ~ # export JRE_HOME=<JDK/JRE_installation_path>
```

Linux Installation

Before you begin

Create an installation directory `/opt/cariden` or `/opt/wae` that has **wae** privileges.

-
- Step 1** Download the digitally signed Cisco WAE Design software package from the [Cisco download site](#).
 - Step 2** Verify and extract the digitally signed binary to a location of your choice. See [Verification of Digitally Signed Images, on page 2](#).
 - Step 3** Enter the following command:


```
./WAE-Design-k9-7.6.0-Linux-x86_64.bin
```
 - Step 4** Choose the installation directory that you created at the beginning.
 - Step 5** Install and verify the license. See [License Installation](#).
-

Verification of Digitally Signed Images

The Cisco WAE Design software is digitally signed. This is to ensure that the WAE Design software running on your systems is secure and has not been tampered with, and that the software originated from a trusted source.

Verify Signed Images for Linux

-
- Step 1** For Linux, the certificates and digital signatures are embedded in the downloaded files - `WAE-Design-k9-7.6.0-Linux-x86_64.signed.bin`.
 - Step 2** Run the self-extracting signed binary. This extracts the Release Binary and validates using the signature file.

Verification in Linux

```
[admin@wae-vm-21 workspace.signed]$ ./WAE-Design-k9-7.6.0-Linux-x86_64.signed.bin
Unpacking...
Verifying signature...
Downloading CA certificate from http://www.cisco.com/security/pki/certs/crcam2.cer ...
Successfully downloaded and verified crcam2.cer.
Downloading SubCA certificate from http://www.cisco.com/security/pki/certs/innerspace.cer ...
Successfully downloaded and verified innerspace.cer.
Successfully verified root, subca and end-entity certificate chain.
Successfully fetched a public key from WAE-CCO_RELEASE.cer.
Successfully verified the signature of WAE-Design-k9-7.6.0-Linux-x86_64.bin using WAE-CCO_RELEASE.cer
```
 - Step 3** The generated `WAE-Design-k9-7.6.0-Linux-x86_64.bin` is the Linux installer for WAE.

Run the Linux installer once more to extract the Linux binary.

Start WAE Design

To start WAE Design from the directory in which the WAE Design software is installed:

Step 1 Double-click the **wae_design** executable.

Step 2 From the CLI, enter:

```
./wae_design
```

(Optional) You can associate the plan file using the .pln format with the **wae_design** executable. Double-clicking a .pln file opens the plan in a new instance of the GUI.
