



G Commands

This chapter describes the Cisco Nexus 1000V commands that begin with the letter G.

Send document comments to nexus1k-docfeedback@cisco.com.

group (Port Profile Role)

To assign a group to a port profile role, use the **group** command. To remove the group, use the no form of the command.

```
group group_name
```

```
no group group_name
```

Syntax Description	group Specify that a group is to be added to the port-profile role, and the name of the group <i>group_name</i> (maximum of 32 characters).
---------------------------	---

Defaults	None
-----------------	------

Command Modes	Port profile role configuration (config-port-profile-role)
----------------------	--

SupportedUserRoles	network-admin
---------------------------	---------------

Command History	Release	Modification
	4.2(1)SV1(4)	This command was introduced.

Usage Guidelines

Examples This example shows how to assign the credit group to the supportRole:

```
n1000v# config t
n1000v(config)# port-profile-role supportRole
n1000v(config-port-profile-role)# group credit
```

This example shows how to remove the credit group assignment from the supportRole:

```
n1000v# config t
n1000v(config)# port-profile-role supportRole
n1000v(config-role)# no group credit
```

Related Commands	Command	Description
	show port-profile-role	Displays the port profile role configuration, including role names, descriptions, assigned users, and assigned groups.
	show port-profile-role users	Displays available users and groups.

Send document comments to nexus1k-docfeedback@cisco.com.

Command	Description
show port-profile	Displays the port profile configuration, including roles assigned to them.
port-profile-role	Creates a port profile role.
user	Assigns a user to a port profile role.
assign port-profile-role	Assigns a port profile role to a specific port profile.
feature port-profile-role	Enables support for the restriction of port profile roles.
port-profile	Creates a port profile.

Send document comments to nexus1k-docfeedback@cisco.com.

gunzip

To uncompress a compressed file, use the **gunzip** command.

gunzip *filename*

Syntax Description	<i>filename</i>	Name of a file. The filename is case sensitive.
---------------------------	-----------------	---

Defaults	None
-----------------	------

Command Modes	Any
----------------------	-----

SupportedUserRoles	network-admin
---------------------------	---------------

Command History	Release	Modification
	4.0(4)SV1(1)	This command was introduced.

Usage Guidelines	<p>The compressed filename must have the .gz extension.</p> <p>You do not have to enter the .gz extension as part of the filename.</p> <p>The Cisco NX-OS software uses Lempel-Ziv 1977 (LZ77) coding for compression.</p>
-------------------------	--

Examples	<p>This example shows how to uncompress a compressed file:</p> <pre>n1000v# gunzip run_cfg.cfg</pre>
-----------------	--

Related Commands	Command	Description
	dir	Displays the directory contents.
gzip	Compresses a file.	

Send document comments to nexus1k-docfeedback@cisco.com.

gzip

To compress a file, use the **gzip** command.

gzip *filename*

Syntax Description	<i>filename</i>	Name of a file. The filename is case sensitive.
---------------------------	-----------------	---

Defaults	None
-----------------	------

Command Modes	Any
----------------------	-----

SupportedUserRoles	network-admin
---------------------------	---------------

Command History	Release	Modification
	4.0(4)SV1(1)	This command was introduced.

Usage Guidelines	After you use this command, the file is replaced with the compressed filename that has the .gz extension. The Cisco NX-OS software uses Lempel-Ziv 1977 (LZ77) coding for compression.
-------------------------	--

Examples	This example shows how to compress a file: n1000v# gzip run_cfg.cfg
-----------------	---

Related Commands	Command	Description
	dir	Displays the directory contents.
gunzip	Uncompresses a compressed file.	

Send document comments to nexus1k-docfeedback@cisco.com.