



## Configuring Network Details

---

This chapter contains the following sections:

- [Configuring a Network Interface, on page 1](#)
- [Displaying Appliance Network Details, on page 2](#)

### Configuring a Network Interface

You can configure a network interface for the Cisco UCS Director appliance by choosing **Configure Network Interface**.

---

**Step 1** From the Cisco UCS Director Shell menu, choose **Configure Network Interface** and press **Enter**.

```
After configuring the network interface, you must restart the Cisco UCS Director services for the updated network configuration to be used.  
Do you want to Configure DHCP/STATIC IP [d/s] ? :
```

**Step 2** Choose one of the following configuration selections:

- Choose **d** to configure a DHCP IP address.
- Choose **s** to configure a static IP address.

**Step 3** To configure a static IP address, enter **s** and press **Enter**. The following information is displayed.

```
Configuring STATIC configuration..  
Enter the ethernet interface that you want to configure [ens192/ens224]:
```

**Step 4** Enter the Ethernet interface to configure (for example, ens192) and press **Enter**. The following information is displayed:

```
Do you want to configure IPv4 STATIC IP for ens192 [y/n]
```

**Step 5** Enter **y** and press **Enter**. The following information is displayed:

```
IP Address: 172.21.231.44  
Netmask: 255.255.255.192  
Gateway IP address: 172.21.231.1  
DNS Server1:  
DNS Server2:  
Configuring Network with : INTERACE(ens192), IP(172.21.231.44), Netmask(255.255.255.192),
```

```
Gateway(172.21.231.1),DNS Server1(), DNS Server2()
Do you want to continue [y/n]?
```

**Step 6** Enter **n** to discontinue the configuration process. Press **Enter** to complete the process.

**Step 7** To configure a DHCP IP address, enter **d** and press **Enter**. The following information is displayed.

```
Configuring DHCP configuration..
Enter the ethernet interface that you want to configure [ens192/ens224]:
```

**Step 8** Enter the Ethernet interface to configure (for example, ens224) and press **Enter**. The following information is displayed:

```
Do you want to configure IPv4 [v4]:
```

**Step 9** To configure IPv4, enter **v4** and press **Enter**. The following information is displayed:

```
Not in Static IP Mode
Do you want to configure DHCP [IPv4] for ens224 [y/n]?
```

**Step 10** Enter **y** to configure DHCP [IPv4] for ens224 and press **Enter**. The following information is displayed:

```
Configuring DHCP IP for ens224
Successfully configured DHCP IP for ens224
```

**Step 11** Press **Enter** to return to the main menu.

## Displaying Appliance Network Details

You can display the Cisco UCS Director appliance network details by choosing the **Display Network Details** option.

**Step 1** From the Cisco UCS Director Shell menu, choose the **Display Network Details** option and press **Enter**.

The following information is displayed:

```
Network details....
ens192
  Link encap:Ethernet HWaddr 00:50:56:97:1E:2D
  inet addr:192.0.2.23 Bcast:192.0.2.255 Mask:255.255.255.0
  inet6 addr: fe80::230:56gg:fe97:1e2d/64 Scope:Link
  UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
  RX packets:189818223 errors:14832 dropped:17343 overruns:0 frame:0
  TX packets:71520969 errors:0 dropped:0 overruns:0 carrier:0
  collisions:0 txqueuelen:1000
  RX bytes:105749301003 (98.4 GiB) TX bytes:27590555706 (25.6 GiB)
  Interrupt:59 Base address:0x2000

lo
  Link encap:Local Loopback
  inet addr:127.0.0.1 Mask:255.0.0.0
  inet6 addr: ::1/128 Scope:Host
  UP LOOPBACK RUNNING MTU:16436 Metric:1
  RX packets:1821636581 errors:0 dropped:0 overruns:0 frame:0
  TX packets:1821636581 errors:0 dropped:0 overruns:0 carrier:0
  collisions:0 txqueuelen:0
  RX bytes:327846827946 (305.3 GiB) TX bytes:327846827946 (305.3 GiB)
```

Press return to continue ...

**Step 2** Press **Enter** to complete the process.

---

