



CHAPTER 60

Mobility Profile

You can use Cisco Unified Communications Manager Bulk Administration Tool to add Mobility Profiles to the Cisco Unified Communications Manager database with a unique identity.


The following topics explain the options for managing mobility profiles:

- [Inserting Mobility Profile, page 60-1](#)
- [Deleting Mobility Profile, page 60-2](#)
- [Exporting Mobility Profile, page 60-3](#)

Inserting Mobility Profile

Use the following procedure to insert mobility profiles in bulk.

Procedure

-
- Step 1** Choose **Bulk Administration > Mobility > Mobility Profile > Insert Mobility Profile**. The Insert Mobility Profile Configuration window displays.
- Step 2** From the File Name drop-down list box, choose the CSV data file that you created for this specific bulk transaction.
-  **Note** For information on the Mobility Profile CSV file format, see [Mobility Profile File Format, page A-33](#).
-
- Step 3** Checking the Override the existing configuration check box, overwrites the existing Mobility Profile settings with the information that is contained in the file that you want to insert.
- Step 4** In the Job Information field, enter the Job description.
- Step 5** Click the Run Immediately radio button to insert the profile immediately or, click Run Later to insert it at a later time.
- Step 6** Click **Submit** to create a job for inserting the Mobility Profile.
- Step 7** Use the Job Scheduler option in the Bulk Administration main menu to schedule and activate this job. For more information on jobs, see [Chapter 82, “Scheduling Jobs.”](#). For information on log files, see [“BAT Log Files” section on page 83-3](#).

**Note**

If any information for a record fails, BAT does not insert that Mobility profile record.

Additional Information

- See the [“Related Topics”](#) section on page 60-4.

Deleting Mobility Profile

This section describes how to delete a Mobility Profile from the Cisco Unified Communications Manager database.

Before You Begin

Before you can delete a Mobility Profile from Cisco Unified Communications Manager Administration, you must do the following:

- Create a text file that lists each Mobility Profile that you want to delete on a separate line.
- Upload the custom file with the first node of the Cisco Unified Communications Manager server. See [Chapter 2, “Uploading and Downloading Files.”](#)

To delete mobility profiles by using a custom file, use the following procedure.

**Note**

Do not use the insert or export transaction files that are created with bat.xlt for the delete transaction. Instead, you must create a custom file with details of the Mobility Profile records that need to be deleted. Use only this file for the delete transaction. The custom delete file does not require a header and you can enter values for the name or description or mobile client calling option.

Procedure

-
- Step 1** Choose **Bulk Administration > Mobility > Mobility Profile > Delete Mobility Profile**. The Delete Mobility Profile Configuration window displays.
 - Step 2** From the Delete Mobility Profile where Name/Description/Mobile Client Calling Option in custom file drop-down list box, choose the file that you uploaded for deleting Mobility Profile.
 - Step 3** Click **Find**.
 - Step 4** The Job Information section displays along with the selected Mobility Profile.
 - Step 5** You can choose to run the job immediately or later by selecting the corresponding radio buttons.
 - Step 6** Click **Submit** to create a job for deleting the Mobility Profile.
A message in the Status section lets you know that the job was submitted successfully.
 - Step 7** Use the Job Scheduler option in the Bulk Administration main menu to schedule and/or activate this job.
-

Additional Information

- See the [“Related Topics”](#) section on page 60-4.

Exporting Mobility Profile

To export Mobility Profiles by using BAT, use the following procedure.

Procedure



Note If you are accessing help from the Export Mobility Profile Configuration window, skip to [Step 9](#).

- Step 1** Choose **Bulk Administration > Mobility > Mobility Profile > Export Mobility Profile**. The Find and List Mobility Profiles To Export window displays.
- Step 2** In the first Find Mobility Profile where drop-down list box, choose a field to query from the following options:
- Name
 - Description
 - Mobile Client Calling Option
- Step 3** In the second drop-down list box, choose from the following options:
- begins with
 - contains
 - is exactly
 - ends with
 - is empty
 - is not empty
- Step 4** In the search field box, enter the value that you want to locate, such as a specific profile name or profile description.
- Step 5** You can choose AND or OR to add multiple filters and repeat Step 2 through Step 4 to further define your query.
- Step 6** Click **Find**.
- All matching records display. You can change the number of items that display on each page by choosing a different value from the Rows per Page drop-down list box.
- Step 7** From the list of records that display, click the link for the record that you want to view.
- To find all the mobility profiles that are registered in the database, click **Find** without entering any search text. The window displays the record that you choose.
- Step 8** Click **Next**.
- The Export Mobility Profile Configuration window displays.
- Step 9** In the File Name text box, enter the Mobility Profile file name you intend to export.
- Step 10** From the File Format drop-down list box, choose the Mobility Profile file format.
- Step 11** In the Job Information area, enter the Job description.
- Step 12** Click the Run Immediately radio button to export mobility profiles immediately or, click Run Later to export at a later time.
- Step 13** Click **Submit** to create a job for exporting Mobility Profile.

- Step 14** Use the Job Scheduler option in the Bulk Administration main menu to schedule and/or activate this job. For more information on jobs, see [Chapter 82, “Scheduling Jobs.”](#)
For information on log files, see [“BAT Log Files” section on page 83-3.](#)
-

Additional Information

- See the [“Related Topics” section on page 60-4.](#)

Related Topics

- [Inserting Mobility Profile, page 60-1](#)
- [Deleting Mobility Profile, page 60-2](#)
- [Exporting Mobility Profile, page 60-3](#)