



## License Commands

---

- [license client reset registration, on page 1](#)
- [license file, on page 1](#)
- [license management change user name, on page 2](#)
- [license management reset user password, on page 2](#)
- [license management list users, on page 3](#)
- [license management product re-register all, on page 3](#)
- [license management reset, on page 3](#)
- [license management security update, on page 4](#)
- [license management service, on page 4](#)
- [license management set log level core\\_services, on page 5](#)
- [license management set log level product\\_instances, on page 5](#)
- [license management system remove, on page 6](#)
- [license management unlock admin, on page 6](#)

### license client reset registration

Use this command to reset the license client registration state to unregistered.

#### license client reset registration

---

##### Command Modes

Administrator (admin)

##### Requirements

Command privilege level: 1 and 4

Allowed during upgrade: No

Applies to: Cisco Prime License Manager

### license file

This command asks to select a license file from a list.

**license file diagnose | get**

#### Syntax Description

##### Parameters Description

**diagnose** Prints diagnostic information of the selected file.

**get** Creates a TAR file of the license file(s) on the system and transfers the TAR file to a remote area.

#### Command Modes

Administrator (admin:)

#### Requirements

Command privilege level for **diagnose** : 1 and 4

Command privilege level for **get** : 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management change user name

This command takes parameters interactively and changes the username of the administrator.

**license management change user name**

#### Syntax Description

##### Parameters Description

**name** Specifies the administrator username.

#### Command Modes

Administrator (admin:)

#### Requirements

Command privilege level: 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management reset user password

This command takes parameters interactively and changes the password of the administrator.

**license management reset user password**

#### Syntax Description

##### Parameters Description

**password** Specifies the administrator password.

---

**Command Modes** Administrator (admin:)**Requirements**

Command privilege level: 4

Allowed during upgrade: No

Applies to: Cisco Prime License Manager

## license management list users

This command lists the administrative users.

**license management list users**

---

**Command Modes** Administrator (admin:)**Requirements**

Command privilege level: 0,1, and 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management product re-register all

This command forces re-registration of all product instances associated with this Enterprise License Manager/Cisco Prime License Manager server. This command may take some time for re-registration and synchronization with all product instances to complete.

**license management product re-register all**

---

**Command Modes** Administrator (admin:)**Requirements**

Command privilege level: 1 and 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management reset

This command resets the identity, store data, and essentially removes all the installed licenses. It also restarts the Cisco Prime License Manager server process to make the changes effective.

**license management reset identity | registration**

Syntax Description	Parameters	Description
	<b>identity</b>	Resets the identity
	<b>registration</b>	Resets the registration

**Command Modes**

Administrator (admin:)

**Requirements**

Command privilege level: 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management security update

Use this command to download the Cisco Prime License Manager security update from the specified remote server location and install the contents of the specified security update file.

**license management security update****Requirements**

Command privilege level: 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

## license management service

This command activates or deactivates a given service on the Cisco Prime License Manager server.

**license management service activate | deactivate**

Syntax Description	Parameters	Description
	<b>activate</b>	Activates a given service on the Cisco Prime License Manager server.
	<b>deactivate</b>	Deactivates a given service on the Cisco Prime License Manager server.

**Command Modes**

Administrator (admin:)

**Requirements**

Command privilege level: 1 and 4

Allowed during upgrade: No

Applies to: Enterprise License Manager, Cisco Prime License Manager

# license management set log level core\_services

This command sets the log level for core services.

**license management set log level core\_services** **error** | **warning** | **info** | **debug**

Syntax Description	Parameters	Description
	<b>error</b>	Provides runtime errors or unexpected conditions that could be critical.
	<b>warning</b>	Provides messages about potential problems.
	<b>info</b>	Provides general information that may be useful. This parameter is set by default.
	<b>debug</b>	Provides detailed information about the flow of the process. We recommend that you use set this parameter on an as needed basis only.

Command Modes	Administrator (admin:)
	<b>Requirements</b>
	Command privilege level: 0, 1, and 4
	Allowed during upgrade: No
	Applies to: Cisco Prime License Manager.

# license management set log level product\_instances

This command sets the log level for product instances.

**license management set log level product\_instances** **error** | **warning** | **info** | **debug**

Syntax Description	Parameters	Description
	<b>error</b>	Provides runtime errors or unexpected conditions that could be critical.
	<b>warning</b>	Provides messages about potential problems.
	<b>info</b>	Provides general information that may be useful. This parameter is set by default.
	<b>debug</b>	Provides detailed information about the flow of the process. We recommend that you use set this parameter on an as needed basis only.

Command Modes	Administrator (admin:)
	<b>Requirements</b>
	Command privilege level: 0,1, and 4
	Allowed during upgrade: No

Applies to: Cisco Prime License Manager.

## license management system remove

This command allows you to remove an unused Cisco Prime License Manager instance from a coresident deployment.

### license management system remove

---

**Command Modes**

Administrator (admin:)

**Requirements**

Command privilege level: 4

Allowed during upgrade: No

Applies to: Cisco Prime License Manager

## license management unlock admin

Use this command to unlock a Cisco Prime License Manager server defined user. The command prompts for the name of the user to unlock.

### license management unlock admin

---

**Command Modes**

Administrator (admin:)

**Requirements**

Command privilege level: 1 and 4

Allowed during upgrade: No

Applies to: Cisco Prime License Manager