

Upgrade Path

The following table lists the upgrade paths to replace an existing Unified CVP version with a new one.

Table 1: Unified CVP Upgrade Paths

Upgrade Path from Older Release to New Release	Platform Change	Conversion Process	Description
Unified CVP 11.0(1)/11.5(1) to 11.6(1)	No	Direct upgrade to Unified CVP 11.6(1).	
Unified CVP 10.5(1) to 11.6(1)	Yes	 Perform an in-place upgrade from Windows Server 2008 R2 SP1 to Windows Server 2012 R2 Standard Edition. Upgrade to Unified CVP 11.6(1). 	Change in platform from 11.0(1) release
Unified CVP 10.0(1) to 11.6(1)	Yes	 Upgrade to Unified CVP 10.5(1). Perform an in-place upgrade from Windows Server 2008 R2 SP1 to Windows Server 2012 R2 Standard Edition. Upgrade to Unified CVP 11.6(1). 	Change in platform from 11.0(1) release

Upgrade Path from Older Release to New Release	Platform Change	Conversion Process	Description
Unified CVP 9.0(1) to 11.6(1)	Yes	 Upgrade to Unified CVP 10.5(1). Perform an in-place upgrade from Windows Server 2008 R2 SP1 to Windows Server 2012 R2 Standard Edition. Upgrade to Unified CVP 11.6(1). 	Change in platform from 11.0(1) release
Unified CVP Reporting Server 11.0(1)/11.5(1) to 11.6(1)	No	Direct upgrade to Unified CVP Reporting Server 11.6(1). For more information, see the Upgrade Unified CVP Reporting Server section.	
Unified CVP Reporting Server 10.5(1) to 11.6(1)	Yes	 Migrate to Unified CVP Reporting Server 11.6(1). Follow the procedure in Migrate Unified CVP Reporting Server. 	Change in platform from 11.0(1) release

- Unified CVP Upgrade Strategies, on page 2
- Important Considerations for Upgrade, on page 3
- Pre-Upgrade Tasks, on page 4
- Upgrade Existing Unified CVP Virtual Machine, on page 4
- Upgrade Unified CVP, on page 7
- Upgrade Operations Console, on page 8
- Upgrade Unified CVP Reporting Server, on page 11
- Upgrade Unified CVP Server, on page 11
- Upgrade Remote Operations, on page 12
- Upgrade Unified Call Studio, on page 13
- Postupgrade Tasks, on page 13

Unified CVP Upgrade Strategies

You can upgrade Unified CVP in a maintenance window. However, when there are a large number of CVP servers to upgrade, it may not be possible to upgrade all of them in one maintenance window. Using the upgrade strategies, you can help large Unified CVP deployments distribute the upgrade process. In addition, you can divide the server upgrades into multiple steps that can be completed over several maintenance windows.

Unified CVP upgrade strategies are described in the following sections.

CVP Units

A CVP unit is a single virtual machine and may comprise VXML Servers and Call Servers. You can upgrade one CVP unit at a time for the Unified CVP deployments that have multiple CVP units. For example, you can upgrade a CVP unit of related servers in a maintenance window. This deployment may be useful for call centers. There may be a need to migrate to Session Initiation Protocol (SIP) to continue call processing and minimize the risks.

Multiphased Approach

Multiphased approach is a strategy to upgrade a subset of Unified CVP Servers and resume call processing. Using the multiphased upgrade approach, you can divide the upgrades in phases over time. If a Unified CVP deployment has multiple CVP units, you can upgrade each unit using the multiphased approach.

Depending on the deployment, choose one of the following multiphased approaches:

- Upgrade all servers of a certain type in a maintenance window.
- Upgrade a subset of a server type in a maintenance window.
- Upgrade a subset of a server type from a CVP unit in a maintenance window.

Use multiphased approach to upgrade the components in the following sequence:

- 1. Operations Console
- 2. Unified CVP Reporting Server
- 3. Unified CVP Server



Note

It is not necessary to upgrade all servers in a category in a single maintenance window; however, you must upgrade all Unified CVP components of one type before moving to the next set of components in the Unified CVP deployment or the CVP unit.

Related Topics

Upgrade Unified CVP, on page 7

Important Considerations for Upgrade

- Upgrade Unified CVP during off-peak hours or during a maintenance window to avoid service interruptions.
- Do not make any configuration changes during the upgrade, because the changes are lost after the upgrade.
- Ensure that a CVP unit remains offline until you upgrade all the components in that unit.

- Upgrade Unified CVP components in a sequence for a successful deployment. A change in upgrade sequence results in loss of call data and error or inability to configure properties that are introduced in the new version.
- Push the TCL and VXML files to their respective ingress and VXML gateways after the CVP Operations Console is upgraded, but before any other CVP components are upgraded.

Pre-Upgrade Tasks

Related Topics

Configure Virtual CPU Settings, on page 4

Upgrade Virtual Memory, on page 5

Upgrade Virtual Machine Hardware Version, on page 5

Expand Disk Space of Virtual Machines, on page 6

Upgrade Existing Unified CVP Virtual Machine

The following sections discuss the steps to upgrade the virtual machine hardware by using VMware vSphere Web Client (Thin Client).



Note

You must not use VMware vSphere Client (Thick Client) to upgrade the virtual machine hardware.

Configure Virtual CPU Settings

Complete the following procedure to change the virtual hardware resource setting for CPU on Unified CVP virtual machines.

Procedure

- **Step 1** Power off the virtual machine.
- **Step 2** Right-click the virtual machine, choose **Edit Settings**.
- Step 3 Click the Virtual Hardware tab.
- Step 4 Click CPU.
- **Step 5** From the **Cores per Socket** drop-down list, select **1**.
- **Step 6** In the **Reservation** field, enter the CPU reservation speed (defined in MHz) for Unified CVP virtual machines.

For more information about virtual hardware resource setting for CPU and memory, see *Virtualization for Cisco Unified Customer Voice Portal* available at http://www.cisco.com/c/dam/en/us/td/docs/voice_ip_comm/uc_system/virtualization-virtualization-cisco-unified-customer-voice-portal.html.

Step 7 Click **OK** to save the settings.

What to do next

Upgrade Virtual Memory

Related Topics

Upgrade Virtual Memory, on page 5

Upgrade Virtual Memory

Complete the following procedure to upgrade the system memory on Unified CVP virtual machines.

Procedure

Step 1	Ensure that the virtual machine is switched off.
Step 2	Right-click the Virtual Machine and select Edit Settings.
Step 3	Click the Virtual Hardware tab.
Step 4	Click Memory.
Step 5	In the RAM field, change the RAM value (in MB) of Unified CVP virtual machines as defined in the <i>Virtualization for Cisco Unified Customer Voice Portal</i> available at https://www.cisco.com/c/dam/en/us/td/docs/voice_ip_comm/uc_system/virtualization/virtualization-cisco-unified-customer-voice-portal.html.
Step 6	In the Reservation field, enter the RAM value (in MB) corresponding to Unified CVP VMs, as defined in the <i>Virtualization for Cisco Unified Customer Voice Portal</i> .
Step 7	Click OK to save the settings.

What to do next

Upgrade the Virtual Machine Hardware Version.

Related Topics

Upgrade Virtual Machine Hardware Version, on page 5

Upgrade Virtual Machine Hardware Version

Complete the following procedure to upgrade the virtual machine hardware version on Unified CVP virtual machines.

Procedure

Step 1	Ensure that the virtual machine is switched off.
Step 2	Right-click the virtual machine and select Edit Settings.
Step 3	Click the Virtual Hardware tab.
Step 4	Click Upgrade.
Step 5	Check the Schedule VM Compatibility Upgrade check box.
Step 6	From the Compatible with (*) drop-down list, choose one of the following options:

- ESXi 5.5 and later
- ESXi 6.0 update 2 and later
- ESXi 6.5 with VMFS5
- ESXi 6.5 with VMFS 5
- ESXi 6.5 U2 and later updates with VMFS 6
- ESXi 6.7 with VMFS 6
- **Step 7** Click **OK** to save the settings.
- **Step 8** Power on the virtual machine.

What to do next

Expand the Virtual Machines Disk Space

Related Topics

Expand Disk Space of Virtual Machines, on page 6

Expand Disk Space of Virtual Machines

Complete the following procedure to expand the virtual machines disk space on Unified CVP virtual machines.

Procedure

- Step 1 Ensure that the virtual machine is switched off. Step 2 Right-click the virtual machine and choose **Edit Settings**. Step 3 Click the **Virtual Hardware** tab. Step 4 In the **Hard disk 1** field, change the disk size value (in GB) of the Unified CVP virtual machines, as defined in the Virtualization for Cisco Unified Customer Voice Portal available at https://www.cisco.com/c/dam/en/ us/td/docs/voice_ip_comm/uc_system/virtualization/virtualization-cisco-unified-customer-voice-portal.html. Step 5 Click OK. Step 6 Power on the virtual machine. Step 7 Log into your operating system. Step 8 Right-click My PC and select Manage.
- Step 9 Select File and Storage Services > Disks.
- belief I he and beliage bet vices > Disks.
- Step 10 In the Volumes area, right-click C drive and select Extend Volume....
- **Step 11** Change the disk size value (in GB) of the Unified CVP virtual machines as defined in the *Unified CVP Virtualization Wiki*.
- Step 12 Click OK.
- **Step 13** Restart the server.

Enable Resource Reservation on Upgraded Virtual Machine

After the virtual machine hardware version is upgraded based on the information provided in the *Virtualization* for Cisco Unified Customer Voice Portal, perform the following steps to enable resource reservation on the respective Unified CVP virtual machines.

For more information on supported virtual machine hardware versions, see *Virtualization for Cisco Unified Customer Voice Portal* available at https://www.cisco.com/c/dam/en/us/td/docs/voice_ip_comm/uc_system/virtualization/virtualization-cisco-unified-customer-voice-portal.html.

Procedure

- **Step 1** Login to vSphere Client and select the Unified CVP virtual machine.
- Step 2 Right-click the virtual machine and select the option Edit Settings from the popup menu. The Virtual Machine Properties window pops up.
- **Step 3** Select the **Resources** tab.

The Virtual Hardware Resource Setting that can be customized is shown in the left dialog box. The Resource Allocation for respective virtual hardware is shown in the right.

Step 4 Enable resource reservation for Unified CVP virtual machines.

Note

To enable the Virtual Hardware Resource reservation for Unified CVP virtual machines, the setting for CPU and memory must be modified. For information about virtual hardware resource setting for CPU and memory, see *Virtualization for Cisco Unified Customer Voice Portal* available at https://www.cisco.com/c/dam/en/us/td/docs/voice_ip_comm/uc_system/virtualization/virtualization-cisco-unified-customer-voice-portal.html.

Step 5 After the virtual hardware resource setting for CPU and memory for CVP virtual machines are set, click **OK** to close the VM Properties dialog box.

The CVP virtual machine is reconfigured and the **Resource Reservation** is enabled.

Upgrade Unified CVP



Note

When you upgrade Cisco Unified CVP Server (VXML Server included), you must also upgrade Unified Call Studio to the same version. Unified Call Studio can work with CVP Server only if both of them have the same version.

Perform the Unified CVP upgrade in the following sequence:

Procedure

Step 1 Back up any third-party libraries (.class or .jar files) that are found at the following locations (where APP_NAME is the name of each deployed voice application):

• %CVP HOME%\VXMLServer\common\classes

- %CVP HOME%\VXMLServer\common\lib
- %CVP HOME%\VXMLServer\applications\APP NAME\java\application\classes
- %CVP HOME%\VXMLServer\applications\APP NAME\java\application\lib
- %CVP HOME%\VXMLServer\applications\APP NAME\java\util

Note

- By default, %CVP HOME% is C:\Cisco\CVP.
- Tomcat is upgraded from 7.0 to 8.0.33 in Unified CVP 11.6(1). Back up any third-party .jar files that are required by VXML applications from the %CVP_HOME%\VXMLServer\Tomcat\common\lib folder. This common folder is no more available in Tomcat 8.0.33. As a result, after upgrading to Unified CVP 11.6(1), copy the earlier backed up .jar files back to %CVP_HOME%\VXMLServer\Tomcat\lib folder.
- **Step 2** Upgrade Cisco Unified CVP Operations Console (OAMP). For more information, see the Upgrade Operations Console section.
- **Step 3** (Optional) Upgrade Cisco Unified CVP Reporting Server. For more information, see the Upgrade Reporting Server section.
- **Step 4** Upgrade Cisco Unified CVP Server. For more information, see the Upgrade the Unified CVP Server section.
- **Step 5** Upgrade Cisco Unified Remote Operations. For more information, see the Upgrade Remote Operations section.
- **Step 6** Upgrade Cisco Unified Call Studio. For more information, see the Upgrade Unified Call Studio section.
- **Step 7** Upgrade previously deployed Unified CVP voice applications.

Upgrade Operations Console

The installed default media files are overwritten with the media format you choose for the Unified CVP upgrade; however, the customized media files are not overwritten during the upgrade. Customized media files, such as custom applications and Whisper Agent-Agent Greeting (WAAG), are retained in the format as they were prior to upgrade.



Note

For Unified CVP upgrade, u-law is the default media file format type.

Following sections describe the various scenarios of Operations Console upgrade.

Upgrade Operations Console 11.0(1) in U-law to Operations Console 11.6(1) in U-law

Procedure

Step 1 Mount the Unified CVP ISO image.

- **Step 2** Navigate to C:\CVP\installer windows and run setup.exe.
 - The installer automatically detects the previous installation and guides you through the upgrade process.
- **Step 3** Restart the server.
- Step 4 Navigate to the C:\Cisco\CVP\conf location and manually configure the Unified CVP properties file.
 - For more information, see the Manual Configuration of Unified CVP Properties section.
- **Step 5** Restart the server.

Upgrade Operations Console 11.0(1) in U-law to Operations Console 11.6(1) in A-law

Procedure

- **Step 1** Navigate to the C:\Cisco\CVP\conf location.
- Step 2 Convert the custom media files, such as custom applications and Whisper Agent-Agent Greeting (WAAG), and applications that are in u-law to A-law.
- Step 3 In the cvp_pkgs.properties file, add the cvp-pkgs.PromptEncodeFormatALaw = 1 property at line 7 to enable the A-law flag.

Note Ensure that you leave a space before and after the "=" sign.

- **Step 4** Mount the Unified CVP ISO image, and run setup.exe.
- **Step 5** Follow the instructions on the screen.
- **Step 6** Restart the server.
 - Note
- All the standard packaged media files and applications are installed in A-law format.
- Custom media files, such as custom applications and Whisper Agent-Agent Greeting (WAAG) are retained in the format as they were prior to upgrade.
- Step 7 Navigate to the C:\Cisco\CVP\conf location and manually configure the Unified CVP properties file. For more information, see the Manual Configuration of Unified CVP Properties section.
- **Step 8** Restart the server.

Upgrade Operations Console 11.0(1) in A-law to Operations Console 11.6(1) in A-law

Procedure

Step 1 Navigate to the C:\Cisco\CVP\conf location.

Step 2 In the cvp_pkgs.properties file, add the cvp-pkgs.PromptEncodeFormatALaw = 1 property at line 7 to enable the A-law flag.

Note Ensure that you leave a space before and after the "=" sign.

Step 3 Mount the Unified CVP ISO image and run setup.exe.

The installer automatically detects the previous installation, and guides you through the upgrade process.

- **Step 4** Follow the instructions on the screen.
- **Step 5** Restart the server.

Note

- All the standard packaged media files and applications are installed in the A-law format.
- Custom media files, such as custom applications and WAAG, are retained in the format as they were prior to upgrade.
- Step 6 Navigate to the C:\Cisco\CVP\conf location and manually configure the Unified CVP properties file. For more information, see the Manual Configuration of Unified CVP Properties section.
- **Step 7** Restart the server.

What to do next

Load the IOS scripts into the Cisco IOS memory.

Upgrade Operations Console 11.0(1) in A-law or U-law to Operations Console 11.6(1) in G729

Procedure

- **Step 1** Navigate to the C:\Cisco\CVP\conf location.
- Step 2 In the cvp_pkgs.properties file, add the cvp-pkgs.PromptEncodeFormatG729 = 1 property at line 7 to enable the G729 flag.

Note Ensure that you leave a space before and after the "=" sign.

- **Step 3** Mount the Unified CVP ISO image and run setup.exe.
- **Step 4** Follow the instructions on the screen.
- **Step 5** Restart the server.

Note

- All the standard packaged media files and applications are installed in G729 format.
- Custom media files, such as custom applications and Whisper Agent-Agent Greeting (WAAG) are retained in the format as they were prior to upgrade.
- Navigate to the C:\Cisco\CVP\conf location and manually configure the Unified CVP properties file. For more information, see the Manual Configuration of Unified CVP Properties section.

Step 7 Restart the server.

Upgrade Unified CVP Reporting Server

Before you begin

- Back up the Informix database in another drive.
- Turn off the scheduled purge.
- Ensure that the Unified CVP Reporting Server is not part of any domain and is part of a work group. Add it to the domain after the upgrade, if necessary.

Perform the following steps to upgrade the Unified CVP Reporting Server:

Procedure

- **Step 1** Perform Steps 1 to 5 of the Install Unified CVP Reporting Server procedure.
- Step 2 From the Ready to Install the Program window, select Unified CVP Reporting Server component and click Upgrade.
- **Step 3** On the **Authentication** window, enter a password and click **Next**.

Note

- Adhere to the password formation criteria that are listed in the Configuring Secure Passwords section.
- After the upgrade, add the Unified CVP Reporting Server to the domain, if necessary.
- Do not cancel the **cvp_dbadmin user authentication** popup window.
- **Step 4** Choose to restart the computer right after the upgrade or to restart it later, and click **Finish**.
- Step 5 Navigate to the C:\Cisco\CVP\conf location and manually configure the Unified CVP properties file. For more information, see the Manual Configuration of Unified CVP Properties section.
- **Step 6** Restart the server.

Upgrade Unified CVP Server

Before you begin

For A-law implementation in Unified CVP Server, install the latest Unified CVP FCS build.



Note

After successful upgrade of Unified CVP server, the **CVP Call Server Service Startup Type** is set to **Automatic** by default.

Upgrade CVP Server 11.0(1) in U-law to CVP Server 11.6(1) in U-law

Perform Steps 1 to 4 of the Upgrade Operations Console 11.0(1) in U-law to Operations Console 11.6(1) in U-law procedure.

- Log into Operations Console of the current version of Unified CVP and click Bulk Administration >
 File Transfer > Scripts and Media.
- **2.** Load the gateway download transferred files into the Cisco IOS memory for each CVP service using the Cisco IOS **call application voice load <service_name>** CLI command.
- **3.** Restore any backed-up third-party libraries.
- **4.** Upgrade the CVP Server's license.

Upgrade CVP Server 11.0(1) in U-law to CVP Server 11.6(1) in A-law

Perform Steps 1 to 8 of the Upgrade Operations Console 11.0(1) in U-law to Operations Console 11.6(1) in A-law.

Upgrade CVP Server 11.0(1) in A-law to CVP Server 11.6(1) in A-law

Perform Steps 1 to 7 of the Upgrade Operations Console 11.0(1) in A-law to Operations Console11.6(1) in A-law procedure.

Upgrade CVP Server 11.0(1) in A-law or U-law to CVP Server 11.6(1) in G729

Perform Steps 1 to 7 of the Upgrade Operations Console 11.0(1) in A-law or U-law to Operations Console 11.6(1) in G729 procedure.

Upgrade Remote Operations

Procedure

Step 1 Mount the Unified CVP ISO image, and run setup.exe.

The installer automatically detects the installation and upgrade of Remote Operations and guides you through the upgrade process.

- **Step 2** Follow the instructions on the Upgrade screens and click **Upgrade**.
- **Step 3** Restart the Server.

Upgrade Unified Call Studio

Before you begin

Obtain a new license for Unified Call Studio because licenses for earlier versions are invalid with the latest version.



Note

Upgrade of Call Studio is supported through the migration process.

Procedure

Step 1 Open Call Studio, right-click any existing project in the Navigator view, choose **Export**.

The **Export** wizard opens.

Step 2 Navigate to General > File System, and click Next.

Note From the list displayed by the Export wizard, select multiple projects to export them simultaneously.

- **Step 3** Browse to the directory where the projects will be exported and click **OK** and then click **Finish**.
- **Step 4** Uninstall the Call Studio software.

For more information, see the Unified CVP/Call Studio Uninstallation section.

Step 5 Install the Call Studio software.

For more information, see the Install Unified Call Studio section.

Postupgrade Tasks

After you upgrade the Unified CVP components, synchronize the metadata files using the Sync-up tool. For more information, see Initiate Metadata Synchronization for Unified CVP Rest API.



Note

- If Context Services is enabled, then register the device with Context Services again through OAMP.
- If you are using a VRU connection port other than the default port (5000), then click Save and Deploy
 of Unified CVP Call Server from OAMP.

Related Topics

Initiate Metadata Synchronization for Unified CVP Rest API Unified CVP Redeployment

Manual Configuration of Unified CVP Properties

The following table lists the procedure to manually configure the Unified CVP properties files based on the upgrade path.

Table 2: Manual Configuration of Unified CVP Properties

Unified CVP Component	Upgrade Path	Manual Configuration Process
CVP Server	10.5(1) to 11.6(1)	

Unified CVP Component	Upgrade Path	Mar	nual Configuration Process
		1.	Navigate to the C:\Cisco\CVP\conf location.
		2.	Open the cvpwsmconfig.properties file and add the following entry:
			wsm.job.cleanup.duration=1
		3.	Open the icm.properties file and update the following entry:
			#Maximum Number Of Calls ICM.maxCalls=6144
			<pre>#Use newcall trunk group id for pre-routed calls(Default is true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false</pre>
		4.	Open the orm.xml file and replace the existing content with the following content:
			<pre><?xml version="1.0" encoding="UTF-8"?> <orm <="" pre="" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"></orm></pre>
			<pre>xsi:noNamespaceSchemaLocation="orm.xsd"> <ormaddresses></ormaddresses> </pre>
		5.	Open the system.properties file and update the following entry:
			ThreadManager.totalThreads = 500 Infrastructure.threadWeight=4 SIP.threadWeight=50 IVR.threadWeight=1 ICM.threadWeight=1
			Remove the following entry:
			CVPServlet.upgradeProperties = true
		6.	Open the vxml.properties file and add the following entry:
			#ContextService properties #************************************
			VXML.ContextService.maxRetries=1 VXML.ContextService.requestTimeout=1200 VXML.ContextService.labMode=false VXML.ContextService.executorThreadPoolSize=50 VXML.ContextService.httpMaxConnectionsPerRoute=50 VXML.ContextService.statsLogInterval=1800000 VXML.ContextService.getStatusInterval = 30000
			#**************
		7.	Open the ivr.properties file and update the following entry:
			# Valid media file extensions list. IVR.ValidMediaFileExtension=.wav, .au, .vox, .rm
		8.	Open the oamp.properties file and add the following entries in the

Unified CVP Component	Upgrade Path	Manual Configuration Process
		respective files:
		<pre>coamp.properties # OAMP Interval for Context Service get Status in seconds (default: 30 seconds) omgr.contextServiceStatusInterval=30 # Context Service status timeout value (in seconds) omgr.csStatusTimeout=180 # SSL Context to be used omgr.sslContextProtocol=TLSv1.2</pre> 9. Open the sip.properties file and add the following entry:
		<pre>#whether to send Reinvite to caller after Whipser done SIP.ReinviteCallerAfterWhisperDone=true #System wide ReasonCode to cause code Mapping SIP.System.ReasonCodeToCauseCode=</pre>

Unified CVP Component	Upgrade Path	Manual Configuration Process
<u> </u>		10. Open the sip.properties file and add the following entry:
		<pre># Outbound proxy SIP listen (secure) port. SIP.Proxy.Secure.Port=5061</pre>
		<pre># Port on which to listen for incoming sip secure requests SIP.Incoming.Secure.Port = 5061</pre>
		<pre># KeyStorePath SIP.Secure.KeyStorePath = C:\\Cisco\\CVP\\conf\\security\\.keystore Note: This file path must be the actual install path.</pre>
		<pre># KeyStorePassword SIP.Secure.KeyStorePassword =</pre>
		<pre># TrustStorePath SIP.Secure.TrustStorePath =</pre>
		<pre># TrustStorePassword SIP.Secure.TrustStorePassword =</pre>
		#KeyStoreType SIP.Secure.KeyStoreType = JCEKS
		<pre>#TrustStoreType SIP.Secure.TrustStoreType =</pre>
		<pre># KeyAlgorithm SIP.Secure.KeyAlgorithm = SunX509</pre>
		<pre>#TrustStoreAlgorithm SIP.Secure.TrustStoreAlgorithm =</pre>
		<pre># Incoming secure Protocol SIP.Incoming.Secure.Transport = TLS</pre>
		#Outgoing secure Protocol SIP.Outgoing.Secure.Transport = TLS
		#Secure ciphers colon(;) seperated e.g TLS_RSA_WITH_AES_128_CBC_SHA SIP.Secure.Ciphers = TLS_RSA_WITH_AES_128_CBC_SHA
		#Secure TLS versions flags e.g TLSv1,TLSv1.1,TLSv1.2 SIP.Secure.Tlsv1Enabled = false SIP.Secure.Tlsv1dot1Enabled = false SIP.Secure.Tlsv1dot2Enabled = true
		#Secure Protocol SIP.Secure.Protocol = TLS
		# Client Certificate is needed or not.
		SIP.Secure.UseClientAuth = false #Whether to use backup IVR Sub System
		SIP.UseBackupIVRSS = false
		#Calls Max Threshold

Unified CVP Component	Upgrade Path	Manual Configuration Process
		SIP.CallsMaxThreshold = -1 Note: This value indicates the maximum number of calls that a Call Server can process. The default value is -1, which denotes the maximum number of licenses (3000). This value can be configured in the range of 0-3000.
		11. Add the following entries in the respective files:
		<pre>jmx_callserver.conf com.sun.management.jmxremote.rmi.port = 2097 com.sun.management.jmxremote.ssl.enabled.protocols=TLSv1.</pre>
		<pre>jmx_oamp.conf com.sun.management.jmxremote.rmi.port = 10000 com.sun.management.jmxremote.ssl.enabled.protocols=TLSv1.</pre>
		<pre>jmx_vxml.conf com.sun.management.jmxremote.rmi.port = 9697 com.sun.management.jmxremote.ssl.enabled.protocols=TLSv1.</pre>
		<pre>jmx_wsm.conf com.sun.management.jmxremote.rmi.port = 10003 com.sun.management.jmxremote.ssl.enabled.protocols=TLSv1.</pre>
		<pre>orm_jmx.properties com.sun.management.jmxremote.rmi.port=3000 com.sun.management.jmxremote.ssl.enabled.protocols=TLSv1.</pre>
		12. Open the orm.properties file and add the following entries in the respective files:
		orm.properties #Media server root directory.
		mediaserver.root.dir =
		# SSL Context to be used orm.sslContextProtocol=TLSv1.2

Unified CVP Component	Upgrade Path	Manual Configuration Process	
		13.	Navigate to the C:\Cisco\CVP location and locate the connector node with attribute SSLCertificateFile=" <install_path>\security\wsm.crt" in the file: wsm\Server\Tomcat\conf\server.xml and add the following:</install_path>
			ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256, TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256, TLS_RSA_WITH_AES_256_CBC_SHA,TLS_RSA_WITH_AES_128_CBC_SHA, TLS_RSA_WITH_AES_128_CBC_SHA256"
			sslEnabledProtocols="TLSv1.2"
			Example:
			<pre><connector <="" pre="" sslcertificatefile="C:\Cisco\CVP\conf\security\wsm.crt" sslcertificatekeyfile="C:\Cisco\CVP\conf\security\wsm.key" sslenabled="true"></connector></pre>
			<pre>acceptCount="100" ciphers="TLS ECDHE ECDSA WITH AES 128 GCM SHA256,</pre>
			TLS ECDHE RSA WITH AES 128 GCM SHA256,TLS RSA WITH AES 256 CBC SHA,
			TLS_RSA_WITH_AES_128_CBC_SHA, TLS_RSA_WITH_AES_128_CBC_SHA256"
			<pre>clientAuth="false" disableUploadTimeout="true" enableLookups="true" executor="tomcatThreadPool" keyAlias="wsm_certificate" keystoreFile="C:\Cisco\CVP\conf\security\.keystore" keystorePass="****" keystoreType="JCEKS" port="8111" protocol="org.apache.coyote.http11.Http11NioProtocol" scheme="https" secure="true" sslEnabledProtocols="TLSv1.2" sslProtocol="TLS"/></pre>
		14.	Locate the connector node with the attribute SSLCertificateFile=" <install_path>\security\vxml.crt" in the file: VXMLServer\Tomcat\conf\server.xml</install_path>
			and add or update the following:
			sslEnabledProtocols="TLSv1.2"
		15.	Locate the connector node with the attribute SSLCertificateFile=" <install_path>\security\vxml.crt" in the file: CallServer\Tomcat\conf\server.xml</install_path>
			and add or update the following:
			sslEnabledProtocols="TLSv1.2"
		16.	Go to Tomcat's JVM arguments of VXML Server, and replace the following registry entry:
			Dhttps.client.protocol=TLSv1.2
			with
			Djdk.tls.client.protocols=TLSv1.2

Unified CVP Component	Upgrade Path	Manual Configuration Process	
CVP Server	11.0(1) to 11.6(1)	1. Follow Steps 1 through 5 from the preceding row, CVP Server Upgrade from 10.5(1) to 11.6(1)	
		2. Open the vxml.properties file and add the following entry:	
		#ContextService properties #********************************* VXML.ContextService.executorThreadPoolSize=50 VXML.ContextService.httpMaxConnectionsPerRoute=50 VXML.ContextService.statsLogInterval=1800000 VXML.ContextService.getStatusInterval = 30000 #*********************************	
		from 10.5(1) to 11.6(1). 4. Go to Tomcat's JVM arguments of VXML Server, and replace the following registry entry:	
		Dhttps.client.protocol=TLSv1.2	
		with	
		Djdk.tls.client.protocols=TLSv1.2	
CVP Server	11.5(1) to 11.6(1)	1. Open the icm.properties file and update the following:	
		#Use newcall trunk id for pre-routed calls (Default is true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false	
		2. Follow Steps 2 and 3 from the preceding row, CVP Server Upgrade from 11.0(1) to 11.6(1).	
		3. Go to Tomcat's JVM arguments of VXML Server, and replace the following registry entry:	
		Dhttps.client.protocol=TLSv1.2	
		with	
		Djdk.tls.client.protocols=TLSv1.2	

Unified CVP Component	Upgrade Path	Manual Configuration Process
Operations Console	10.5(1) to 11.6(1)	

Unified CVP Component	Upgrade Path	Manual Configuration Process	
		1.	Navigate to the C:\Cisco\CVP\conf location.
		2.	Open the cvpwsmconfig.properties file and add the following entry:
			wsm.job.cleanup.duration=1
		3.	Open the icm.properties file and add the following entry:
			# Maximum Number Of Calls ICM.maxCalls=6144
			<pre>#Use newcall trunk group id for pre-routed calls(Default is true)</pre>
			ICM.useNewCallTrunkGroupIDforPreRoutedCall = false
		4.	Open the orm.xml file, and replace the existing content with the following content:
			<pre><?xml version="1.0" encoding="UTF-8"?> <orm <="" pre="" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"></orm></pre>
			<pre>xsi:noNamespaceSchemaLocation="orm.xsd"> <ormaddresses></ormaddresses> </pre>
		5.	Open the system.properties file and update the following entry:
			ThreadManager.totalThreads = 500 Infrastructure.threadWeight=4 SIP.threadWeight=50 IVR.threadWeight=1 ICM.threadWeight=1 Remove the following entry: CVPServlet.upgradeProperties = true
		6.	Open the vxml.properties file and add the following entry: #ContextService properties
			<pre>#ContextService properties #************************************</pre>
		7.	Open the ivr.properties file and update the following entry:
			<pre># Valid media file extensions list. IVR.ValidMediaFileExtension=.wav, .au, .vox, .rm</pre>
		8.	Open the oamp.properties file and add the following entries in the respective files:
			oamp.properties

Unified CVP Component	Upgrade Path	Manu	al Configuration Process
			# OAMP Interval for Context Service get Status in seconds (default: 30 seconds)
			omgr.contextServiceStatusInterval=30
			# Context Service status timeout value (in seconds)
			omgr.csStatusTimeout=180
			# SSL Context to be used omgr.sslContextProtocol=TLSv1.2
			Follow Steps 9 through 12 from the preceding row, CVP Server Upgrade from 10.5(1) to 11.6(1).
		1	Navigate to the C:\Cisco\CVP location and locate the connector node with attribute
			SSLCertificateFile=" <install_path>\security\wsm.crt" in the file: wsm\OPSConsoleServer\Tomcat\conf\server.xml and add the following:</install_path>
			ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256, TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256, TLS_RSA_WITH_AES_256_CBC_SHA,TLS_RSA_WITH_AES_128_CBC_SHA TLS_RSA_WITH_AES_128_CBC_SHA256"
			sslEnabledProtocols="TLSv1.2"
			<pre>Example:</pre>
			ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256,
		I	TLS ECDHE RSA WITH AES 128 GCM SHA256,TLS RSA WITH AES 256 CBC SHA TLS RSA WITH AES 128 CBC SHA,TLS RSA WITH AES 128 CBC SHA256
			<pre>clientAuth="false" disableUploadTimeout="true" enableLookups="true"</pre>
			<pre>executor="tomcatThreadPool" keyAlias="wsm_certificate" keystoreFile="C:\Cisco\CVP\conf\security\.keystore" keystorePass="****" keystoreType="JCEKS" port="8111"</pre>
			protocol="org.apache.coyote.http11.Http11NioProtocol" scheme="https" secure="true" sslEnabledProtocols="TLSv1.2 sslProtocol="TLS"/>
		11.	Locate the connector node with the attribute
			SSLCertificateFile=" <install_path>\security\vxml.crt" in the file: OPSConsoleServer\Tomcat\conf\server.xml</install_path>
			and add or update the following:
			sslEnabledProtocols="TLSv1.2"

Unified CVP Component	Upgrade Path	Manual Configuration Process
Operations Console	11.0(1) to 11.6(1)	

Unified CVP Component	Upgrade Path	Manual Configuration Process
<u>-</u>		1. Navigate to the C:\Cisco\CVP\conf location
		2. Open the cvpwsmconfig.properties file and add the following entry:
		wsm.job.cleanup.duration=1
		3. Open the icm.properties file and add the following entry:
		# Maximum Number Of Calls ICM.maxCalls=6144
		#Use newcall trunk group id for pre-routed calls(Default is true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false
		4. Open the orm.xml file, and replace the existing content with the following content:
		<pre><?xml version="1.0" encoding="UTF-8"?> <orm xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:nonamespaceschemalocation="orm.xsd"> <ormaddresses></ormaddresses> </orm></pre>
		5. Open the system.properties file and add the following entry:
		ThreadManager.totalThreads = 500 Infrastructure.threadWeight=4 SIP.threadWeight=50 IVR.threadWeight=1 ICM.threadWeight=1 Remove the following entry: CVPServlet.upgradeProperties = true
		6. Open the oamp.properties file and add the following entries in the respective files:
		<pre>oamp.properties # OAMP Interval for Context Service get Status in second (default: 30 seconds) omgr.contextServiceStatusInterval=30</pre>
		# Context Service status timeout value (in seconds) omgr.csStatusTimeout=180
		# SSL Context to be used omgr.sslContextProtocol=TLSv1.2
		7. Follow Steps 10 through 12 from the preceding row, CVP Server Upgrade from 10.5(1) to 11.6(1).
		8. Navigate to the C:\Cisco\CVP location and locate the connector node with attribute SSLCertificateFile=" <install_path>\security\wsm.crt" in the file: wsm\OPSConsoleServer\Tomcat\conf\server.xml and add the following:</install_path>

Unified CVP Component	Upgrade Path	Manual Configuration Process
		ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256, TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256, TLS_RSA_WITH_AES_256_CBC_SHA,TLS_RSA_WITH_AES_128_CBC_SHA, TLS_RSA_WITH_AES_128_CBC_SHA256"
		sslEnabledProtocols="TLSv1.2"
		<pre>Example:</pre>
I		ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256,
		TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256,TLS_RSA_WITH_AES_256_CBC_SHA,
		TLS_RSA_WITH_AES_128_CBC_SHA,TLS_RSA_WITH_AES_128_CBC_SHA256
		<pre>clientAuth="false" disableUploadTimeout="true" enableLookups="true" executor="tomcatThreadPool" keyAlias="wsm_certificate" keystoreFile="C:\Cisco\CVP\conf\security\.keystore" keystorePass="****" keystoreType="JCEKS" port="8111" protocol="org.apache.coyote.http11.Http11NioProtocol" scheme="https" secure="true" sslEnabledProtocols="TLSv1.2" sslProtocol="TLS"/></pre>
		9. Locate the connector node with the attribute
		SSLCertificateFile=" <install_path>\security\vxml.crt" in the file: OPSConsoleServer\Tomcat\conf\server.xml and add or update the following:</install_path>
		sslEnabledProtocols="TLSv1.2"

Unified CVP Component	Upgrade Path	Manual Configuration Process
Operations Console	11.5(1) to 11.6(1)	

Unified CVP Component	Upgrade Path	Manual Configuration Process
		1. Open the icm.properties file and add the following entry:
		#Use newcall trunk group id for pre-routed calls(Default true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false
		2. Open the oamp.properties file and add the following entries in the respective files:
		<pre>oamp.properties # OAMP Interval for Context Service get Status in second (default: 30 seconds) omgr.contextServiceStatusInterval=30</pre>
		# Context Service status timeout value (in seconds) omgr.csStatusTimeout=180
		<pre># SSL Context to be used omgr.sslContextProtocol=TLSv1.2</pre>
		3. Follow Steps 10 through 12 from the preceding row, CVP Server Upgra from 10.5(1) to 11.6(1).
		4. Navigate to the C:\Cisco\CVP location and locate the connector no with attribute SSLCertificateFile="C:\Cisco\CVP\conf\security\oamp.c in the file: OPSConsoleServer\Tomcat\conf\server.xm. and add the following:
		ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256, TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256, TLS_RSA_WITH_AES_256_CBC_SHA,TLS_RSA_WITH_AES_128_CBC_SHA TLS_RSA_WITH_AES_128_CBC_SHA256"
		sslEnabledProtocols="TLSv1.2"
		<pre>Example: <connector sslcertificatefile="C:\Cisco\CVP\conf\security\wsm.crt" sslcertificatekeyfile="C:\Cisco\CVP\conf\security\wsm.key SSLEnabled=" td="" true"<=""></connector></pre>
		acceptCount="100" ciphers="TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256,
		TLS ECDHE RSA WITH AES 128 GCM SHA256,TLS RSA WITH AES 256 CBC S TLS RSA WITH AES 128 CBC SHA,TLS RSA WITH AES 128 CBC SHA2
		<pre>clientAuth="false" disableUploadTimeout="true" enableLookups="true" executor="tomcatThreadPool" keyAlias="wsm_certificate" keystoreFile="C:\Cisco\CVP\conf\security\.keystore" keystorePass="***" keystoreType="JCEKS"</pre>
		<pre>port="8111" protocol="org.apache.coyote.http11.Http11NioProtocol" scheme="https" secure="true" sslEnabledProtocols="TLSv1.2" sslProtocol="TLS"/></pre>
		5. Locate the connector node with the attribute SSLCertificateFile="C:\Cisco\CVP\conf\security\oamp.crt" in the file

Unified CVP Component	Upgrade Path	Manual Configuration Process
		OPSConsoleServer\Tomcat\conf\server.xml
		and add or update the following:
		sslEnabledProtocols="TLSv1.2"
Reporting Server		1. Navigate to the C:\Cisco\CVP\conf location
	11.6(1)	2. Open the cvpwsmconfig.properties file and add the following entry:
		wsm.job.cleanup.duration=1
		3. Open the icm.properties file and add the following entry:
		# Maximum Number Of Calls ICM.maxCalls=6144
		#Use newcall trunk group id for pre-routed calls(Default is
		true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false
		4. Open the orm.xml file, and replace the existing content with the following content:
		<pre><?xml version="1.0" encoding="UTF-8"?> <orm xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xsi:nonamespaceschemalocation="orm.xsd"> <ormaddresses></ormaddresses> </orm></pre>
		5. Open the system.properties file and add the following entry:
		ThreadManager.totalThreads = 500 Infrastructure.threadWeight=4 SIP.threadWeight=50 IVR.threadWeight=1 ICM.threadWeight=1 Remove the following entry: CVPServlet.upgradeProperties = true
		6. Open the reporting properties file and add the following entry:
		RPT.DBAdminPassword = ENCRYPTEDPWD
		Note The value (ENCRYPTEDPWD) of the new entry must be same as that of the RPT.DBPassword value.
		7. Follow Steps 10 through 13 from the preceding row, CVP Server Upgrade from 10.5(1) to 11.6(1).

Unified CVP Component	Upgrade Path	Manual Configuration Process
Reporting Server	11.5(1) to 11.6(1)	1. Open the icm.properties file and add the following entry:
		#Use newcall trunk group id for pre-routed calls(Default is true) ICM.useNewCallTrunkGroupIDforPreRoutedCall = false 2. Follow Steps 10 through 13 from the preceding row, CVP Server Upgrade from 10.5(1) to 11.6(1).

Manual Configuration of Unified CVP Properties