



Status API

The Status API retrieves information about the state of rules that collectively determine if the system is working correctly.

- [Configuration Rules, on page 2](#)
- [Operation Rules, on page 3](#)

The system periodically checks the state of the rules. To force the status to be updated, refer to the [Scan API](#).

URL

`https://<server>/unifiedconfig/config/status`

Operations

- **get**: Returns the status rule results, using the URL
`https://<server>/unifiedconfig/config/status`.

Response Parameters

- **name**: The name of the status. See the [Configuration Rules, on page 2](#) and [Operation Rules, on page 3](#).
- **category**: The status category of Configuration or Operation.
- **level**: The severity of the condition. Values include: OK, ERROR, and BLOCKED. The BLOCKED level indicates that the rule has not been processed yet or that the failure of another rule prevents this rule from running.
- **machine**: A collection for the machine ([Machine Inventory API](#)) including the machine's name, type, and refURL. See [References](#).

Example Get Response

```
<results>
  <statuses>
    <status>
      <name>SOCIAL MINER MR_ENABLED</name>
      <category>CONFIGURATION</category>
      <level>BLOCKED</level>
      <machines>
```

```

    <machine>
      <refURL>/unifiedconfig/config/
        machineinventory/6110</refURL>
      <machineType>EXTERNAL_SOCIAL_MINER
      </machineType>
      <name>Machine_2563_00002</name>
    </machine>
  </machines>
</status>
<status>
  <name>SERVER_CONNECTION</name>
  <category>OPERATION</category>
  <level>OK</level>
  <machines>
    <machine>
      <refURL>/unifiedconfig/config/
        machineinventory/6110</refURL>
      <machineType>EXTERNAL_SOCIAL_MINER
      </machineType>
      <name>Machine_2563_00002</name>
    </machine>
  </machines>
</status>
<status>
  <name>SERVER_CREDENTIALS</name>
  <category>OPERATION</category>
  <level>OK</level>
  <machines>
    <machine>
      <refURL>/unifiedconfig/config/
        machineinventory/6110</refURL>
      <machineType>EXTERNAL_SOCIAL_MINER
      </machineType>
      <name>Machine_2563_00002</name>
    </machine>
  </machines>
</status>
</statuses>
</results>

```

- [Configuration Rules, page 2](#)
- [Operation Rules, page 3](#)

Configuration Rules

Common Rules for All Machines

These rules show the potential configuration errors and warnings for all machines.

Table 1: Common Rules

Rule	Description
CAN_RESOLVE_ADDRESS_TO_FQDN	Machine address must be resolvable to a fully qualified domain name (FQDN).

Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse Machines

These rules show the potential configuration errors and warnings for Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse machines.

Table 2: Unified CCE AW, Unified Intelligence Center, CUIC-LD-IdS, and Finesse Rules

Rule	Description
SSO_COMPONENT_STATUS_MATCHES_GLOBAL	The global SSO status must be the same as component SSO status.
SSO_VALID_IDS_REFERENCE	If single sign-on is enabled, this machine must be associated with a valid Cisco Identity Service.

Table 3: Unified CCE AW Rules

Rule	Description
TASK_ROUTING_APP_PATHS_EXIST	Each Peripheral Gateway with a Communications Manager PIM must have an associated Task Routing Application Path.

SocialMiner Machines

These rules show the potential configuration errors and warnings for SocialMiner machines.

Table 4: SocialMiner Rules

Rule	Description
SOCIAL_MINER_MR_ENABLED	Multichannel routing must be enabled on SocialMiner.

Operation Rules

Common Operation Rules

These rules show the potential operation errors and warnings for the following machines:

- All Unified CCE components
- Unified Intelligence Center
- CUIC-LD-IdS
- Finesse
- Live Data
- Identity Service
- SocialMiner

Table 5: Common Rules

Rule	Description
SERVER_CONNECTION	<p>The Diagnostic Portal, AXL, REST, or SOAP service on this machine must be in service. The status you see varies according to the product type, as follows:</p> <ul style="list-style-type: none"> • Unified CCE: The Cisco ICM Diagnostic Framework service on the Principal AW must be reachable on the network. • CUIE-LD-IdS: The SOAP service on the Publisher must be reachable on the network. • Finesse: The SOAP service on the Primary Finesse machine must be reachable on the network. • IdS: The REST service on the Primary Identity Server must be reachable on the network • SocialMiner: The service must be reachable on the network.
SERVER_CREDENTIALS	<p>The inventory's credentials for the machine must be valid. The status you see varies according to the product type, as follows:</p> <ul style="list-style-type: none"> • Unified CCE: The Diagnostic Framework credentials entered for the Principal AW must be valid for all CCE components in the solution. • CUIE-LD-IdS: The Unified Intelligence Center Administration credentials entered for the Publisher must be valid • Finesse: The Finesse Administration credentials entered for the Primary Finesse machine must be valid. • IdS: The Identity Service Administration credentials entered for the Primary Identity Server must be valid • SocialMiner: The service credentials must be valid. <p>Note This rule does not apply to a standalone Live Data machine.</p>