

Troubleshoot

- Locate chip.log File, page 1
- Locate chip.dmp File, page 1
- Reset Admin Password for Cisco Jabber Guest Administration, page 2
- Reset Root Password for Cisco Jabber Guest Server, page 2

Locate chip.log File

If you are asked to send the chip.log file, use the following procedure.

Procedure

Step 1 Do one of the following:

- For Windows, navigate to %HOMEPATH%\Appdata\LocalLow\Cisco\chip. Note %HOMEPATH% is generally of the form 'C:\Users\username'.
- For Safari and Firefox (49 or below) on Mac OS X, navigate to ~/Library/"Internet Plug-Ins"/"Cisco Jabber Guest Plug-in.version-number.plugin"/Contents/Frameworks/Logs.
- For Chrome and Firefox (50 or later) on Mac OS X, navigate to ~/Applications/"Cisco Jabber Guest Add-on.version-number"/Contents/Frameworks/Logs

Step 2 Compress the file and email it back to the requester.

Locate chip.dmp File

If your plug-in crashes, a dump file called chip.dmp is created. Currently, this file is created only for plug-in crashes on Microsoft Windows. If you are asked to send the chip.dmp file, follow this procedure.

1

Procedure

Step 1	Navigate to %HOMEPATH%\Appdata\LocalLow\Cisco\chip.		
	Note	%HOMEPATH% is generally of the form	
		'C:\Users\ <i>username</i> '.	
Step 2	Compress the file and email it back to the requester.		

Reset Admin Password for Cisco Jabber Guest Administration

Procedure

Step 1	Sign in to the Cisco Jabber Guest server as root.		
Step 2	Change directory to /opt/cisco/webcommon/scripts:		
	cd /opt/cisco/webcommon/scripts		
Step 3	Enter the following command:		
	python mongo_admin_reset.py		
	The password is reset to its default value: jabbercserver.		

Reset Root Password for Cisco Jabber Guest Server

Procedure

- **Step 1** Open a console session for the Cisco Jabber Guest server and restart the server.
- **Step 2** Press any key to interrupt the start process.
- **Step 3** Press e to edit.
- Step 4 From the entries, select kernel and press e to edit.



- **Step 5** Start the server in single-user mode:
 - a) Add the word single to the end of the line.
 - b) Press the Enter key.



Step 6 Press b to start the server. The Cisco Jabber Guest server starts in single-user mode.

1

eth0: registered as PCnet/PCI II 79C970A pcnet32: 1 cards found.			
parport pc 00:08: reported by Plug and Play ACPI			
parport0: PC-stule at 0x378, irg 7 [PCSPP.TRISTATE]			
ppdev: user-space parallel port driver			
rraa araa araa araa araa araa araa	E	OK	
Setting hostname localhost.localdomain:	Γ	OK	
Checking filesustems			
	E	OK	
Remounting root filesustem in read-write mode:	Ē	OK	
mount: according to mtab. /dev/sda1 is already mounted on	1		
Mounting local filesustems:	E	OK	
Enabling /etc/fstab_swaps:	E	OK	
Welcome to CentOS			
Starting udev:	E	OK	
Setting hostname localhost.localdomain:	Ε	OK	
Checking filesystems			
에서 2019년 1월 19일 년 1월 19일 2월 2월 2월 19일 1월 19일 1월 19일 1월 19일 1월	Γ	OK	
Remounting root filesystem in read-write mode:	Ε	OK	
mount: according to mtab, /dev/sda1 is already mounted on	1		
Mounting local filesystems:	E	OK	
Enabling /etc/fstab_swaps:	E	0K	
[root@localhost /]# _			

Step 7 Enter **passwd root**, and then enter a new password.

Step 8 Restart the server.