



Plugin Configuration Mode Commands

You enter this mode using the **plugin** command in the Global Configuration mode.

Command Modes	<p>This chapter describes the commands available in the Plugin Configuration Mode. This mode is associated with the Dynamic Software Upgrade (DSU) process described in the <i>System Administration Guide</i>.</p> <p>Exec > Global Configuration > Plugin Configuration</p> <p>configure > plugin <i>plugin_name</i></p> <p>Entering the above command sequence results in the following prompt:</p> <pre>[context_name]host_name(config-plugin-plugin_name)#</pre>
Important	<p>The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).</p>
Important	<p>For information on common commands available in this configuration mode, refer to the Common Commands chapter.</p> <ul style="list-style-type: none">• attribute, on page 1• module priority, on page 2

attribute

This command is not supported in this release.

Product	All
Privilege	Security Administrator, Administrator
Command Modes	<p>Exec > Global Configuration > Plugin Configuration</p> <p>configure > plugin <i>plugin_name</i></p> <p>Entering the above command sequence results in the following prompt:</p>

```
[context_name]host_name(config-plugin-plugin_name)#
```

Syntax Description **attribute** *attribute_name attribute_value*

Usage Guidelines The command is not supported in this release.

module priority

Configures the priority in the Version Priority List (VPL) for a specified version of a plugin module.

Product ADC

Privilege Security Administrator, Administrator

Command Modes Exec > Global Configuration > Plugin Configuration

configure > plugin *plugin_name*

Entering the above command sequence results in the following prompt:

```
[context_name]host_name(config-plugin-plugin_name)#
```

Syntax Description **module priority** *number version plugin_version attribute attribute_name attribute_value*
no module priority *number*

no

Removes the configured priority in the module priority list.

priority *number*

Specifies the priority of the plugin module as an integer from 1 through 100. Priority "1" has the highest priority.

version *plugin_version*

Specifies the version number of the plugin module. The version number is derived from the filename of the downloaded plugin.

attribute *attribute_name attribute_value*

Specifies an attribute value pair.

attribute_name specifies the name of an attribute value pair as an alphanumeric string from 1 through 255 characters.

attribute_value specifies the value of an attribute value pair as an alphanumeric string from 1 through 255 characters.

Usage Guidelines Assign a priority number to a specific version of patch for the corresponding plugin. The priority number in the module priority list determines which version will be loaded when the **update module** command is used.

The **show plugin** command displays the VPL configuration status of this plugin module.

Example

The following command sets the priority of p2p plugin module version *1.17.4340* to 2 where the filename was **libp2p-1.2.0.so.tgz**:

```
module priority 2 version 1.2.0
```

module priority