



ACS Bandwidth Policy Configuration Mode Commands

The ACS Bandwidth Policy Configuration Mode is used to create and manage Active Charging Service (ACS) Bandwidth Policies.



Note In 12.3 and earlier releases, a maximum of 64 bandwidth policies can be configured.
In 14.0 and later releases, a maximum of 256 bandwidth policies can be configured.

Command Modes

Exec > ACS Configuration > Bandwidth Policy Configuration

active-charging service *service_name* > **bandwidth-policy** *policy_name*

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-bandwidth-policy)#
```



Important

The commands or keywords/variables that are available are dependent on platform type, product version, and installed license(s).

- [end, on page 1](#)
- [exit, on page 2](#)
- [flow limit-for-bandwidth, on page 2](#)
- [group-id, on page 3](#)

end

Exits the current configuration mode and returns to the Exec mode.

Product

All

Privilege

Security Administrator, Administrator

Syntax Description

end

Usage Guidelines Use this command to return to the Exec mode.

exit

Exits the current mode and returns to the parent configuration mode.

Product All

Privilege Security Administrator, Administrator

Syntax Description `exit`

Usage Guidelines Use this command to return to the parent configuration mode.

flow limit-for-bandwidth

This command allows you to configure the flow limit-for-bandwidth parameter for the current bandwidth policy.

Product ACS

Privilege Security Administrator, Administrator

Command Modes Exec > ACS Configuration > Bandwidth Policy Configuration

active-charging service *service_name* > **bandwidth-policy** *policy_name*

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-bandwidth-policy)#
```

Syntax Description **flow limit-for-bandwidth** *id* *bandwidth_id* **group-id** *group_id*
no flow limit-for-bandwidth *id* *bandwidth_id*

no

If previously configured, removes the specified flow limit-for-bandwidth configuration in the current bandwidth policy.

id *bandwidth_id*

Specifies ID for the current bandwidth policy.

bandwidth_id must be an integer from 1 through 65535.

group-id *group_id*

Specifies group ID for the current bandwidth policy.

group_id must be an integer from 1 through 65535.

Usage Guidelines Use this command to configure the flow limit-for-bandwidth configuration for a bandwidth policy.

Example

The following command configures the Flow Limit-for-Bandwidth configuration with bandwidth policy ID *test123* and group ID *123*:

```
flow limit-for-bandwidth id test123 group-id 123
```

group-id

This command allows you to configure the group ID for the current bandwidth policy.

Product

ACS

Privilege

Security Administrator, Administrator

Command Modes

Exec > ACS Configuration > Bandwidth Policy Configuration

active-charging service *service_name* > **bandwidth-policy** *policy_name*

Entering the above command sequence results in the following prompt:

```
[local]host_name(config-bandwidth-policy)#
```

Syntax Description

```
group-id group_id direction { downlink | uplink } peak-data-rate peak_data_rate
peak-burst-size peak_burst_size violate-action { discard |
lower-ip-precedence } [ committed-data-rate committed_data_rate
committed-burst-size committed_burst_size [ exceed-action { discard |
lower-ip-precedence } ] ]
{ default | no } group-id group_id direction { downlink | uplink }
```

default

Configures this command with default settings for the specified group ID.

no

If previously configured, removes the specified group ID configuration from the current bandwidth policy.

group_id

Specifies the group ID.

group_id must be an integer from 1 through 65535.

direction { *downlink* | *uplink* }

Specifies the direction for which bandwidth will be controlled.

peak-data-rate *peak_data_rate*

Specifies the peak data rate, in bits per second.

peak_data_rate must be an integer from 1 through 4294967295.

Default: 0

peak-burst-size *peak_burst_size*

Specifies the peak burst size, in bytes.

peak_burst_size must be an integer from 1 through 4294967295.

Default: 0

violate-action { discard | lower-ip-precedence }

Specifies the action to be taken if Peak Data Rate is surpassed.

- **discard**: Specifies to discard the packet
- **lower-ip-precedence**: Specifies to lower IP precedence of the packet

committed-data-rate *committed_data_rate*

Specifies the committed Data Rate, in bits per second. This can also be used to specify the Guaranteed Bit Rate (GBR) for Network Controlled QoS (NCQoS) without exceed-action.

committed_data_rate must be an integer from 1 through 4294967295.

Default: 0

committed-burst-size *committed_burst_size*

Specifies the committed burst size, in bytes.

committed_burst_size must be an integer from 1 through 4294967295.

Default: 0

exceed-action { discard | lower-ip-precedence }

Specifies the action to be taken if Committed Data Rate is surpassed.

- **discard**: Specifies to discard the packet.
- **lower-ip-precedence**: Specifies to lower IP precedence of the packet.

Usage Guidelines

Use this command to configure the Group ID for an bandwidth policy.

Example

The following command configures the group ID *111* to control bandwidth in the downlink direction specifying peak data rate of *10000* bits per second and peak burst size of *10000* bytes while specifying the action to be taken on violation as discard:

```
group-id 111 direction downlink peak-data-rate 10000 peak-burst-size 10000
violate-action discard
```