



UPF Load Control Profile Configuration Mode Commands

Load control profile configuration commands enable the UPF to send its load information to a peer node to adaptively balance the session load across UPFs. The load information reflects the operating status of the resources of the UPF.

Command Modes Exec > Global Configuration > UPF Load Control Profile Configuration

configure > upf-load-control-profile *profile_name*

Entering the above command results in the following prompt:

```
[local]UPlane (config-upf-load-control-profile)#
```



Important Available commands or keywords/variables vary based on platform type, product version, and installed license(s).

- [inclusion-frequency, on page 1](#)
- [end, on page 2](#)

inclusion-frequency

Configures parameters to determine the inclusion frequency of the Load Control Information IE for a UPF Control Profile configuration.

Product UPF

Privilege Administrator, Security Administrator

Command Modes Exec > Global Configuration > UPF Load Control Profile Configuration

configure > upf-load-control-profile *profile_name*

Entering this command results in the following prompt:

```
[local]UPlane (config-upf-load-control-profile)#
```

end**Syntax Description**

```
inclusion-frequency { advertisement-interval interval_in_seconds |
change-factor change_factor }
```

inclusion-frequency

Specifies that parameters to determine the inclusion frequency of the Load Control Information IE for a UPF Load Control Profile is configured. This parameter specifies how often the operator wants to send this information to the peers.

advertisement-interval *interval_in_seconds*

Configures the advertisement-interval for Load Control in seconds. Specifies the frequency at which the load control information should be sent to the peers.

interval_in_seconds must be an integer 0–3600.

Default: 300

change-factor *change_factor*

Specifies the percentage change from the previous LCI factor, at which the LCI IE is sent out.

change_factor must be an integer 1–20.

Default: 5%

Usage Guidelines

Use this command to specify parameters to determine the inclusion frequency of the Load control information IE for a UPF Load Control Profile configuration.

Example

```
[local]UPlane(config-upf-load-control-profile)# inclusion-frequency advertisement-interval
300
[local]UPlane(config-upf-load-control-profile)# inclusion-frequency change-factor 5
```

end

Exits the current configuration mode and returns to the Global Configuration mode.

Product

UPF

Privilege

Security Administrator, Administrator

Syntax Description

end

Usage Guidelines

Use this command to return to the Global Configuration mode.