



CPS vDRA Advanced Tuning Guide, Release 19.4.0

First Published: 2021-01-27

Last Modified: 2021-01-27

Americas Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at www.cisco.com/go/offices.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <https://www.cisco.com/c/en/us/about/legal/trademarks.html>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2021 Cisco Systems, Inc. All rights reserved.



CONTENTS

PREFACE

Preface v

About This Guide v

Audience v

Additional Support v

Conventions (all documentation) vi

Communications, Services, and Additional Information vii

Important Notes vii

CHAPTER 1

vDRA Advanced Tuning 1

Threading Configuration 1

Database Capacity 3

Database Alert Expressions 4

Database Connection Settings 5

Audit Rate Limiter 7



Preface

- [About This Guide](#), on page v
- [Audience](#), on page v
- [Additional Support](#), on page v
- [Conventions \(all documentation\)](#), on page vi
- [Communications, Services, and Additional Information](#), on page vii
- [Important Notes](#), on page vii

About This Guide

This document is a part of the Cisco Policy Suite documentation set.

For information about available documentation, see the *CPS Documentation Map* for this release at [Cisco.com](https://www.cisco.com).

Audience

This guide is best used by these readers:

- Network administrators
- Network engineers
- Network operators
- System administrators

This document assumes a general understanding of network architecture, configuration, and operations.

Additional Support

For further documentation and support:

- Contact your Cisco Systems, Inc. technical representative.
- Call the Cisco Systems, Inc. technical support number.
- Write to Cisco Systems, Inc. at support@cisco.com.

- Refer to support matrix at <https://www.cisco.com/c/en/us/support/index.html> and to other documents related to Cisco Policy Suite.

Conventions (all documentation)

This document uses the following conventions.

Conventions	Indication
bold font	Commands and keywords and user-entered text appear in bold font .
<i>italic font</i>	Document titles, new or emphasized terms, and arguments for which you supply values are in <i>italic font</i> .
[]	Elements in square brackets are optional.
{x y z }	Required alternative keywords are grouped in braces and separated by vertical bars.
[x y z]	Optional alternative keywords are grouped in brackets and separated by vertical bars.
string	A nonquoted set of characters. Do not use quotation marks around the string or the string will include the quotation marks.
courier font	Terminal sessions and information the system displays appear in courier font.
<>	Nonprinting characters such as passwords are in angle brackets.
[]	Default responses to system prompts are in square brackets.
!, #	An exclamation point (!) or a pound sign (#) at the beginning of a line of code indicates a comment line.



Note

Means reader take note. Notes contain helpful suggestions or references to material not covered in the manual.



Caution

Means reader be careful. In this situation, you might perform an action that could result in equipment damage or loss of data.

**Warning****IMPORTANT SAFETY INSTRUCTIONS.**

Means danger. You are in a situation that could cause bodily injury. Before you work on any equipment, be aware of the hazards involved with electrical circuitry and be familiar with standard practices for preventing accidents. Use the statement number provided at the end of each warning to locate its translation in the translated safety warnings that accompanied this device.

SAVE THESE INSTRUCTIONS

**Note**

Regulatory: Provided for additional information and to comply with regulatory and customer requirements.

Communications, Services, and Additional Information

- To receive timely, relevant information from Cisco, sign up at [Cisco Profile Manager](#).
- To get the business impact you're looking for with the technologies that matter, visit [Cisco Services](#).
- To submit a service request, visit [Cisco Support](#).
- To discover and browse secure, validated enterprise-class apps, products, solutions and services, visit [Cisco Marketplace](#).
- To obtain general networking, training, and certification titles, visit [Cisco Press](#).
- To find warranty information for a specific product or product family, access [Cisco Warranty Finder](#).

Cisco Bug Search Tool

[Cisco Bug Search Tool](#) (BST) is a web-based tool that acts as a gateway to the Cisco bug tracking system that maintains a comprehensive list of defects and vulnerabilities in Cisco products and software. BST provides you with detailed defect information about your products and software.

Important Notes

**Important**

Any feature or GUI functionality that is not documented may not be supported in this release or may be customer specific, and must not be used without consulting your Cisco Account representative.



CHAPTER 1

vDRA Advanced Tuning

The configuration values in this document are based on the type and size of DRA deployment.

The deployment can be categorized into two sizes:

- Small Deployment - 2 Directors and 4 workers
- Large Deployment - 8 directors and 10 workers



Note Recommended values are based on:

- Local Latency:
 - 20 ms for small deployments
 - 25 ms on large deployments
- Remote Latency:
 - 55 ms for small deployments
 - 50 ms for large deployments

In case the latency changes to a higher value, recommended values for all the configurations highlighted in this document needs to be re-characterized again.

- [Threading Configuration, on page 1](#)
- [Database Capacity, on page 3](#)
- [Database Alert Expressions, on page 4](#)
- [Database Connection Settings, on page 5](#)
- [Audit Rate Limiter, on page 7](#)

Threading Configuration

Thread pool configurations are applicable to java processes that run-in diameter-endpoint-s1xx on Director VM and binding-s1xx container on Worker VMs in DRA.

For more information on Threading Configuration, refer to the *CPS vDRA Configuration Guide*.

Table 1: Thread Pool Names

Thread Pool Name	Description
bindings	This thread pool is used for IMSI_APN/MSISDN_APN AAR lookup (MOG) and binding audit updates.
bindings.lookup	This thread pool is used only if appsharding.reader thread pool is overloaded. This thread pool is applicable only for AAR VoLTE calls.
bindings.delete	This thread pool is used to query session database and enqueue session and all the binding for deletion.
bindings.response	This thread pool is used to receive database storage response and forwards it as bind store response. This is applicable for CCR-I requests.
msgtimeouts	This thread pool is used to process timed out requests.
qprocessor	This thread pool is used to process inter director Diameter messages and offload the message to senders queue.
receivers	This thread pool is used to receive and process all incoming diameter messages from the diameter stack.
senders	This thread pool is used to write messages on the specific TCP connection.
localcpPublishers	This thread pool is used to publish messages to local control plane.
globalcpPublishers	This thread pool is used to publish messages to global control plane.
cpSubscriberWorker	This thread pool is used to process messages received on local and global control plane.
pcrfQuery	This thread pool is used for PCRF session queries used only for Rx AAR VoLTE calls.
stackStopHandler	This thread pool is used to gracefully disconnect diameter peers on process shutdown.
appsharding.reader	This thread pool is specific to Rx AAR VoLTE IPv6 binding lookup and processing. This thread pool is created for each shard.

The following tables lists recommended values when single DRA installaiton TPS is above 200 K.



Important

The highlighted values must be explicitly configured.

Table 2: Recommended Values

Thread Pool Name	Default Values		Recommended Values	
	Threads	Queue Size	Threads	Queue Size
bindings	30	1000	60	10000
bindings. lookup	10	1000	10	1000
bindings. delete	10	1000	30	10000
bindings. response	10	1000	10	1000
msgtimeouts	3	1000	3	1000
qprocessor	30	5000	30	5000
receivers	40	5000	40	5000
senders	40	5000	40	5000
localcpPublishers	15	2000	15	2000
globalcpPublishers	40	3000	40	3000
cpSubscriberWorker	30	10000	30	10000
pcrfQuery	20	400	20	400
stackStopHandler	50	0	50	0
appsharding. reader	1	1000	2	1000

Database Capacity



Note Rated database capacity has been arrived at after performing capacity tests.

The following table lists the database capacity for small and large deployments.

Table 3: Database Capacity

Deployment	Cluster	No. of Primary Shards (dual DB enabled)	Network Latency (in ms)	Database Capacity (in k)	Database Capacity Per Shard	85% Threshold Value
Small Deployment	Session_IPv6	8	20	30	$30000/8 = 3750$	3200
	IMSI_MSISDN	4	55	15	$15000/4 = 3750$	3200
Large Deployment	Session_IPv6	48	25	180	$180000/48 = 3750$	3200
	IMSI_MSISDN	48	50	145	$145000/48 = 3020$	2600

The following is the test call model used to determine the capacity for each cluster:

1. CCR_I, CCR_T and AAR call model for Session-IPv6 database cluster capacity.
2. CCR-I and CCR_T call model for IMSI-APN/MSISDN-APN database cluster capacity.
3. Database capacity is based on network latency mentioned in the [Table 3: Database Capacity, on page 4](#). If network latency is changed to higher value, then database capacity needs to be re-characterized.

Database Alert Expressions

Database alerts refer to alerts that can be configured to be triggered if the capacity of the database exceeds beyond a certain threshold.

IMSI_MSISDN Cluster

```
alert rule DRA_IMSI_MSISDN_DB_TPS_EXCEEDED
```

```
expression
```

```
"sum(rate(mongo_operation_total{state='primary',type='mongo',op=~'update|query|delete',cluster='IMSI_MSISDN'}[5m])) > (3200 * sum(mongo_node_state_primary{cluster='IMSI_MSISDN',type='mongo'}))"
```

```
event-host-label instance
```

```
message "{{ $labels.instance }}" Persistence DB TPS exceeded , current value is {{ $value }}"
```

```
snmp-severity critical
```

```
snmp-clear-message "{{ $labels.instance }}" Persistence DB TPS in control, current value is {{ $value }}"
```

Session_IPv6 Cluster

```
alert rule DRA_SESS_IPV6_DB_TPS_EXCEEDED
```

```
expression
```

```
"sum(rate(mongo_operation_total{state='primary',type='mongo',op=~'update|query|delete',cluster=~'SES_IPV6_*'}[5m])) > (3200 * sum(mongo_node_state_primary{cluster=~'SES_IPV6_*',type='mongo'}))"
```

```
event-host-label instance
```

```
message "{{ $labels.instance }}" Persistence DB TPS exceeded , current value is {{ $value }}"
```

```
snmp-severity critical
```

```
snmp-clear-message "{{ $labels.instance }}" Persistence DB TPS in control, current value is {{ $value }}" !"
```

Database Connection Settings

The following configurations vary based on deployment size (Small or Large) and should be configured accordingly. The worker VM java processes connect to the databases and create two database connection pools based on the database operation:

- Create/Update, and Delete
- Read

For more information on configuration syntax and examples, refer to the *CPS vDRA Operations Guide*.

binding db-connection-settings

The recommended values listed in the table are for write operations (Create/Update, Delete):



Important

The highlighted values must be explicitly configured.

Table 4: Recommended Value for Write Operations

Deployment	Bindings	connection-per-host	
		Default Values	Recommended Values
Small Deployment	drasession	10	14
	ipv6	10	10
	imsiapn	10	35
	msisdnapi	10	10
	ipv4	10	10
Large Deployment	drasession	10	10
	ipv6	10	10
	imsiapn	10	20
	msisdnapi	10	20
	ipv4	10	2

binding db-read-connection-settings

The recommended values listed in the table are for read operations:



Important The highlighted values must be explicitly configured.

Table 5: Recommended Value for Read Operations

Deployment	Bindings	connections-per-host-for-read	
		Default Values	Recommended Values
Small Deployment	drasession	5	5
	ipv6	5	5
	imsiapn	5	3
	msisdnapn	5	5
	ipv4	5	5
Large Deployment	drasession	5	20
	ipv6	5	20
	imsiapn	5	10
	msisdnapn	5	10
	ipv4	5	1

binding cluster-binding-dbs imsiapn-msisdnapn

The following configuration is applicable only for large deployments. With this configuration IMSI-APN and MSISDN-APN bindings databases use the same connection pool for database transactions. This configuration helps in reducing the overall threads count in the worker VM.

Table 6: Recommended Values

Deployment	Recommended Value
Small Deployment	Disable
Large Deployment	Enable

Audit Rate Limiter

Database Audit is an important functionality in DRA. To ensure that the database does not fill up with unnecessary entries or expired entries are cleared, a house keeping process is always functional. The following parameters should be used based on the deployment size and rated capacity of the system.

Table 7: Audit Rate Limiter Recommended Values

Deployment	Rate Limiter	Stale Session Expiry Count	Binding DB Read Preference
Small Deployment	100	6	Nearest
Large Deployment	51	6	Nearest

