



Add CDL Utility to PCF Software Image

Table 1: Feature History

Feature Name	Release Information	Description
Addition of CDL Utility to PCF Software Image	2023.04	PCF supports the <code>pcf-utilities</code> pod to retain the CDL utility scripts on master nodes post force VM redeploy from Cluster Manager. Default Setting: Enable – Always on

- [Feature Summary and Revision History, on page 1](#)
- [Feature Description, on page 2](#)
- [Configuration, on page 2](#)
- [Troubleshooting, on page 2](#)

Feature Summary and Revision History

Summary Data

Table 2: Summary Data

Applicable Products or Functional Area	PCF
Applicable Platform(s)	SMI
Feature Default Setting	Enabled - Always-on
Related Documentation	Not Applicable

Revision History

Table 3: Revision Details

Revision Details	Release
First Introduced.	2023.04.0

Feature Description

PCF supports the `pcf-utilities` pod to retain the CDL utility scripts on master nodes post force VM redeploy from Cluster Manager. Only the CDL utility scripts are productized through PCF software image.

The scripts is available on following master node persistent volume path:

```
/data/<pcf-namespace>/ data-pcf-utilities-0/cdl/
```

There is high availability during master node failure where scripts are available. The ouput generated from the utility are available in the same location where scripts are executed.

Configuration

The following configuration confirms the status of `volume-claims` to ensure if the volume is enabled:

```
# show running-config k8s
Tue Oct 3 17:48:44.943 UTC+00:00
k8s name unknown
k8s namespace pcf
k8s nf-name pcf
k8s registry dockerhub.cisco.com-smi-fuse-docker-internal
k8s single-node false
k8s use-volume-claims true
k8s image-pull-secrets regcred
k8s ingress-host-name 10.84.124.37.nip.io
```

Volume storage class is to be `local` in the DB configuration.

```
[unknown] pcf# show running-config db
Tue Oct 3 18:59:36.348 UTC+00:00
db global-settings db-replica 1
db global-settings volume-storage-class local
db spr shard-count 1
[unknown] pcf#
```



Note By default, the volume configurations are enabled.

Troubleshooting

Following are the troubleshooting scenarios:

1. To show persistent volume and volume claims.

Following is an output for the persistent volume and volume claims:

```
luser@rid5704583-aneeluru-1-master1:~$ kubectl get pvc -A | grep utilities
pcf data-pcf-utilities-0 Bound data-pcf-utilities-0-pcf 5Gi RWO local-storage 18h
luser@rid5704583-aneeluru-1-master1:~$
luser@rid5704583-aneeluru-1-master1:~$ kubectl get pvc -A | grep utilities
pcf data-pcf-utilities-0 Bound data-pcf-utilities-0-pcf 5Gi RWO local-storage 18h
luser@rid5704583-aneeluru-1-master1:~$
```

2. To display pcf-utilities pod.

Following is an output to show pcf-utilities pod:

```
luser@rid5704583-aneeluru-1-master1:~$ kubectl get pod -A | grep utilities
pcf      pcf-utilities-0      1/1     Running  0          18h   192.xxx.xxx.xxx
rid5704583-aneeluru-1-master1    <none>  <none>
luser@rid5704583-aneeluru-1-master1:~$
```

3. To display the pcf-utilities volume path and output.

Following example displays the pcf-utilities volume path and output:

```
luser@rid5704583-aneeluru-1-master1:~$ getpvs
NAMESPACE  NAME                                     STATUS   VOLUME
CAPACITY   ACCESS MODES   STORAGECLASS   AGE
pcf        data-pcf-utilities-0                   Bound    data-pcf-utilities-0-pcf
      5Gi       RWO           local-storage  18h
pcf        db-etcd-pcf-etcd-cluster-0             Bound    db-etcd-pcf-etcd-cluster-0-pcf
      10Gi      RWO           local-storage  18h
pcf        db-etcd-pcf-etcd-cluster-1             Bound    db-etcd-pcf-etcd-cluster-1-pcf
      10Gi      RWO           local-storage  18h
pcf        db-etcd-pcf-etcd-cluster-2             Bound    db-etcd-pcf-etcd-cluster-2-pcf
      10Gi      RWO           local-storage  18h
pcf        db-local-data-db-admin-0              Bound    db-local-data-db-admin-0-pcf
      5Gi       RWO           local-storage  18h
pcf        db-local-data-db-admin-config-0        Bound    db-local-data-db-admin-config-0-pcf
      5Gi       RWO           local-storage  18h
NAME          CAPACITY   ACCESS MODES   RECLAIM POLICY   STATUS
CLAIM         STORAGECLASS   REASON      AGE
data-pcf-utilities-0-pcf      5Gi       RWO          Retain      Bound
pcf/data-pcf-utilities-0      local-storage          18h
db-etcd-pcf-etcd-cluster-0-pcf      10Gi      RWO          Retain      Bound
pcf/db-etcd-pcf-etcd-cluster-0      local-storage          18h
db-etcd-pcf-etcd-cluster-1-pcf      10Gi      RWO          Retain      Bound
pcf/db-etcd-pcf-etcd-cluster-1      local-storage          18h
db-etcd-pcf-etcd-cluster-2-pcf      10Gi      RWO          Retain      Bound
pcf/db-etcd-pcf-etcd-cluster-2      local-storage          18h
db-local-data-db-admin-0-pcf      5Gi       RWO          Retain      Bound
pcf/db-local-data-db-admin-0      local-storage          18h
```

