Probleemoplossing voor Secure Access Error "a;VPN-vestigingsmogelijkheid voor een externe gebruiker is uitgeschakeld. Er wordt geen VPNverbinding tot stand gebracht"a ingesteld.

Inhoud		
Inleiding		
<u>Probleem</u>		
Oplossing		
Gerelateerde informatie		

# Inleiding

Dit document beschrijft hoe u een fout kunt oplossen: "De VPN-vestigingsmogelijkheid voor een externe gebruiker is uitgeschakeld. Er wordt geen VPN-verbinding tot stand gebracht."

## Probleem

Wanneer een gebruiker probeert verbinding te maken met RA-VPN (Remote Access VPN) met de Secure Access-head-end, wordt de fout afgedrukt in het venster voor beveiligde clientmelding van Cisco:

- VPN-vestigingsmogelijkheid voor een externe gebruiker is uitgeschakeld. A VPN connection will not be established.
- Cisco Secure-client kan geen verbinding met de opgegeven beveiligde gateway maken. Probeer het opnieuw.

🕈 🕙 Cisco Secure Client - 🗆 🗙	te modified
AnyConnect VPN: Ready to connect.	31/2023 1:14 AM 17/2023 5:01 PM
Cisco Secure Client	× 1/2023 2:07 AM
VPN establishment capability for a remote user is disabled. A VPN connection will not be established.	1/2023 2:05 AM
OK Cisco Secure Client	×
This PC Cisco Secure Client was not able to establish the specified secure gateway. Please try con	h a connection to necting again.
Metwork ems 1 item selected	ОК

Cisco Secure Client - probleem bij verbinding met Cisco Secure Access

De genoemde fout wordt gegenereerd wanneer de gebruiker via de RDP is verbonden met de Windows-pc, probeert verbinding te maken met RA-VPN vanaf de betreffende pc, en WindowsVPN Establishment is ingesteld Op Local Users Only (default option).

Windows VPN Establishment bepaalt het gedrag van de beveiligde client-Cisco wanneer een gebruiker die op afstand is aangemeld bij de client-pc een VPN-verbinding tot stand brengt. De mogelijke waarden zijn:

• Local Users Only

Verhindert een op afstand ingelogde (RDP) gebruiker een VPN-verbinding te maken.

• Allow Remote Users

Hiermee kunnen externe gebruikers een VPN-verbinding tot stand brengen. Als de ingestelde VPN-verbinding routing echter tot gevolg heeft dat de externe gebruiker wordt losgekoppeld, wordt de VPN-verbinding beëindigd om de externe gebruiker in staat te stellen weer toegang te krijgen tot de client-pc. Externe gebruikers moeten 90 seconden wachten na de oprichting van VPN als ze hun externe inlogsessie willen loskoppelen zonder dat de VPN-verbinding wordt beëindigd.

# Oplossing

Navigeer naar Cisco Secure Access Dashboard.

- Klik Op Connect > End User Connectivity
- Klik op Virtual Private Network
- · Kies het profiel dat u wilt wijzigen en klik op Edit

VPN Profiles A VPN profile allows	for configuration of n	emote user connections	through a VPN. <b>Help</b> <u>C</u>				^
New Servic     Download ti     Certificate	e Provider Certificat ne new service provie Management C	e der certificate and upload	d in your identity provider (IdP) to avo	id user Authentication failures. The cert	ificate will expire on date 11/8/2023. Download and	update the certificate now from	×
Q Search							+ Add
name	General	Authentication	Traffic Steering	Secure Client Configuration	Profile URL	Download XML	
CiscoSSPT1	ciscosspt.es TLS, IKEv2	SAML	Connect to Secure Access 1 Exception(s)	12 Settings	fb57.vpn.sse.cisco.com/CiscoSSPT1 🗗	<u>ح</u>	
							Edit
							Duplicate

Cisco Secure Access - PRI-VPN

Klik op Cisco Secure Client Configuration > Client Settings > Edit

← End User Connectivity VPN Profile			
General settings Default Domain: ciscospt.es   DNS Server: Umbrella (208.67.222.222, 208.67.222.220)   Protocol: TLS / DTLS, KEv2      Authentication	Cisco Secure Client Configure Select various settings to configure 2	guration e how Cisco Secure Client operates.Help C	+ Download VM
SAML Traffic Steering (Split Tunnel) Connect to Secure Access   1 Exceptions	Pre Selected Settings	tings 12 Client Certificate Settings 4	B Download XML
Cisco Secure Client Configuration	Use Start before Logon Minimize on connect	Enabled Enabled	
	Autoreconnect	Enabled	
	Windows Logon Enforcement	Single Local Logon	
	Linux Logon Enforcement	Single Local Logon	
	Windows VPN Establishment	All Remote Users	
	Linux VPN Establishment	Local Users Only	
	Clear SmartCard PIN	Enabled	
	IP Protocol Supported	IPv4	
	Proxy Settings	Native	
	Allow local proxy connections	Enabled	
	Authentication Timeout	30	
(	Cancel		Back Save

Cisco Secure Access - RA-VPN-clientconfiguratie

Klik op Administrator Settigns en wijzigen Windows VPN Establishment Van Local User Only in All Remote Users

	BE	FORE			AFT	ER
Administrator Settings			]			
Windows Logon Enforcement		Windows VPN Establishment		Windows Logon Enforcement		Windows VPN Establishment
Single Local Logon	~	Local Users Only v		Single Local Logon	*	All Remote Users ~
Linux Logon Enforcement		Linux VPN Establishment		Linux Logon Enforcement		Linux VPN Establishment
Single Local Logon	*	Local Users Only ~		Single Local Logon	~	Local Users Only ~

Cisco Secure Access - Windows VPN-instelling

#### En klik op Opslaan

General		3 ~
Administrator Settings		9 ^ 9
Windows Logon Enforcement	Windows VPN Establishment	
Single Local Logon ~	All Remote Users ~	
Linux Logon Enforcement	Linux VPN Establishment	
Single Local Logon ~	Local Users Only ~	
_		
Clear SmartCard PIN		User controllable
Clear SmartCard PIN		User controllable
Clear SmartCard PIN  IP Protocol Supported  IPv4	~	User controllable
Clear SmartCard PIN  Protocol Supported  Proxy Settings	~	User controllable
Clear SmartCard PIN  Protocol Supported  Proxy Settings Native	<ul> <li>✓</li> </ul>	User controllable
Clear SmartCard PIN  Protocol Supported  Proxy Settings Native  Allow local proxy connections	<ul> <li>✓</li> <li>✓</li> </ul>	User controllable

Cisco Secure Access - Windows VPN-instelling 2

Wanneer u de RA-VPN-sessie vanaf de externe Windows-pc instelt, moet u de Tunnel Mode als Bypass Secure Access. Anders loopt u het risico de toegang tot de externe Windows-pc te verliezen.



Cisco Secure Access - tunnelmodus

Voor meer informatie over Tunnel Mode check het volgende artikel punt nummer 6:

https://docs.sse.cisco.com/sse-user-guide/docs/add-vpn-profiles

### Gerelateerde informatie

- <u>Gebruikershandleiding voor beveiligde toegang</u>
- <u>Cisco Technical Support en downloads</u>

#### Over deze vertaling

Cisco heeft dit document vertaald via een combinatie van machine- en menselijke technologie om onze gebruikers wereldwijd ondersteuningscontent te bieden in hun eigen taal. Houd er rekening mee dat zelfs de beste machinevertaling niet net zo nauwkeurig is als die van een professionele vertaler. Cisco Systems, Inc. is niet aansprakelijk voor de nauwkeurigheid van deze vertalingen en raadt aan altijd het oorspronkelijke Engelstalige document (link) te raadplegen.