

在Firepower设备管理器中配置并验证系统日志

目录

[简介](#)

[先决条件](#)

[要求](#)

[配置](#)

[验证](#)

[故障排除](#)

简介

本文档介绍如何在Firepower设备管理器(FDM)中配置系统日志。

先决条件


要求

Cisco 建议您了解以下主题：


- Firepower威胁防御
- 运行Syslog软件以收集数据的Syslog服务器

配置

步骤1:在Firepower设备管理器主屏幕中，选择屏幕右下角System Settings下的Logging Settings。



第二步：在“系统设置”屏幕上，选择左侧菜单中的“日志记录设置”。



第三步：选择Syslog Servers下的+号设置Data Logging切换开关。

第四步：选择Add Syslog Server。或者，您可以在Objects - Syslog Servers中创建系统日志服务器对象。

Logging Settings

Remote Servers

DATA LOGGING

Syslog Servers



Filter

Nothing found

[Create new Syslog Server](#)

CANCEL

OK

Please select an Event List Filter

第五步：输入系统日志服务器的IP地址和端口号。选择“数据接口”的单选按钮，然后选择“确定”。

Edit Syslog Entry



IP Address

10.88.243.52

Protocol Type

UDP TCP

Port Number

514

514, 1025 - 65535

Interface for Device Logs

Select the interface for sending diagnostic syslog messages.

i Note: The source IP address will either be for the management interface, or for the gateway interface if you route through data interfaces.

Data Interface

Please select an interface

Management Interface

CANCEL

OK

第六步：接下来，选择新的Syslog服务器，然后选择OK。

Syslog Servers



Filter

<input checked="" type="checkbox"/>		10.88.243.52	
-------------------------------------	--	--------------	--

[Create new Syslog Server](#) CANCEL OK

步骤 7.选择Severity level for filtering all events单选按钮并选择所需的日志记录级别。

Remote Servers

DATA LOGGING

Syslog Servers



10.88.243.52

Severity level for filtering FXOS chassis syslogs

Information

Message Filtering for Firepower Threat Defense

Severity level for filtering all events

Information

Alert

Critical

Error

Warning

Notification

Information

Debug

步骤 8 选择屏幕底部的 Save。

SAVE

步骤 9 验证设置是否成功。

Device Summary

Logging Settings

✔ Successfully saved logging settings.

步骤 10部署新设置。



和

Pending Changes

✔ Last Deployment Completed Successfully
18 Aug 2022 03:18 PM. [See Deployment History](#)

Deployed Version (18 Aug 2022 03:18 PM)	Pending Version
Access Rule Edited: <i>Inside_Outside_Rule</i>	
ruleAction: TRUST	PERMIT
eventLogAction: LOG_BOTH	LOG_FLOW_END
+ Syslog Server Added: 172.16.1.250:514	
-	syslogServerIpAddress: 172.16.1.250
-	portNumber: 514
-	protocol: UDP
-	name: 172.16.1.250:514
deviceInterface:	
-	inside
Device Log Settings Edited: <i>Device-Log-Settings</i>	
syslogServerLogFilter.dataLogging.loggingEnabled: true	true
syslogServerLogFilter.dataLogging.platformLogLevel: INFORMATIONAL	INFORMATIONAL
-	syslogServerLogFilter.fileMalwareLogging.loggingEn: true
-	syslogServerLogFilter.fileMalwareLogging.severityL: true
syslogServerLogFilter.dataLogging.syslogServers:	
-	172.16.1.250:514
Access Policy Edited: <i>NGFW-Access-Policy</i>	

MORE ACTIONS ▾ CANCEL **DEPLOY NOW** ▾


可选。

此外，可以将访问控制策略访问控制规则设置为登录系统日志服务器：


步骤1: 点击屏幕顶部的Policies (策略) 按钮。



第二步： 将鼠标悬停在ACP规则的右侧以添加日志记录并选择铅笔图标。



第三步： 选择Logging选项卡，选择At End of Connection的单选按钮，选择Select a Syslog Alert Configuration下的下拉箭头，在Syslog Server上选择，然后选择OK。



第四步： 部署配置更改。

验证


步骤1:任务完成后，可以使用show running-config logging命令检验FTD CLI清除模式中的设置。

```
Copyright 2004-2020, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

Cisco Fire Linux OS v6.7.0 (build 62)
Cisco Firepower 2130 Threat Defense v6.7.0 (build 65)

[> show running-config logging
logging enable
logging timestamp
logging buffer-size 5242880
logging buffered informational
logging trap debugging
logging host ngfw-management 10.88.243.52
logging permit-hostdown
>
```

第二步：导航到Syslog服务器并验证Syslog服务器应用程序是否接受Syslog消息。



故障排除


步骤1:如果Syslog应用程序上的Syslog消息生成任何消息，请从FTD CLI执行数据包捕获以检查数据包。在clish提示符后输入system support diagnostic-cli命令，从Clish模式更改为LINA。

```
[> system support diagnostic-cli
Attaching to Diagnostic CLI ... Press 'Ctrl+a then d' to detach.
Type help or '?' for a list of available commands.

[FTD-1> en
[FTD-1> enable
[Password:
[FTD-1#
FTD-1#
```

第二步：为udp 514创建一个数据包捕获（如果使用tcp，则为tcp 1468）

第三步：验证通信是否正在进行到Syslog服务器上的网络接口卡。使用Wireshark或加载的其他数据包捕获实用程序。双击Wireshark中的接口，让系统日志服务器开始捕获数据包。



第四步：键入udp.port==514并选择顶部栏右侧的箭头，在顶部栏中为udp 514设置显示过滤器。从输出中，确认数据包是否正在发送到Syslog服务器。

*Ethernet0

Archivo Edición Visualización Ir Captura Analizar Estadísticas Telefonía Wireless Herramientas Ayuda

ip.addr == 10.88.146.119

No.	Time	Source	Destination	Protocol	Length	Info
26	0.328459	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:34: %FTD-7-710005: UDP request discarded from
145	0.965848	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:35: %FTD-7-710005: UDP request discarded from
294	1.902835	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:36: %FTD-7-710005: UDP request discarded from
303	1.969237	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:36: %FTD-7-710005: UDP request discarded from
435	3.614217	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:38: %FTD-7-710005: UDP request discarded from
461	3.990606	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:38: %FTD-7-710005: UDP request discarded from
523	4.329918	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:38: %FTD-7-710005: UDP request discarded from
540	4.465525	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:38: %FTD-7-710005: UDP request discarded from
572	4.904842	10.88.146.119	10.88.243.52	Syslog	155	LOCAL4.DEBUG: Aug 19 2022 16:59:39: %FTD-7-710005: UDP request discarded from

> Frame 26: 155 bytes on wire (1240 bits), 155 bytes captured (1240 bits) on interface \Device\NPF_{FFB4AA7C-2AE5-4A96-BFFA-F3A92CE11E17}, id 0

> Ethernet II, Src: Cisco_df:1a:f5 (84:3d:c6:df:1a:f5), Dst: VMware_b3:f9:3b (00:50:56:b3:f9:3b)

> Internet Protocol Version 4, Src: 10.88.146.119, Dst: 10.88.243.52

> User Datagram Protocol, Src Port: 36747, Dst Port: 514

> Syslog message: LOCAL4.DEBUG: Aug 19 2022 16:59:34: %FTD-7-710005: UDP request discarded from 0.0.0.0/68 to diagnostic:255.255.255.255/67\n

```

0000  00 50 56 b3 f9 3b 84 3d c6 df 1a f5 08 00 45 00  ·PV···:= ······E·
0010  00 8d 2b 13 40 00 3c 11 78 f1 0a 58 92 77 0a 58  ··+·@·<·x··X·w·X
0020  f3 34 8f 8b 02 02 00 79 6a a1 3c 31 36 37 3e 41  ·4······y j·<167>A
0030  75 67 20 31 39 20 32 30 32 32 20 31 36 3a 35 39  ug 19 20 22 16:59
0040  3a 33 34 3a 20 25 46 54 44 2d 37 2d 37 31 30 30  :34: %FT D-7-7100
0050  30 35 3a 20 55 44 50 20 72 65 71 75 65 73 74 20  05: UDP request
0060  64 69 73 63 61 72 64 65 64 20 66 72 6f 6d 20 30  discarde d from 0
0070  2e 30 2e 30 2e 30 2f 36 38 20 74 6f 20 64 69 61  .0.0./6 8 to dia
0080  67 6e 6f 73 74 69 63 3a 32 35 35 2e 32 35 35 2e  gnostic: 255.255.
0090  32 35 35 2e 32 35 35 2f 36 37 0a                255.255/ 67·

```

wireshark_Ethernet01BP1Q1.pcapng Paquetes: 11865 · Mostrado: 77 (0.6%) · Perdido: 0 (0.0%) Perfil: Default

第五步：如果Syslog服务器应用程序未显示数据，请排除Syslog服务器应用程序中的设置故障。确保使用的是正确的udp/tcp协议和正确的端口514/1468。

关于此翻译

思科采用人工翻译与机器翻译相结合的方式将此文档翻译成不同语言，希望全球的用户都能通过各自的语言得到支持性的内容。

请注意：即使是最好的机器翻译，其准确度也不及专业翻译人员的水平。

Cisco Systems, Inc. 对于翻译的准确性不承担任何责任，并建议您总是参考英文原始文档（已提供链接）。