將Azure配置為身份提供程式的FMC SSO

目錄

簡介 必要條件 需求 採用元件 背景資訊 IdP配置 SP配置 FMC上的SAML 限制和警告 設定 身份提供程式上的配置 Firepower管理中心上的配置 高級配置 — RBAC with Azure 驗證 疑難排解 瀏覽器SAML日誌 FMC SAML日誌

簡介

本文檔介紹如何使用Azure作為身份提供程式(idP)配置Firepower管理中心(FMC)單一登入(SSO)。

安全斷言標籤語言(SAML)是實現SSO的最常見的基礎協定。公司維護一個登入頁面,在其後面是一個身份儲存庫和各種身份驗證規則。它可以輕鬆配置任何支援SAML的Web應用,從而讓您登入到所有Web應用。它也有安全方面的好處,既不會強迫使用者為其需要訪問的每個Web應用保留(並可能重複使用)密碼,也不會將密碼暴露給這些Web應用。

必要條件

需求

思科建議您瞭解以下主題:

- 對Firepower管理中心的基本瞭解
- 對單點登入的基本瞭解

採用元件

本檔案中的資訊是根據以下軟體版本:

•思科Firepower管理中心(FMC)版本6.7.0

• Azure - IdP

本文中的資訊是根據特定實驗室環境內的裝置所建立。文中使用到的所有裝置皆從已清除(預設))的組態來啟動。如果您的網路運作中,請確保您瞭解任何指令可能造成的影響。

背景資訊

SAML術語

SAML的配置必須在兩個位置完成:在IdP和SP上。需要配置IdP,使其瞭解使用者想要登入到特定 SP時向何處傳送以及如何傳送該資訊。 需要配置SP,使其知道可以信任由IdP簽名的SAML斷言。

對SAML至關重要的幾個術語的定義:

- 身份提供程式(IdP) 執行身份驗證的軟體工具或服務(通常通過登入頁和/或儀表板進行視覺化);檢查使用者名稱和密碼、驗證帳戶狀態、呼叫雙因素等。
- •服務提供商(SP) 使用者嘗試獲取訪問許可權的Web應用程式。
- SAML斷言 通過瀏覽器重定向通過HTTP傳送的斷言使用者身份和通常為其他屬性的消息

ldP配置

SAML斷言的規範、斷言應包含的內容以及斷言的格式設定由SP提供並在IdP中設定。

- EntityID SP的全域性唯一名稱。格式各異,但看到此值格式化為URL的情況越來越常見。
 範例: <a href="https://<FQDN-or-IPaddress>/saml/metadata>">https://<FQDN-or-IPaddress>/saml/metadata>
- 斷言使用者服務(ACS)驗證器 正規表示式(regex)形式的安全措施,用於確保SAML斷言傳送 到正確的ACS。這僅在由SP發起的登入期間起作用,其中SAML請求包含ACS位置,因此,此 ACS驗證程式將確保SAML請求提供的ACS位置是合法的。
 示例:https://<FQDN-or-IPaddress>/saml/acs
- Attributes 屬性的數量和格式可能大不相同。通常至少有一個屬性nameID,它通常是嘗試登 入的使用者的使用者名稱。
- SAML簽名演算法 SHA-1或SHA-256。不太常用的SHA-384或SHA-512。此處提到此演算法 與X.509證書結合使用。



SP配置

與上面部分相反,本節介紹ldP提供的資訊並在SP上設定。

- 頒發者URL IdP的唯一識別符號。格式化為包含有關IdP資訊的URL,以便SP可以驗證其收到 的SAML斷言是從正確的IdP發出的。
 示例: <saml:Issuer https://sts.windows.net/0djgedfasklf-sfadsj123fsdv-c80d8aa/ >
- SAML SSO終結點/服務提供商登入URL 一個IdP終結點,當SP在此使用SAML請求重定向時 啟動身份驗證。

示例: https://login.microsoftonline.com/023480840129412-824812/saml2

• SAML SLO(單一註銷)終結點 — 一個IdP終結點,它在SP重定向到此處時關閉IdP會話,通 常是在按一下**註銷**之後。 示例: https://access.wristbandtent.com/logout

FMC上的SAML

FMC中的SSO功能是從6.7開始引入的。新功能簡化了FMC授權(RBAC),因為它將現有資訊對映到 FMC角色。它適用於所有FMC UI使用者和FMC角色。目前,它支援SAML 2.0規範以及這些支援的 IDP

- OKTA
- OneLogin
- PingID
- Azure AD
- 其他(符合SAML 2.0的任何IDP)

限制和警告

- •只能為全域性域配置SSO。
- HA配對中的FMC需要個別組態。
- •只有本地/AD管理員可以配置單一登入。
- 不支援從ldp啟動的SSO。

設定

身份提供程式上的配置

步驟1.登入Microsoft Azure。導航到Azure Active Directory >企業應用程式。

Home >	
Default Directory C Azure Active Directory	Overview
*	💿 Switch tenant 📋 Delete tenant 🕂 Create
i Overview	
🚀 Getting started	
Preview hub	Azure Active Directory can help you enable remote
🔀 Diagnose and solve problems	Default Directory
Manage	Search your tenant
🚨 Users	y search your tenant
🚨 Groups	Tenant information
External Identities	Your role
Roles and administrators	Global administrator More info
Administrative units (Preview)	License
Enterprise applications	Azure AD Free
	Tenant ID

•步驟2.在「Non-Gallery Application」下建立新應用程式,如下圖所示。

Home > Default Directory > Enterprise applications | All applications > Add an application >

Add your own application

Name * ①	
Firepower Test	~
Once you decide on a name for your new application, click the "Add" button below and we'll walk you through some simple configuration steps to get the application working.	
Supports: ①	
SAML-based single sign-on Learn more	
Automatic User Provisioning with SCIM Learn more	

Password-based single sign-on Learn more

步驟3.編輯已建立的應用程式,然後導覽至Set up single sign on > SAML,如下圖所示。



步驟4.編輯基本SAML配置並提供FMC詳細資訊:

- FMC URL: https://<FMC-FQDN-or-IPaddress>
- •識別符號(實體ID): <u>https://<FMC-FQDN-or-IPaddress>/saml/metadata</u>
- 回覆URL: <u>https://<FMC-FQDN-or-IPaddress>/saml/acs</u>
- 登入URL: /https://<FMC-QDN-or-IPaddress>/saml/acs
- RelayState:/ui/login

Enterprise Application



將剩餘部分保留為預設值 — 對於基於角色的訪問,將對此進行進一步討論。

這標籤身份提供程式配置的結束。下載將用於FMC配置的聯合後設資料XML。

Firepower管理中心上的配置

步驟1.登入到FMC,導航到設定>使用者>單點登入並啟用SSO。選擇Azure作為提供程式。

cisco	Firepower Ma System / Users / S	anagement Center	Overview	Analysis	Policies Devices Objects AMP Intelligence	
User	s User Roles	External Authentication	Single Sign	-On	Single Sign-On (SSO) Configuration	
				Select FM	IC SAML Provider	• ×
				Select the S Okta OneLo Azure PingID Other	GAML provider to authenticate SSO users for the FMC:	
				Step 1 of 3		Next

步驟2.在此處上載從Azure下載的XML檔案。它會自動填充所需的所有詳細資訊。

	Single Sign-On (SSO) Configuration	
	Configuration Details 🖌 Identity Provider Single Sign-On URL	
Configure A	zure Metadata	@ ×
Configure the F required fields Manual Co O Upload XI	MC to work with your Azure IdP by selecting one of the following two opt for your SSO manually, or upload the XML metadata file. onfiguration ML File	ions: Fill out
Drag a creder	nd drop an XML file here, or click to upload an XML file containing your S ntials.	SO
Step 2 of 3	Back	Next

步驟3.驗證組態並按一下Save,如下圖所示。

Verify Azure Metadata	9	×	(
Test the Azure metadata by clicking the Test Configuration button on the System / Users / S Sign-On page after you save.) Identity Provider Single Sign-On URL	ingle		
Identity Provider Issuer			
X.509 Certificate			
Step 3 of 3 Back	Save	Ð	

高級配置 — RBAC with Azure

若要使用各種角色型別對映到FMC的角色 — 您需要編輯Azure上的應用程式清單以將值分配給角色。預設情況下,角色具有Null值。

步驟1.導航到建立的Application,然後按一下Single sign-on。

Home > Default Directory | App registrations >



Search (Cmd+/) «	🔟 Delete 🌐 Endpoints
R Overview	Display name : Cisco-Firepower
🍊 Quickstart	Application (client) ID :
💉 Integration assistant (preview)	Directory (tenant) ID :
Manage	Object ID :
Branding	
➔ Authentication	Starting June 30th, 2020 we will no longer add any new features to Azure Active Directory Authentic updates. Applications will need to be upgraded to Microsoft Authentication Library (MSAL) and Mic
📍 Certificates & secrets	
Token configuration	
-> API permissions	Call APIS
Expose an API	
Owners	
Roles and administrators (Preview)	
0 Manifest	
Support + Troubleshooting	Build more powerful apps with rich user and business data from Microsoft services and your own company's data sources.
P Troubleshooting	View API permissions
New support request	

步驟2.編輯使用者屬性和宣告。新增名為:角色並選擇值作為user.assignedroles。

Home > Default Directory > Enterprise applications | All applications > Cisco-Firepower | Single sign-on > SAML-based Sign-on >

User Attributes & Claims

T Add new claim T Add a group claim == Columns		
Required claim		
Claim name	Value	
Unique User Identifier (Name ID)	user.userprincipalname [nameid-for	
Additional claims		
Claim name	Value	
Claim name http://schemas.xmlsoap.org/ws/2005/05/identity/claims/emailaddress	Value user.mail	••••
Claim name http://schemas.xmlsoap.org/ws/2005/05/identity/claims/emailaddress http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname	Value user.mail user.givenname	•••
Claim name http://schemas.xmlsoap.org/ws/2005/05/identity/claims/emailaddress http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name	Value user.mail user.givenname user.userprincipalname	••••
Claim name http://schemas.xmlsoap.org/ws/2005/05/identity/claims/emailaddress http://schemas.xmlsoap.org/ws/2005/05/identity/claims/givenname http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name http://schemas.xmlsoap.org/ws/2005/05/identity/claims/surname http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name	Value user.mail user.givenname user.userprincipalname user.surname	····

步驟3.導覽至**<Application-Name> > Manifest**。 編輯清單。檔案採用JSON格式,預設使用者可供 複製。例如 — 此處建立了2個角色:使用者和分析師。

Home > Default Directory App registra	tions >	
Cisco-Firepower M	anifest	\$
✓ Search (Cmd+/) «	Save	🗙 Discard 👖 Upload 🚽 Download 🛛 ♡ Got feedback?
Overview	The editor	r below allows you to update this application by directly modifying its JSON represer
🗳 Quickstart		
A	1 {	
Integration assistant (preview)	2	"id": "00f52e49-10a0-4580-920f-98aa41d58f6f",
	3	"acceptMappedClaims": null,
Manage	4	"accessTokenAcceptedVersion": null,
🚍 Branding	5	"addIns": [], "allowPublicCliont": false
	7	"annId": "51dcc017-6730-41ee-b5cd-4e5c380d85c3"
Authentication	8	"appRoles": [
Contificator & correte	9	{
	10	"allowedMemberTypes": [
Token configuration	11	"User"
	12	1,
API permissions	13	"description": "Analyst",
Expose an API	14	"displayName": "Analyst",
	15	"id": "18d14569-c3bd-439b-9a66-3a2aee01d13f",
Owners	16	"isEnabled": true,
	1/	"tang": null,
Roles and administrators (Preview)	10	"value": "Analyst-1"
0 Manifest	20	<pre>}.</pre>
	21	{
Support + Troubleshooting	22	"allowedMemberTypes": [
	23	"User"
A Troubleshooting	24],
	25	"description": "User",
New support request	26	"displayName": "User",
	27	"1d": "18d14569-c3bd-439b-9a66-3a2aee01d14f",
	28	"Istnabled": true,
	30	"origin": "Application".
	31	"value": "User-1"
	32	}.

步驟4.導航到**<Application-Name> > Users and Groups**。編輯使用者並分配新建立的角色,如下圖 所示。

Edit Assianment	Only a single role can be selected
Default Directory	P Enter role name to filter items
Users	Analyst
Select a role	User
None Selected	>
	-
	Selected Role
	Applyst
	Analyst

步驟4.登入到FMC並在SSO中編輯高級配置。對於, 組成員屬性:答 將您在應用程式清單中提供 的**顯示名稱**分配給角色。

 Advanced Configuration (Role Mapping) 					
Default User Role	Administrator				
Group Member Attribute	roles				
Access Admin					
Administrator					
Discovery Admin					
External Database User					
Intrusion Admin					
Maintenance User					
Network Admin	User				
Security Analyst					
Security Analyst (Read Only)	Analyst				
Security Approver					
Threat Intelligence Director (TID) User					

完成後,您應該能夠登入到他們的指定角色。

驗證

步驟1.從瀏覽器導航至FMC URL:https://<FMC URL>。按一下「Single Sign-On」,如下圖所示。

cisco	
Firepower Management	
Center	
Username Password	
Single Sign-On Log In	
	Junction Firepower Management Center

系統會將您重新導向至Microsoft登入頁面,且成功登入將返回FMC預設頁面。

步驟2.在FMC上,導航到**System > Users**,檢視新增到資料庫的SSO使用者。

test1@shbharticisco.onmicrosoft.com	Security Analyst	External (SSO)
test2guy@shbharticisco.onmicrosoft.com	Administrator	External (SSO)

驗證SAML身份驗證,這是成功授權所實現的工作流程(此映像為實驗室環境):

瀏覽器SAML日誌

GET	https://10.106.46.191/sso/saml/login
GET	https://login.microsoftonline.com/0f03f72e-db12-496d-89b5-4ab9fc80d8aa/saml2?RelayState=7_ni-J1fNA5sEeVvoAuhcvtH6CWKjxwyGhhxJpArDjKAFMbK-wvJ2RSP&SAMLFSAML
GET	https://login.live.com/Me.htm?v=3
POST	https://login.microsoftonline.com/common/GetCredentialType?mkt=en-US
POST	https://login.microsoftonline.com/0f03f72e-db12-496d-89b5-4ab9fc80d8aa/login
GET	https://login.live.com/Me.htm?v=3
POST	https://login.microsoftonline.com/kmsi
POST	https://10.106.46.191/sami/acs SAML
GET	https://login.microsoftonline.com/favicon.ico
GET	https://10.106.46.191/sso/saml/login
GET	https://10.106.46.191/ui/login
POST	https://10.106.46.191/auth/login

FMC SAML日誌

在/var/log/auth-daemon.log上驗證FMC上的SAML日志

root@shbhartiiftfmc1:/var/log# tail -f auth-daemon.log	
suth-daemon 2020/08/09 04:59:11 I! Writing Audit Log to DB.	
suth-daemon 2020/08/09 04:59:11 I! Parsing SAML ACS Response	
suth-daemon 2020/08/09 04:59:11 I! SAML ACS Response Parsed, ID: id-56574e8a5f44bdd50102743d2cc9350b75f74d8c	
suth-daemon 2020/08/09 04:59:11 I! Authorizing Response, ID : id-56574e0a5f44bdd50102743d2cc9350b75f74d8c	
suth-daemon 2020/08/09 04:59:11 I! No member value in Data. Using Default Role.	
suth-daemon 2020/08/09 04:59:11 I! Attribute Map in the token : map[http://schemas.microsoft.com/claims/authnmethodsreferences:[http://schemas.microsoft.com/ws/2008/06/identity/authenticationmethous	d/password]
ttp://schemas.microsoft.com/identity/cla///b5-4ab9fc80d8aa/} http://schemas.microsoft.com/identity/cla	
.microsoft.com/identity/claims/objectide	mlsoap.org/
/2005/05/identity/claims/givenname:[Test]] http://schemas.xmlsoap.org/ws/2005/05/identity/claims/name:[test1@shbharticisco.onmicrosoft.com] http://schemas.xmlsoap.org/ws/2005/05/identity/claims/si	
napped_role_uuid:[bee2eb18-e129-11df-a04a-42c66f0a3b36]]	