



CHAPTER 2

Transport Gateway Installation / Registration / Configuration

This chapter covers the following areas:

- [Transport Gateway requirements.](#)
- [Security Considerations When Using a Transport Gateway.](#)
- [Installation process overview for the Transport Gateway.](#)
- [Download the Transport Gateway package.](#)
- [Install the Transport Gateway package for Windows.](#)
- [Uninstall the Transport Gateway for Windows.](#)
- [Install the Transport Gateway for Solaris.](#)
- [Uninstall the Transport Gateway for Solaris.](#)
- [Register and configure the Transport Gateway.](#)
- [Using the Call Home Mailbox.](#)

Transport Gateway Requirements

The Transport Gateway is operational on the following operating systems:

- [Solaris](#)
- [Windows: 2000, 2003, XP platforms](#)

The Transport Gateway will be installed on the workstation, which has access to the Call Home mailbox, in the event that the user wants to use the Transport Gateway to forward Call Home messages securely, using an SSL connection.

System Requirements for Solaris

The following are the system requirements for the Solaris platform:

- Operating System – Solaris 5.8 (5.8 or Higher is Recommended).
- CDE or Xterm (Display supported).
- Netscape Navigator 4.76 or later.
- Textedit or dtpad application for viewing log files from the User Interface of Transport Gateway.
- Sun sparc Processor.
- PC or laptop with 512 MB of RAM (1 GB recommended).
- Hard disk: 60 MB + (15KB for every Call Home message).
- Broadband Internet connectivity for faster response to the Cisco servers (recommended).

System Requirements for Windows

System Requirements for Windows for the Transport Gateway Smart Call Home Connector:

- Operating System:
 - Windows 2000
 - Windows 2003
 - Windows XP platforms
 - Pentium 4 or later (Pentium M recommended)
- PC or laptop with 512 MB of RAM (1 GB recommended).
- Hard disk: 60 MB + (15KB for every Call Home message).
- Broadband Internet connectivity for faster response to the Cisco servers (recommended).

Security Considerations When Using a Transport Gateway

When going through a Transport Gateway follow the instructions listed below:

- The SMTP protocol is not encrypted and hence the path between the Catalyst switch and the Transport Gateway through the SMTP server must be located in a secure zone. The network administrator must ensure that the path between the Catalyst switch and the Transport Gateway is such that the packets are not transported across networks where there is a possibility of the packets being snooped and hence inadvertently provide access to proprietary information.

Sensitive information in the switch configuration such as passwords and SNMP Community strings are scrubbed before being sent over the wire as a means of mitigating the risk of exposure.

- We recommend that the Transport Gateway be installed on the secure internal network, rather than off another segment on the firewall. In a typical configuration, this setup will provide access to the Proxy server, the Email server as well as to the Internet. This would be done without requiring changes to the firewall configuration, as all communication will be initiated by the Transport Gateway from the Internal network on the highest security zone to other segments in lower security zones.

Any return communication will also pass through the firewall as the traffic will be part of an existing session.

- As part of Transport Gateway registration, the Transport Gateway sends a registration request to the Cisco backend. The Cisco backend generates a unique Transport Gateway ID and a password and sends these back to the Transport Gateway in the response. This ID and Password are sent in any request to the Cisco backend after the initial registration.

This communication is through HTTPS and using port 443; see [Table 2-1](#) for a list of the protocols and ports used between the source and destination devices in this mode of communication.


- For customers who need to proxy any traffic between their network and the outside world, the Transport Gateway can communicate with a HTTPS proxy server. The configuration windows in the Transport Gateway enables the setting of the proxy server name and port number.

Table 2-1 Protocols and Ports used with the Transport Gateway

Source	Destination	Protocol	Port	Purpose
Catalyst Switch	Customer Email Server	SMTP	25	Switch to send mail to the TG
Transport Gateway	Customer Email Server	POP3/IMAP	110/143 respectively and can be changed by the customer	TG to pick up the mail from the Switch
Transport Gateway	Cisco's back-end server	HTTPS	443	TG to send SCH messages to the back-end server without a proxy server – Option 1
Transport Gateway	Customer's proxy server en route to Cisco's back-end server	HTTPS	Customer Supplied	TG to send SCH messages to the back-end server using a proxy server – Option 2

Installation Process Overview for the Transport Gateway

The Transport Gateway will be automatically registered on the Cisco backend during installation. The following figure displays an overview of the Transport Gateway installation and registration process.



Download the Transport Gateway Package

To download the Transport Gateway package perform the following tasks:

-
- Step 1** Cisco Transport Gateway package can be downloaded from the following URL <http://www.cisco.com/cgi-bin/tablebuild.pl/cisco-transport-gateway>. Click the previous link and the corresponding window opens. The customer needs to log in to the web application where a link to the download location will be provided.
- Step 2** On the web application click the download link for the Cisco Transport Gateway package to start downloading the package.




Note The user is not required to be registered in the Smart Call Home application for downloading the Transport Gateway package.

Install the Transport Gateway Package for Windows

Install the Transport Gateway package, by continuing the following tasks:

-
- Step 1** Double-click on the downloaded the Transport Gateway executable; this starts the Transport Gateway installation wizard.




Note A logo briefly appears which contains the Cisco Transport Gateway version and release information, followed by a brief display of the initializing window, then the Welcome window for the Installation Wizard appears.


Install the Transport Gateway Package for Windows



184177




184178




184179

- Step 2** Click **Next** to continue the install process; the Directory name location window appears.



- Step 3** Either use the default location to install the Transport Gateway or select a different location by clicking **Browse** and navigating to the new directory location.
- Step 4** When the correct directory location is specified in the Directory Name field, click **Next**; the Transport Gateway is installed in the default or new specified directory location and a summary information page appears


■ Install the Transport Gateway Package for Windows




Step 5 Review the information on the page and validate the following items:

- Installation directory location is correct.
- Storage requirement is acceptable.

Step 6 After verifying data, click **Install**; the installation progress window appears

**Note**

After the wizard completes the installation, a window appears that indicates the installation is successfully completed.



- Step 7** When the system detects that the Transport Gateway has not yet been registered on the Cisco backend, the system requests the customer to complete the Transport Gateway installation.

**Note**

The customer can install an upgrade of the Transport Gateway over the current version, without having to do any of the following tasks:


- Manually uninstall the current version.
- Re-configure the Transport Gateway.
- Re-register the Transport Gateway on the Cisco backend.

- Step 8** Click **Finish**; a Cisco Transport Gateway window appears, with the Proxy Settings tab selected.

Uninstall the Transport Gateway for Windows

This section describes the process for uninstalling the Transport Gateway.

To uninstall the Transport Gateway application, perform the following steps:




184184

- Step 1** On the Windows desktop click **Start > All Programs > Cisco Transport Gateway > Uninstall Cisco Transport Gateway**; an informational window containing the version and release data appears briefly, followed by the Cisco Transport Gateway - Uninstallation Wizard.



184185


Uninstall the Transport Gateway for Windows



- Step 2** Click **Next**; a prompt appears asking if you would like to keep the Transport Gateway Registration in Smart Call Home, the default is Yes.




- Step 3** Click the option you want to use; clicking **Yes** keeps the Transport Gateway registration before performing the uninstall. Clicking either option **Yes** or **No** displays the summary information window which identifies the folder where the Cisco Transport Gateway application was installed.




- Step 4** Ensure that the correct location is referenced and click **Uninstall**; a progress window appears indicating what percentage of the uninstall process is completed, and still remains

■ Uninstall the Transport Gateway for Windows



- Step 5** When the uninstall process has completed, an informational window opens and indicates that the Cisco Transport Gateway was successfully uninstalled.



Step 6 Click **Finish**.

Install the Transport Gateway for Solaris

To install the Transport Gateway application on the machines running Solaris operation System, a binary installer of the Transport Gateway for the Solaris Sparc should be downloaded and executed for installation.

Modes of Installation

There are three modes of installation

1. **GUI mode** – It will have wizards which will guide user to the installation process.
2. **Console mode**– The installation progress will be displayed on the console (e.g. Xterm display supported).

3. **Silent mode** – Installation will be performed in the background and no wizards and progress information will be displayed during the process.

Installing the Transport Gateway Bundle in GUI mode

To install the Transport Gateway in GUI mode perform the following steps:

-
- Step 1** Download the installer to the Solaris machine in a binary mode.
 - Step 2** Navigate to the directory that contains the installer.
 - Step 3** If necessary, change the installer file's permissions to make the binary executable by typing from a command prompt:

```
$ chmod +x your_binary_executable
e.g., $ chmod 755 CSCOSchtg.install
```



Note Be sure to replace `your_binary_executable` with the actual filename of the binary that you downloaded.


- Step 4** The installation directory for the Transport Gateway would be `/opt/CSCOSchtg`. Make sure, you have adequate space on your system for the installation.
- Step 5** Launch the installer by typing from a command prompt:

```
$ ./your_binary_executable
```



Note Again, be sure to replace `your_binary_executable` with the actual filename of the binary that you downloaded.

The starting message is shown in the following figure.




- Step 6** The splash window appears for a few seconds and then the wizard shows a dialog to indicate that it is preparing for the setup as shown in the figure.




- Step 7** The wizard displays a welcome window that provides the details of the application that will be installed.

■ Install the Transport Gateway for Solaris




Step 8 Click **Next**; the installation wizard window appears.




- Step 9** Click **Install** to start installing Cisco Transport Gateway onto your computer.
- Step 10** Once the installation process is completed, you will get a confirmation message informing that the installation was successful.
- Step 11** After installation is done, Cisco Transport Gateway client application can be seen in the location '/opt/CSCOSchtg'.


Install the Transport Gateway for Solaris



Step 12 Click **Finish** to complete the installation process and launch the application; the xterm window shows the start of the application.



- Step 13** After successful installation and launch of the Transport Gateway, the Transport Gateway Application appears.



184197

To install the Transport Gateway bundle in Console mode

To install the Transport Gateway in Console mode, perform the following steps:

- Step 1** Download the installer to the Solaris machine in a binary mode.
- Step 2** Navigate to the directory that contains the installer.
- Step 3** If necessary, change the installer file's permissions to make the binary executable by typing from a command prompt:

```
$ chmod +x your_binary_executable
e.g. $ chmod 755 CSCOSchtg.install
```



- Note** Be sure to replace `your_binary_executable` with the actual filename of the binary that you downloaded.

Install the Transport Gateway for Solaris

Step 4 The installation directory for the Transport Gateway would be `/opt/CSCOSchtg`. Make sure, you have adequate space on your system for the installation.

Step 5 Launch the installer by typing from a command prompt:

```
$ ./your_binary_executable
e.g. $ ./CSCOSchtg.install -silent
```



Note Again, be sure to replace `your_binary_executable` with the actual filename of the binary that you downloaded.

No intervention is required from the user, After Successful installation; the Transport Gateway will automatically start the service and launches the UI.

```
xterm via TELNET)
-----
WELCOME
-----

The Installation of the Cisco Transport Gateway might take 7 to 10 minutes for
completion. Please wait while the installation is in progress.

Preparing the installer...
OK: Checking JRE patches
WARNING: It is strongly recommended that you apply the following patches to your
system
108993-41
111023-02
112438-01
111308-05
109147-24
110934-10
110380-04
108989-02
108528-22
108987-13
108940-54
112396-02
111111-03
108714-07
112472-01
111310-01
108773-19
108921-16
108652-98
112003-03
```

184188

```

112003-03
PRE INSTALL SUMMARY:
-----
Cisco Transport Gateway will be installed in the following location:

/opt/CSCOSchtg

for a total size:

    95.1 MB
Admin Rights OK ...
Creating built in user...
Creating built in group...
Installing bin...
Installing resources...
Installing lib...
Installing com...
Installing conf...
POST INSTALL SUMMARY:
-----
The Cisco Transport Gateway package was successfully installed.
Launching service...
Please do the following tasks to complete installation.
(a) Proxy Settings
(b) Register Transport Gateway
(c) Configure Cisco Transport Gateway
Note: Application launching may take few minutes. Please wait...

# █

```

184199

To install the Transport Gateway bundle in Silent mode:

To install the Transport Gateway in Silent mode perform the following steps:

-
- Step 1** Download the installer to the Solaris machine in a binary mode.
 - Step 2** Navigate to the directory that contains the installer.
 - Step 3** If necessary, change the installer file's permissions to make the binary executable by typing from a command prompt:

```
$ chmod +x your_binary_executable
e.g. $ chmod 755 CSCOSchtg.install
```



Note

Be sure to replace `your_binary_executable` with the actual filename of the binary that you downloaded.

Step 4 The installation directory for the Transport Gateway would be '/opt/CSCOSchtg'. Make sure, you have adequate space on your system for the installation.

Step 5 Launch the installer by typing from a command prompt:

```
$ ./your_binary_executable -silent
e.g. $ ./CSCOSchtg.install -silent
```



Note Again, be sure to replace your_binary_executable with the actual filename of the binary that you downloaded.

Use CDE / Xterm (Display supported)

No intervention is required from the user, After Successful installation; the Transport Gateway will automatically start the service and launches the UI.

Uninstall the Transport Gateway for Solaris

There are three modes of installation

1. **GUI mode** – It will have wizards which will guide user to the uninstallation process.
2. **Console mode** –The uninstallation progress will be displayed on the console (e.g. Xterm display supported).
3. **Silent mode** – Uninstallation will be performed in the background and no wizards or progress information will be displayed during the process.

Uninstall the Transport Gateway Bundle in GUI mode


To uninstall the Transport Gateway in GUI mode perform the following steps:

Step 1 The user can uninstall Cisco Transport Gateway client application by executing the file '/opt/CSCOSchtg/_uninstTG/uninstaller.bin' in command line from the root directory.




Note The mode of Uninstallation will be automatically chosen by the uninstaller as same as the Installation mode.

- Step 2** Navigate to the root (/) directory of the Solaris system.
- Step 3** Execute the command “/opt/CSCOSchtg/_uninstTG/uninstaller.bin” from the command prompt, the following window opens.




- Step 4** Click **Next** in the welcome window to continue. The user will be prompted with the option to keep the Transport Gateway registration in Smart Call Home.

■ Uninstall the Transport Gateway for Solaris




- Step 5** Click **Yes** to save the registration; the Uninstallation wizard shows the location of installed path.




- Step 6** Click **Uninstall** to uninstall the application; after a few minutes the uninstall process is completed.

Uninstall the Transport Gateway for Solaris



184203

- Step 7** Click **Finish**; this completes the install on the computer.
- Step 8** The xterm window shows that the Transport Gateway was successfully uninstalled.



184204

Uninstall the Transport Gateway bundle in Console mode

To uninstall the Transport Gateway in GUI mode perform the following steps:

- Step 1** The user can uninstall Cisco Transport Gateway client application by executing the file '/opt/CSCOSchtg/_uninstTG/uninstaller.bin' in command line from the root directory.



- Note** The mode of Uninstallation will be automatically chosen by the uninstaller as same as the Installation mode.

- Step 2** A pop up appears. “Would you like to keep the transport gateway registration in Smart Call Home? Yes/No”, Select your choice; a window then shows the progress of the uninstallation process.

- Step 3** The xterm window shows that the Transport Gateway was successfully uninstalled.

```
xterm via TELNET)

      Initializing MultiPlatform Application Launcher.....
      Launching InstallShield Wizard.....

PRE UN-INSTALL SUMMARY:
-----
Cisco Transport Gateway will be uninstalled from the following location:

/opt/CSCOSchtg
Preparing the uninstaller. Please wait...

The Uninstallation of the Cisco Transport Gateway might take 3 to 6 minutes for
completion. Please wait while uninstallation is in progress.

Uninstallation is in progress...
POST UN-INSTALL SUMMARY:
-----
The Cisco Transport Gateway was successfully uninstalled.

#
```

Uninstall the Transport Gateway bundle in Silent mode

To uninstall the Transport Gateway in GUI mode perform the following steps:

- Step 1** The user can uninstall Cisco Transport Gateway client application by executing the file `'/opt/CSCOSchtg/_uninstTG/uninstaller.bin - silent'` in command line from the root directory.



Note The mode of Uninstallation will be automatically chosen by the uninstaller as same as the Installation mode. No intervention is required from the user.

Register and Configure the Transport Gateway

To complete the installation of Transport Gateway package you need to:

- [Launch the Cisco Transport Gateway Application.](#)
- [Select the Proxy Settings.](#)
- [Test Connection before Registration.](#)
- [Register the Transport Gateway.](#)
- [Configure the Transport Gateway Mailbox Settings.](#)



Note The Transport Gateway Registration is done after the Transport Gateway Installation.

Other items that are covered in this section explain how to do the following:

- [Reset the Transport Gateway Password.](#)
- [Using the Call Home Mailbox.](#)
- [Retrieving and Forwarding Call Home Messages from the Mailbox.](#)
- [Maintain Call Home Messages in the Mailbox.](#)
- [Notify the Customer When the Mail Store Reaches Limit.](#)
- [View and Zip the Log Status file.](#)
- [Stop the Transport Gateway Service.](#)
- [Close the Transport Gateway Application Window.](#)

Launch the Cisco Transport Gateway Application




The Cisco Transport Gateway application window appears in the following scenarios:

- The Cisco Transport Gateway application automatically opens when the Transport Gateway installation successfully completes.
- The Transport Gateway installation has been completed and the following is done on one of the following environments:
 - On the Windows desktop choose **Start > All Programs > Cisco Transport Gateway > Configure Cisco Transport Gateway**.



- In Solaris there are two options:
 - If user uses Xterm – User has to execute the command for Configure Cisco Transport Gateway: “/opt/CSCOSchtg/tg/bin/configure.bin”.
 - If user uses CDE: User can launch the configure Transport gateway as in the following figures.

Register and Configure the Transport Gateway



Any of the previous scenarios opens the Cisco Transport Gateway Application window; this window lets you perform the following tasks:


- [Specify the Proxy Settings](#) (default area displayed).
- [Test Connection before Registration](#), from the Transport Gateway to the Cisco Backend.
- [Register the Transport Gateway](#).
- [Configure the Transport Gateway Mailbox Settings](#).
- [Reset the Transport Gateway Password](#).
- [Using the Call Home Mailbox](#).
- [View and Zip the Log Status file](#).
- [Stop the Transport Gateway Service](#).
- [Close the Transport Gateway Application Window](#).

Specify the Proxy Settings

Set Proxy Settings is the default area displayed when the Cisco Transport Gateway Application window opens. This area lets you specify if a proxy server is being used by the Transport Gateway and if so, what the settings should be.

Register and Configure the Transport Gateway

This option is used when a customer installs a Transport Gateway package or wants to modify the existing proxy settings. The customer can specify or change the proxy settings to be used any time after the Transport Gateway has been installed.



To access the different functions on the Cisco Transport Gateway Application perform the following steps:

- Step 1** Click the option that indicates the type proxy server that exists for the Call Home environment:
- No proxy (default for Solaris).
 - Use default proxy (default for Windows OS, not applicable for Solaris).
 - Enter HTTPS proxy server (IP address or hostname) and port number.



Note If the “Enter HTTPS proxy server” choice is selected, you must enter the information for the two corresponding fields.

If the “Use default proxy” or the “Enter HTTPS proxy server” choice is

selected, the proxy user name and password is needed only when proxy authentication is required at the customer site.

If you are unsure what option needs to be selected, contact your IT dept. for additional information.

Test Connection before Registration

Before Registering the Transport Gateway you need to ensure that you can establish the two following connections to the:


- Internet
- Cisco Backend

The Test Connection function notifies you of the status of these two connections; the following events occur during the Test Connection check:

- The customer triggers the connection test with the Cisco Backend.
- The Transport Gateway verifies if there is still a connection with the Cisco Backend.
- The Cisco Backend sends a confirmation.
- The Transport Gateway displays a message indicating the successful connection to the backend or an error message.


To test the connection to the Internet and the Cisco Backend perform the following steps:

- Step 1** On the Transport Gateway Application click **Test Connection**; a progress window appears as the Transport Gateway tests the connection to the Internet and Cisco Backend.





Register and Configure the Transport Gateway

- Step 2** After the connection test a response message appears. Read the response message to see if the Transport Gateway successfully established a connection to the Cisco Backend.



- Step 3** Click **OK**.

- Step 4** On the following figure, check the internet connection icon at the bottom right corner of the window; you will see one of the following connection conditions:
- Internet is disconnected icon,  will see this when the Transport Gateway was not successful connecting to the internet.
 - Internet is connected icon,  will see this when the Transport Gateway is successfully connecting to the internet regardless of whether the Transport Gateway was successful connecting to the Cisco Backend.







Note


Moving and holding your mouse over the Internet connection icon will show an associated message that indicates whether the internet is connected or disconnected.

Register the Transport Gateway


After the Transport Gateway package has been installed on the workstation, the proxy settings have been specified, and the connections verified, the user can then register the Transport Gateway. The application, in the following figure, has three locations that indicate the registration status of the Transport Gateway; all show an initial registration status of not registered:

- Registration Status: field. 
- The bottom left corner of the window. 
- An icon at the bottom right  shows an unlocked lock. 

**Note**

You must have an internet connection, and a successful connection to the Cisco backend, in order to perform the registration process. Note also that the following functions  are not enabled until the registration has been successfully completed:

- Configuration
- Reset password
- Mail Box





Step 1 Click **Registration**;  the Register Transport Gateway area appears. 

Step 2 Enter the following data in the Register Transport Gateway fields:

- Your Cisco.com user id and password (required), only when registering the Transport Gateway; after Transport Gateway registration the Transport Gateway ID and Transport Gateway password will be used.
- Transport Gateway name (required).
- Transport Gateway description (optional).


Register and Configure the Transport Gateway

Step 3 Click **Apply**;  a progress window for Registering Transport Gateway appears.




Note

After the registration is completed a Registration window appears to indicate whether the registration failed or was successful.




If the registration is successful, the registration icon changes from an unlocked icon to a locked icon.


The previously inactive functions  have become enabled.

Configure the Transport Gateway Mailbox Settings

The configuration of the Transport Gateway, for the Call Home Mailbox, is done after the Transport Gateway has been registered. You can tell if the Transport Gateway is configured by looking in the status area. If the Transport Gateway is not configured you will see the following information in the status area:

- A message stating “Cisco Transport Gateway is not configured”.
- The configuration icon will have an X over it. 

Perform the following steps to configure the Transport Gateway for the Call Home Mailbox:




Step 1 On the Cisco Transport Gateway Application click **Configuration**; the Configure Transport Gateway for Call Home Mailbox area  appears.



Note

The figure previous shows the default settings for the Configuration function.

Step 2 Specify the settings you want in the designated Transport Gateway configuration fields,  (see the following figure for an example setting):

- Mail Server Type – Options are POP3 or IMAP.
- Mail Server Hostname or IP Address – Specify the Hostname or IP address of the mail server; the mail server needs to be either a POP3 or IMAP format. The Transport Gateway will pick up the Call Home messages from the specified mail server.



Note

It is recommended that you have a dedicated email server that receives only Call Home messages; otherwise the email server may get slowed down processing non-Smart Call Home Messages.

Register and Configure the Transport Gateway

- **Account Name** – The email id used to access the email on the mail server.
- **Password** – The password for the email id for that account.
- **Mail Server Port Number** – If different from the default value (i.e. 110), then change it to the proper value.
- **Send Call Home Messages** – Need to check this check box to allow Call Home messages to be forwarded to the Cisco backend.
- **Mail Store Size (in MB)** – Indicates if the customer needs to be notified when the mail store size reaches the storage size specified in the associated field.
- **Notify Email Address** – Is the email address that receives the notification when the mail storage exceeds the limit specified in the previous field.

Configure Transport Gateway for Call Home Mailbox

Transport Gateway Configuration for Call Home Mailbox

Mail Server Type: POP3

Mail Server Hostname Or IP Address: email.cisco.com

Account Name: skeeler

Password: *****

Mail Server Port Number: 110

Send Call Home Messages:


Mail Store Size (in MB): 1

Notify Email Address: skeeler@cisco.com

Save


184217

- Step 3** Click **Save**; this displays an informational window that indicates the application is connecting to the mail server.



**Note**

After connecting to the mail server the Transport Gateway Application displays a message indicating that the settings have been stored and will be effective starting with the next Call Home message.



Reset the Transport Gateway Password

To reset the Transport Gateway password that is used to forward Call Home messages to the Cisco Backend perform the following step:

- Step 1** On the Transport Gateway Application click **Reset Password**; the system displays a message indicating that the password was reset successfully and will be automatically used by the Transport Gateway to contact the Cisco Backend.

**Note**

If an error occurs the system logs the date, time and error then displays one of the following error messages:

- A connection could not be established to the Cisco Backend.
- An error occurred on the Cisco Backend and the password could not be reset.

Using the Call Home Mailbox

This section explains how the Transport Gateway maintains the Call Home messages, in the Transport Gateway mail store (mailbox), using the following functions:

- Retrieves and Forward Call Home messages from the mailbox.
- Maintain (send or delete) Call Home messages in the mailbox.
- Notify the Customer When the Mail Store Reaches Limit.

Retrieving and Forwarding Call Home Messages from the Mailbox

The Transport Gateway automatically retrieves Call Home messages from the mailbox and these messages are forwarded either automatically, or can be sent manually, to the Cisco Backend.

The following information describes the process the Transport Gateway uses to retrieve Call Home messages from the mailbox:

- Device(s) send generated Call Home messages to a mailbox to which the Transport Gateway connects to retrieve the Call Home messages.
- The Transport Gateway checks at regular intervals to see if any Call Home messages have arrived in the mailbox.
- New messages are retrieved from the mailbox and stored in the Transport Gateway mail store and deleted from the mailbox.



Note

When the Transport Gateway cannot connect to the mailbox, an error is logged indicating the date/time, event and reason of the error. The Transport Gateway will try to connect to the mailbox every minute, until the connection is back up.

In order for the Transport Gateway to forward the Call Home messages to the Cisco Backend the following pre-requisites need to be accomplished:

- Transport Gateway is registered to the Cisco Backend.
- Transport Gateway has been successfully configured.
- The user checks the **Send Call Home Messages** check box in the configuration window.
- Transport Gateway has a connection to the Cisco Backend.

Transport Gateway will forward Call Home messages to the backend without user interaction if the four previous pre-requisites are met. The Transport Gateway will log the action for each Call Home message in the log.

If for some reason the Transport Gateway is not able to send messages to the backend, the Transport Gateway will continue trying to send them for a specific period of time (3 hours). After this time if they still can not be sent to the backend the Call Home messages will become available in the Transport Gateway mail store; accessible via the Mailbox button in the Transport Gateway. The user can

manually send the messages to the backend or can delete them from the mail store, without sending the messages to the backend. Messages older than 2 days, which are not sent to the backend, will be deleted automatically.

Maintain Call Home Messages in the Mailbox

The Transport Gateway allows you to view the Call Home messages that are available to be sent to the Cisco Backend. This list contains Call Home messages that have been received in the mailbox more than 3 hours ago and less than 2 days ago, and have not yet been successfully sent to the Cisco Backend.

Each Call Home message contains the following information:


- Subject
- Date/time the message was received


The customer can do the following with the Call Home messages:

- Manually send one or more Call Home messages to the Cisco Backend.
- Delete one or more of the messages, to prevent them from being sent to the Cisco backend.

To manually send or delete Call Home messages listed in the mailbox perform the following steps:


Register and Configure the Transport Gateway



Step 1 On the Transport Gateway Application click the **Mailbox** button, the Maintain Call Home Mailbox area appears. 



Note If no Call Home messages are available in the mailbox the system displays the following informational message



Maintain Call Home Message Mailbox

Note: The automated sending of Call Home messages to the Cisco backend is switched ON.

<input type="checkbox"/> Subject	Received
<input type="checkbox"/> System Notification from test-6500 - Test:Test - 200606140500	21/06/2006 14:05:10
<input type="checkbox"/> System Notification from test-6500 - Inventory:Full - 200606140304	21/06/2006 14:03:14
<input type="checkbox"/> System Notification from test-6500 - GOLD Diagnostic:Major - 20060621140302	21/06/2006 14:03:12
<input type="checkbox"/> System Notification from test-6500 - GOLD Diagnostic:Major - 20060621140222	21/06/2006 14:02:32

184222

Step 2 If messages are listed in the mailbox then select the message(s) you want to either send to the Cisco Backend or delete from the mailbox.



Note To select all the files at once, check the check box to the left of the Subject column header. ☐
If you double-click on a specific subject, the system displays the message content.

Step 3 Perform one of the following tasks:

- Click **Send** to send the selected messages to the Cisco Backend.
- Click **Delete** to delete the selected messages from the Transport Gateway mailbox.



Note Messages that have been received by the Transport Gateway for more than 2 days and could not be sent to the Cisco Backend will be automatically deleted by the Transport Gateway.


- For each Call Home message that is deleted, the Transport Gateway logs the action that was executed.

Notify the Customer When the Mail Store Reaches Limit

During configuration the customer has the option to specify a mail store size to indicate at what storage size they wanted to be notified when the Transport Gateway mail store is becoming full.

**Note**


You can see what percentage of the mail store size is being utilized and therefore also available by looking at the icon at the bottom-right corner of the application window that contains the percentage value. The value indicates what percentage of the mail store is currently being used.






The configuration also has a corresponding option to specify a notification email address that the system uses to send an email notification when the mail store is reaching its size limit. When the mail store is reaching its size limit an email notification will be sent to the email address specified in the Notify Email Address field.


View and Zip the Log Status file

To view or zip the Log Status file perform the following steps:



184224


- Step 1** On the Transport Gateway Application click **Log Status**,  the Log Status area appears. 
- Step 2** Select the status log you want to work with, and then click one of the following functions.
- Step 3** Click **View**  to view the status log file; the StatusOfTG file opens with the status information displayed.




```

StatusOfTG - Notepad
File Edit Format View Help
[29 Jan 2007 07:17] - Cisco Transport Gateway service starts!
[29 Jan 2007 07:18] - creating AN connector.....
[29 Jan 2007 07:18] - Configured MailServer Type: pop3
[29 Jan 2007 07:19] - Starting/Restarting Message Age Tracking service
[29 Jan 2007 07:19] - Starting/Restarting Email receiver service
[29 Jan 2007 07:19] - Starting/Restarting Message Dispatcher service
[29 Jan 2007 09:17] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 09:17] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 09:17] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 09:17] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 09:18] - Cisco Transport Gateway service starts!
[29 Jan 2007 09:19] - creating AN connector.....
[29 Jan 2007 09:19] - Configured MailServer Type: pop3
[29 Jan 2007 09:19] - Starting/Restarting Message Age Tracking service
[29 Jan 2007 09:19] - Starting/Restarting Email receiver service
[29 Jan 2007 09:19] - Starting/Restarting Message Dispatcher service
[29 Jan 2007 09:43] - Unable to read the body of the mail, the Message content is not of expected type
[29 Jan 2007 10:29] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 10:30] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 10:30] - The Cisco Transport Gateway service is going to stop.
[29 Jan 2007 10:31] - Cisco Transport Gateway service starts!
[29 Jan 2007 10:32] - creating AN connector.....
[29 Jan 2007 10:32] - Configured MailServer Type: pop3
[29 Jan 2007 10:32] - Starting/Restarting Message Age Tracking service
[29 Jan 2007 10:32] - Starting/Restarting Email receiver service
[29 Jan 2007 10:32] - Starting/Restarting Message Dispatcher service
[29 Jan 2007 13:36] - A problem occured while testing the HTTP connection.
AxisFault
faultCode: {http://xml.apache.org/axis/}HTTP

```

- Step 4** Click **Zip**,  a Save window appears with a filename for the log status zip file.


Register and Configure the Transport Gateway



Note


In the filename, the eight digits after the underscore are the current date (i.e. 29012007 has the day 29, the month 01, and the year 2007). The remaining numbers change as you create successive zip files, so the filename will be unique each time.

- Step 5** You can change the zip filename or location or accept the original filename and location.
- Step 6** When you have the filename and location you want, click **Save**; a progress window appears.



**Note**


When the file is finished being zipped an informational window appears. The informational window lets you know if the zipping of the log file was successful along with the name and location of the zip file.




Step 7 Click **OK**.

Stop the Transport Gateway Service

The Stop Service function closes the Transport Gateway Application window and then stops the Transport Gateway service. To stop the Transport Gateway service, perform the following steps:

Step 1 On the Transport Gateway Application click **Stop Service**;  a Stop Service prompt window opens.



Step 2 If you want to continue stopping the Transport Gateway service click **Yes**, otherwise click **No** to have the Transport Gateway service staying operational.

Close the Transport Gateway Application Window

The Close function closes the Transport Gateway Application window but does not stop the Transport Gateway service. To close the Transport Gateway Application window, perform the following steps:

-
- Step 1** On the Transport Gateway Application click **Close**; the Transport Gateway Application window closes but the Transport Gateway service is still operational.



Note For information on how to start the Transport Gateway Application again, see [Launch the Cisco Transport Gateway Application](#).
