PKI Global Settings Configuration Mode Commands

To configure public key infrastructure (PKI) encryption global settings on a WAAS device, use the **crypto pki global-settings** global configuration command.

> **crypto pki global-settings**

Syntax Description   This command has no arguments or keywords.

Defaults   No default behavior or values.

Command Modes   global configuration

Device Modes   application-accelerator

Usage Guidelines   Use the **crypto pki global-settings** command to configure OCSP and revocation checking. The **crypto pki global-settings** command initiates the global settings configuration mode, as indicated by the following prompt:

```
WAE(config-pki-global-settings)
```

Within global settings configuration mode, you can use the global settings configuration commands to define PKI settings. To return to global configuration mode, enter **exit** at the global settings configuration mode prompt.

Examples   The following example shows how to enter PKI global settings configuration mode:

```
WAE(config)# crypto pki global-settings
WAE(config-pki-global-settings)#
```

Related Commands   (config-pki-global-settings) ocsp

(config-pki-global-settings) revocation-check

(config-pki-global-settings) ocsp

To enter the URL to be used as the global settings for the Online Certificate Status Protocol (OCSP) protocol revocation status checking, use the ocsp PKI global settings configurations mode command.

ocsp url http://*address*

Syntax Description	**url http://***address* The URL to be used for OCSP revocation status checking.

Defaults   No default behavior or values.

Command Modes   PKI global-settings configuration

Device Modes   application-accelerator

central-manager

Examples   The following example shows how to define the OCSP URL as www.myocspurl.com:

```
WAE(config)# crypto pki global-settings
WAE(config-pki-global-settings)# ocsp url http://www.myocspurl.com
```

Related Commands   (config-pki-global-settings) revocation-check

(config-pki-global-settings) revocation-check

To configure the global settings revocation checking method, use the **revocation-check** command.

revocation-check {**ocsp-cert-url** | **ocsp-url**} [**none**]

Syntax Description

ocsp-cert-url	Enables Online Certificate Status Protocol (OCSP) revocation status checking using the CA server URL defined in the CA certificate.
ocsp-url	Enables OCSP revocation status checking using the URL defined for the global OCSP settings.

Defaults   No default behavior or values.

Command Modes   PKI global settings configuration

Device Modes   application-accelerator

central-manager

Examples   The following example shows how to configure the global revocation checking to use the URL defined in the global OCSP settings:

```
WAE(config)# crypto pki global-settings
WAE(config-pki-global-settings)# revocation-check ocsp-url
```

The following example shows how to configure the global revocation checking use the URL defined in the global OCSP settings as the first method, and to use no checking as the second method:

```
WAE(config)# crypto pki global-settings
WAE(config-pki-global-settings)# revocation-check ocsp-url none
```

Related Commands   (config-pki-global-settings) ocsp