

# Implementação MIB do sibilo

## Índice

[Introdução](#)

[Pré-requisitos](#)

[Requisitos](#)

[Componentes Utilizados](#)

[Convenções](#)

[Exemplo de script](#)

[O script](#)

[Informações Relacionadas](#)

## [Introdução](#)

O grupo do sibilo é parte de Cisco MIB proprietário sob o ramo do Gerenciamento de Cisco (.1.3.6.1.4.1.9.9.16.). O grupo do sibilo pode ser usado para estabelecer, executar, e recuperar a atividade do Internet Control Message Protocol (ICMP) entre dispositivos remotos de uma estação de gerenciamento.

## [Pré-requisitos](#)

### [Requisitos](#)

Não existem requisitos específicos para este documento.

### [Componentes Utilizados](#)

Este documento não se restringe a versões de software e hardware específicas.

As informações neste documento foram criadas a partir de dispositivos em um ambiente de laboratório específico. Todos os dispositivos utilizados neste documento foram iniciados com uma configuração (padrão) inicial. Se a sua rede estiver ativa, certifique-se de que entende o impacto potencial de qualquer comando.

### [Convenções](#)

Para obter mais informações sobre convenções de documento, consulte as [Convenções de dicas técnicas Cisco](#).

## [Exemplo de script](#)

Você pode usar o exemplo de script para iniciar esta sequência no HP OpenView ou no Netview. Você pode igualmente incorporar estes comandos como **snmpsets** e **snmpgets** usando os GUI das plataformas de gerenciamento de rede. Use um dos seguintes métodos para alcançar o GUI:

- Da barra de menus, selecione **ferramentas**, então **Navegador MIB: SNMP**.
- No tipo **xnmbrowser** da linha de comando.

## O script

```
Management_Station-----Router_Source-----Router_Dest
echo "##### Create the instance #####"
```

```
##### We've chosen 333 at random. 333 will be the row instance to use for this particular
##### ping experiment. After the ping, the row will be deleted.
##### This keeps the table clean. Router_Source is the dns name of the device we are
##### working with, and public is its RW community string. The values for
##### ciscoPingEntryStatus status are as follows (see Ping MIB): ##### 1 - active ##### 2 -
notInService ##### 3 - notReady ##### 4 - createAndGo ##### 5 - createAndWait ##### 6 -
destroy ##### We will clear out any previous entries by setting ciscoPingEntryStatus = 6
(destroy) snmpset -c public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.16.333 integer 6 ##### We
start building the row by setting ciscoPingEntryStatus = 5 (createAndWait) echo snmpset -c
public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.16.333 integer 5 echo echo "##### Now let's set
the characteristics of the ping #####" ##### Only the first three sets below are REQUIRED.
The rest have default ##### values. #Set ciscoPingEntryOwner = any_name snmpset -c public
Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.15.333 octetstring any_name #Set ciscoPingProtocol = 1 =
ip (see CISCO-TC-V1SMI.my CiscoNetworkProtocol) snmpset -c public Router_Source
.1.3.6.1.4.1.9.9.16.1.1.1.2.333 integer 1 #Set ciscoPingAddress = #.#.#.--take Remote_Dest's ip
& convert each octet to hex snmpset -c public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.3.333
octetstringhex "AB 44 76 67" #Set the packet count to 20 (ciscoPingPacketCount) snmpset -c
public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.4.333 integer 20 #Set the packetsize to 100
(ciscoPingPacketSize) snmpset -c public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.5.333 integer
100 echo echo "##### Now let's verify that the ping is ready to go and launch it #####" #Get
ciscoPingEntryStatus and make sure it is now equal to 2. This means # notInService which
indicates that we're ready to go. snmpget -c public Router_Source
.1.3.6.1.4.1.9.9.16.1.1.1.16.333 # Set ciscoPingEntryStatus = 1 to tell it to activate. snmpset
-c public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.16.333 integer 1 echo echo "##### Let's look
at the results. #####" snmpwalk -c public Router_Source .1.3.6.1.4.1.9.9.16.1.1.1 echo echo
"##### Now that we've gotten the results, let's destroy the row #####" snmpset -c public
Router_Source .1.3.6.1.4.1.9.9.16.1.1.1.16.333 integer 6
```

## Informações Relacionadas

- [Suporte Técnico - Cisco Systems](#)