

Перезагрузите пароль при загрузке для гостя Cisco Jabber

Содержание

[Введение](#)

[Предварительные условия](#)

[Требования](#)

[Используемые компоненты](#)

[Проблема](#)

[Решение](#)

Введение

Этот документ описывает, как перезагрузить пароль при загрузке для Гостя Cisco Jabber.

Предварительные условия

Требования

Cisco рекомендует ознакомиться с CentOS 6.

Используемые компоненты

Сведения в этом документе основываются на Госте Cisco Jabber.

Сведения, представленные в этом документе, были получены от устройств, работающих в специальной лабораторной среде. Все устройства, описанные в этом документе, были запущены с чистой (стандартной) конфигурацией. В рабочей сети необходимо изучить потенциальное воздействие всех команд до их использования.

Проблема

О пароле при загрузке для Гостевого сервера Cisco Jabber забывают или теряют.


Решение

Чтобы устранить эту проблему, выполните следующие действия:

1. Откройте сеанс консоли для Гостевого сервера Jabber и перезагрузки.
2. Нажмите любую клавишу на клавиатуре для прерывания процесса загрузки.



3. Нажмите **e** для редактирования.



4. Выберите **ядро** от записей и нажмите **e** для редактирования.

```
GNU GRUB version 0.97 (632K lower / 3140608K upper memory)
```

```
root (hd0,0)
```

```
kernel /vmlinuz-2.6.32-220.el6.x86_64 ro root=/dev/mapper/vg_kitllcbu→  
initrd /initramfs-2.6.32-220.el6.x86_64.img
```

Use the ↑ and ↓ keys to select which entry is highlighted. Press 'b' to boot, 'e' to edit the selected command in the boot sequence, 'c' for a command-line, 'o' to open a new line after ('O' for before) the selected line, 'd' to remove the selected line, or escape to go back to the main menu.

5. Добавьте слово, **одиночное** до конца линии, и нажмите Enter.

```
[ Minimal BASH-like line editing is supported. For the first word, TAB  
lists possible command completions. Anywhere else TAB lists the possible  
completions of a device/filename. ESC at any time cancels. ENTER  
at any time accepts your changes.]
```

```
<ABEL=79d3d2d4 single█
```

6. Нажмите **b** для начальной загрузки.

```
GNU GRUB version 0.97 (632K lower / 3140608K upper memory)
```

```
root (hd0,0)
```

```
kernel /vmlinuz-2.6.32-220.el6.x86_64 ro root=/dev/mapper/vg_kitllcbu→  
initrd /initramfs-2.6.32-220.el6.x86_64.img
```

Use the ↑ and ↓ keys to select which entry is highlighted. Press 'b' to boot, 'e' to edit the selected command in the boot sequence, 'c' for a command-line, 'o' to open a new line after ('O' for before) the selected line, 'd' to remove the selected line, or escape to go back to the main menu.

Гостевой сервер Jabber загружается в Однопользовательский

режим.

```
eth0: registered as PCnet/PCI II 79C970A
pcnet32: 1 cards_found.
parport_pc 00:08: reported by Plug and Play ACPI
parport0: PC-style at 0x378, irq 7 [PCSP,TRISTATE]
ppdev: user-space parallel port driver
[ OK ]
Setting hostname localhost.localdomain: [ OK ]
Checking filesystems
[ OK ]
Remounting root filesystem in read-write mode: [ OK ]
mount: according to mtab, /dev/sda1 is already mounted on /
Mounting local filesystems: [ OK ]
Enabling /etc/fstab swaps: [ OK ]
Welcome to CentOS
Starting udev: [ OK ]
Setting hostname localhost.localdomain: [ OK ]
Checking filesystems
[ OK ]
Remounting root filesystem in read-write mode: [ OK ]
mount: according to mtab, /dev/sda1 is already mounted on /
Mounting local filesystems: [ OK ]
Enabling /etc/fstab swaps: [ OK ]
[root@localhost ~]# _
```

- 7. Введите **root passwd** для изменения пароля для 'корневого' пользователя. Это побуждает вас для нового пароля.

```
[root@localhost ~]# passwd root
Changing password for user root.
New password: _
```

- 8. Как только пароль при загрузке был изменен, перезагрузите сервер, и у вас теперь есть новый пароль при загрузке.