



CHAPTER 21

Cisco Unified Personal Communicator Settings

Use Cisco Unified Personal Communicator settings to configure the settings that apply to all Cisco Unified Personal Communicator users.

Configuring Cisco Unified Personal Communicator Settings

Follow this procedure to configure the Cisco Unified Personal Communicator settings.

Procedure

- Step 1** Choose **Application > Cisco Unified Personal Communicator > Settings**.
The Cisco Unified Personal Communicator Settings window displays.
- Step 2** Enter the appropriate configuration settings as described in [Table 21-1](#).
- Step 3** From the Directory Server Type drop-down list, choose the appropriate directory server type.
- Step 4** Enter the appropriate LDAP attribute name for your environment that maps to the given Cisco Unified Personal Communicator attribute name. For a list of Cisco Unified Personal Communicator attribute names and the corresponding default LDAP name, see [Table 21-2](#)



Note To reset the attribute mapping field to the defaults for the chosen directory server type, click **Restore Defaults**.

- Step 5** To save the data, click the **Save** icon that displays in the tool bar in the upper, left corner of the window (or click the **Save button** that displays at the bottom of the window).
-

Table 21-1 Cisco Unified Personal Communicator Configuration Settings

Field	Description
Primary TFTP Server	This parameter specifies the primary TFTP server address, either as a fully qualified domain name or as an IP address. Maximum characters: 128
Backup TFTP Server	This parameter specifies the backup TFTP server address, either as a fully qualified domain name or as an IP address. Maximum characters: 128
Directory Server Type	This parameter specifies the appropriate directory server type: <ul style="list-style-type: none"> • Microsoft Active Directory • Netscape or Sun ONE LDAP server <p>Note When you select the appropriate directory server type, Cisco Unified Presence Administration displays the appropriate parameter mapping fields.</p>

Table 21-2 Default LDAP Attribute Mapping

Cisco Unified Personal Communicator User Fields	Default LDAP Mapping Names for Microsoft Active Directory	Default LDAP Mapping Names for Netscape or SUN ONE
UserID	sAMAccountName	uid
FirstName	givenName	givenName
LastName	sn	sn
MiddleName	middleName	initials
Nickname	Nickname	Nickname
Photo		jpegPhoto
Title	title	title
DisplayName	displayName	displayName
NamePrefix	namePrefix	namePrefix
NameSuffix		
Gender	gender	gender
BusinessEMail	mail	mail
BusinessPhoneNumber	telephoneNumber	telephoneNumber
BusinessVoiceMail		voicemail
BusinessMobilePhone	mobile	mobile
BusinessPager	pager	pager
BusinessFax	facsimileTelephoneNumber	facsimileTelephoneNumber
BusinessOtherPhone	otherTelephone	
HomeEMail		
HomeMobilePhone		

Table 21-2 *Default LDAP Attribute Mapping (continued)*

Cisco Unified Personal Communicator User Fields	Default LDAP Mapping Names for Microsoft Active Directory	Default LDAP Mapping Names for Netscape or SUN ONE
HomeFax	pager	
URL	url	labeledURI

