



## **Firepower Management Center REST API Quick Start Guide, Version 6.4.0**

**First Published:** 2019-04-24

**Last Modified:** 2019-09-20

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

All printed copies and duplicate soft copies of this document are considered uncontrolled. See the current online version for the latest version.

Cisco has more than 200 offices worldwide. Addresses and phone numbers are listed on the Cisco website at [www.cisco.com/go/offices](http://www.cisco.com/go/offices).

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: [www.cisco.com go trademarks](http://www.cisco.com/go/trademarks). Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1721R)

© 2019 Cisco Systems, Inc. All rights reserved.



## CONTENTS

---

<b>CHAPTER 1</b>	<b>About the Firepower Management Center REST API</b>	<b>1</b>
	About the Firepower Management Center REST API	1
	Enabling the REST API	1
	Best Practices	2
	Additional Resources	2

---

<b>CHAPTER 2</b>	<b>About the API Explorer</b>	<b>3</b>
	About the API Explorer	3
	Authentication to the API Explorer	3
	Logging into API Explorer	4
	Setting the Domain	4
	Accessing the Legacy API Explorer	4
	Obtaining Sample Code with CodeGen	5
	Downloading the Open API Spec	5
	Generating Sample Code with the CodeGen Utility	6
	Viewing API Parameters	6

---

<b>CHAPTER 3</b>	<b>Connecting with a Client</b>	<b>9</b>
	Authentication from a REST API Client	9
	Requesting an Authentication Token	10
	Refreshing an Authentication Token	11

---

<b>CHAPTER 4</b>	<b>Objects in the REST API</b>	<b>13</b>
	Request Structure	13
	Bulk Rule Posting	15
	Response Structure	16

- Rate Limiting 18
- Payload Limiting 18
- Object Overrides 18
- Audit Services 19
  - GET auditrecords 19
- Deployment Services 19
  - GET deployabledevices 19
  - POST deploymentrequests 20
- Device Group Services 20
  - DELETE devicegrouprecords 20
  - PUT devicegrouprecords 20
  - POST devicegrouprecords 20
  - GET devicegrouprecords 20
- Device Clusters 21
  - GET ftddevicecluster 21
- Device HA Pair Services 21
  - DELETE ftddevicehapair 21
  - PUT ftddevicehapair 21
  - POST ftddevicehapairs 22
  - GET ftddevicehapairs 22
  - DELETE failoverinterfacemacaddressconfigs 22
  - GET failoverinterfacemacaddressconfigs 23
  - POST failoverinterfacemacaddressconfigs 23
  - PUT failoverinterfacemacaddressconfigs 23
  - GET monitoredinterfaces 23
  - PUT monitoredinterfaces 24
- Device Services 24
  - POST copyconfigrequests 24
  - DELETE devicerecords 24
  - PUT devicerecords 24
  - POST devicerecords 25
  - GET devicerecords 25
  - PUT fpphysicalinterfaces 25
  - GET fpphysicalinterfaces 25

DELETE fplogicalinterfaces	25
PUT fplogicalinterfaces	26
POST fplogicalinterfaces	26
GET fplogicalinterfaces	26
DELETE inlinesets	26
PUT inlinesets	27
POST inlinesets	27
GET inlinesets	27
GET staticroutes	27
DELETE ipv4staticroutes	27
PUT ipv4staticroutes	28
POST ipv4staticroutes	28
GET ipv4staticroutes	28
DELETE ipv6staticroutes	28
PUT ipv6staticroutes	29
POST ipv6staticroutes	29
GET ipv6staticroutes	29
DELETE virtualswitches	29
PUT virtualswitches	29
POST virtualswitches	30
GET virtualswitches	30
PUT fpphysicalinterfaces	30
GET fpphysicalinterfaces	30
PUT physicalinterfaces	31
GET physicalinterfaces	31
GET bridgegroupinterfaces	31
POST bridgegroupinterfaces	32
PUT bridgegroupinterfaces	32
DELETE bridgegroupinterfaces	32
GET redundantinterfaces	32
POST redundantinterfaces	32
PUT redundantinterfaces	33
DELETE redundantinterfaces	33
GET etherchannelinterfaces	33

POST etherchannelinterfaces	33
PUT etherchannelinterfaces	34
DELETE etherchannelinterfaces	34
GET subinterfaces	34
POST subinterfaces	34
PUT subinterfaces	34
DELETE subinterfaces	35
GET fpinterfacestatistics	35
POST interfaceevents	35
GET interfaceevents	35
Intelligence Services	35
POST collections	35
POST discoveryinfo	36
GET element	36
DELETE incident	36
PUT incident	36
GET incident	36
PUT indicator	37
GET indicator	37
PUT observable	37
GET observable	37
PUT settings	38
GET settings	38
DELETE source	38
PUT source	38
POST source	38
GET source	38
Integration Services	39
PUT cloudeventsconfigs	39
GET cloudeventsconfigs	39
DELETE externallookups	39
PUT externallookups	39
POST externallookups	40
GET externallookups	40

DELETE packetanalyzerdevices	40
PUT packetanalyzerdevices	40
POST packetanalyzerdevices	40
GET packetanalyzerdevices	41
Object Services	41
GET anyprotocolportobjects	41
GET applicationcategories	41
GET applicationfilters	41
GET applicationproductivities	42
GET applicationrisks	42
GET applications	42
GET applicationtags	42
GET applicationtypes	43
GET certenrollments	43
GET continents	43
GET countries	43
DELETE dnsservergroups	44
PUT dnsservergroups	44
POST dnsservergroups	44
GET dnsservergroups	44
GET endpointdevicetypes	44
GET extendedaccesslist	45
DELETE fqdns	45
PUT fqdns	45
POST fqdns	45
GET fqdns	45
GET geolocation	46
DELETE hosts	46
PUT hosts	46
POST hosts	47
GET hosts	47
DELETE icmpv4objects	47
PUT icmpv4objects	47
POST icmpv4objects	48

GET icmpv4objects	48
DELETE icmpv6objects	48
PUT icmpv6objects	48
POST icmpv6objects	49
GET icmpv6objects	49
DELETE ikev1ipsecproposals	49
PUT ikev1ipsecproposals	49
POST ikev1ipsecproposals	50
GET ikev1ipsecproposals	50
DELETE ikev1policies	50
PUT ikev1policies	50
POST ikev1policies	50
GET ikev1policies	51
DELETE ikev2ipsecproposals	51
PUT ikev2ipsecproposals	51
POST ikev2ipsecproposals	51
GET ikev2ipsecproposals	51
DELETE ikev2policies	52
PUT ikev2policies	52
POST ikev2policies	52
GET ikev2policies	52
DELETE interfacegroups	52
PUT interfacegroups	53
POST interfacegroups	53
GET interfacegroups	53
GET interfaceobjects	53
GET isecuritygroupstags	54
GET keychain	54
DELETE keychain	54
PUT keychain	55
POST keychain	55
GET networkaddresses	55
DELETE networkgroups	56
PUT networkgroups	56

POST networkgroups	56
GET networkgroups	56
DELETE networks	57
PUT networks	57
POST networks	57
GET networks	57
DELETE portobjectgroups	58
PUT portobjectgroups	58
POST portobjectgroups	58
GET portobjectgroups	58
GET ports	59
DELETE protocolportobjects	59
PUT protocolportobjects	59
POST protocolportobjects	59
GET protocolportobjects	60
DELETE ranges	60
PUT ranges	60
POST ranges	60
GET ranges	61
GET realms	61
GET realmusergroups	61
GET realmusers	62
GET securitygrouptags	62
DELETE securityzones	62
PUT securityzones	62
POST securityzones	63
GET securityzones	63
GET siurlfeeds	63
GET siurllists	63
DELETE slamonitors	63
PUT slamonitors	64
POST slamonitors	64
GET slamonitors	64
GET tunneltags	64

GET urlcategories	64
DELETE urlgroups	65
PUT urlgroups	65
POST urlgroups	65
GET urlgroups	65
DELETE urls	66
PUT urls	66
POST urls	66
GET urls	66
GET variablesets	67
DELETE vlangrouptags	67
PUT vlangrouptags	67
POST vlangrouptags	67
GET vlangrouptags	68
DELETE vlantags	68
PUT vlantags	68
POST vlantags	68
GET vlantags	69
Policy Services	69
DELETE accesspolicies	69
PUT accesspolicies	69
POST accesspolicies	69
GET accesspolicies	70
DELETE accessrules	70
PUT accessrules	70
POST accessrules	70
GET accessrules	70
PUT defaultactions	71
GET defaultactions	71
GET loggingsettings	71
PUT loggingsettings	72
GET filepolicies	72
DELETE ftdnatpolicies	72
PUT ftdnatpolicies	72

POST ftdnatpolicies	72
GET ftdnatpolicies	73
DELETE ftds2svpns	73
PUT ftds2svpns	73
POST ftds2svpns	73
GET ftds2svpns	73
PUT advancedsettings	74
GET advancedsettings	74
DELETE endpoints	74
PUT endpoints	74
POST endpoints	74
GET endpoints	75
PUT ikesettings	75
GET ikesettings	75
PUT ipsecsettings	75
GET ipsecsettings	76
DELETE autonatrules	76
PUT autonatrules	76
POST autonatrules	76
GET autonatrules	76
DELETE manualnatrules	77
PUT manualnatrules	77
POST manualnatrules	77
GET manualnatrules	77
GET natrules	78
GET intrusionpolicies	78
GET prefilterpolicies	78
DELETE hitcounts	78
PUT hitcounts	79
GET hitcounts	79
GET snmpalerts	79
GET syslogalerts	80
Policy Assignment Services	80
PUT policyassignments	80

- POST policyassignments 80
- GET policyassignments 80
- Status Services 81
  - GET taskstatuses 81
- System Information 81
  - GET serverversion 81
- Update Packages 81
  - DELETE upgradepackages 81
  - GET upgradepackages 81
  - GET listapplicabledevices 82
  - POST upgradepackage 82
  - GET upgradepackages: Monitor 82



## CHAPTER 1

# About the Firepower Management Center REST API

---

The Firepower Management Center REST API provides a lightweight API to manage a Firepower Management Center.

- [About the Firepower Management Center REST API, on page 1](#)
- [Enabling the REST API, on page 1](#)
- [Best Practices, on page 2](#)
- [Additional Resources, on page 2](#)

## About the Firepower Management Center REST API

With the release of Cisco's Firepower Management Center REST API, you now have light-weight, easy-to-use option for managing Firepower Threat Defense and legacy Firepower devices through a Firepower Management Center.

The REST API is an application programming interface (API), based on "RESTful" principles, which you can quickly enable on any Firepower Management Center running version 6.1 or higher, and use with a REST client.

After installing a REST client, you can contact the specific Firepower Management Center's REST agent and use standard HTTP methods to access current configuration information, and issue additional configuration parameters.

## Enabling the REST API

In Firepower Management Center, the REST API is enabled by default. However, if you are intending to use the REST API, you should confirm that it is enabled.



---

**Note** If you are using UCAPL mode, check that the REST API is not enabled.

---

---

**Step 1** Navigate to System>Configuration>REST API Preferences>Enable REST API

**Step 2** Check the "Enable REST API" checkbox.

**Step 3** Click "Save". A "Save Successful" dialog will display when the REST API is enabled.

---

## Best Practices

Cisco recommends the following best practices for optimal results with the REST API:

- Keep UI users and script users separate. Especially do not use the admin account as an API user.
- Do not give script users more privilege than needed.
- Always validate the content coming from the server.
- Validate/sanitize JSON content, as it may include embedded executable code.
- If you are using CC or UCAPL mode you should disable REST API access to the Firepower Management Center and managed devices.

## Additional Resources

Additional resources for the Firepower Management Center REST API can be found on Cisco DevNet at <https://developer.cisco.com/firepower/>.



## CHAPTER 2

# About the API Explorer

---

- [About the API Explorer, on page 3](#)
- [Authentication to the API Explorer, on page 3](#)
- [Accessing the Legacy API Explorer, on page 4](#)
- [Obtaining Sample Code with CodeGen, on page 5](#)
- [Viewing API Parameters, on page 6](#)

## About the API Explorer

The API Explorer provides a limited interface for the REST API as well as giving a view of the abilities of the REST API.

The API Explorer resides on the Firepower Management Center, and can be accessed via the Firepower Management Center at:

```
https://<management_center_IP_or_name>:<https_port>/api/api-explorer
```

Version 6.4 uses a new API Explorer, based on the OpenAPI Specification (OAS). You can still access the legacy API Explorer if you prefer.

As part of the OAS, you now use CodeGen to generate sample code.

This explorer provides the list of APIs available on the Firepower Management Center, and their details.

## Authentication to the API Explorer

The REST API relies on the same authentication as the Firepower Management Center. Each function in the REST API maps to permissions in the Firepower Management Center.

You can log into the API Explorer using any account on the Firepower Management Center, but you will only be able to perform the functions for which the account has permissions. For more information on setting permissions for user roles, see the *Firepower Management Center Configuration Guide*.

The first time you connect to the API Explorer you may receive an error that the connection is not secure due to an invalid certificate. You will need to add an exception in your browser to use the certificate and accept the connection.

## Logging into API Explorer

The REST API uses the same authentication and permission model as the Firepower Management Center. See the *Firepower Management Center Configuration Guide* for more information.

### Before you begin

Make sure you have an account on your Firepower Management Center with the required permissions to perform the tasks you want to perform using the REST API.

---

**Step 1** Navigate to the following URL: `https://<management_center_IP_or_name>:<https_port>/api/api-explorer`

If you experience an extended load time for the logon screen when using a Firefox browser, enter **about:support** in the search bar and click the **Refresh Firefox** option, then view the Firepower Management Center interface with self-signed certificates in the same Firefox browser. For more information, see <https://support.mozilla.org/en-US/kb/refresh-firefox-reset-add-ons-and-settings>.

**Step 2** Log in with your username and password and click "Sign In"

---

### What to do next

Locate the desired resource and request.

## Setting the Domain

The REST API can perform functions globally, in the default domain, or in specific domains.

### Before you begin

You must have a configured Firepower Management Center, an account with permissions to access the REST API in one or more domains configured on your FMC.

---

In the upper right, drop down the `Domains` menu and select the desired domain.

---

### What to do next

Locate the desired resource and request type.

## Accessing the Legacy API Explorer

The API Explorer has changed for 6.4.0. While the newer API Explorer retains nearly all of the previous functionality, some users may prefer the older interface.

### Before you begin

Make sure you have an account on your Firepower Management Center with the required permissions to perform the tasks you want to perform using the REST API.

Log in to the API Explorer at [https://<management\\_center\\_IP\\_or\\_name>:<https\\_port>/api/api-explorer](https://<management_center_IP_or_name>:<https_port>/api/api-explorer).

---

In the upper right-hand corner click on `Legacy Explorer`.

---

### What to do next

Use the Legacy API Explorer as you would normally.

## Obtaining Sample Code with CodeGen

You can use the CodeGen utility on the Open API Spec to generate sample code in a number of different languages. This utility is an open-source tool you can download online. The resultant code is meant primarily as an educational and bootstrapping tool.

The CodeGen utility creates sample code for the entire Open API Spec. As such, it generates sample code for every allowed method and endpoint in the REST API. The sample code can be in a variety of languages, including HTML, Perl, Python, and Java.

For complete documentation of the CodeGen utility go to <https://repo1.maven.org/maven2/io/swagger/swagger-codegen-cli/>

## Downloading the Open API Spec

The Open API Spec is a standardized specification of a REST API. The Open API Spec for the Firepower Management Center REST API contains details about the endpoints, fields, parameters, and requirements of the API. You can use the API Spec to generate sample code as well as find specific information about API functionality.

The Open API Spec is a JSON file. It can be read by most text editors.

### Before you begin

Have an account on the Firepower Management Center which is able to access the API Explorer.

Make sure that your browser is able to download from sites with self-signed certificates.

- 
- Step 1** Navigate to the following URL: [https://<management\\_center\\_IP\\_or\\_name>:<https\\_port>/api/api-explorer](https://<management_center_IP_or_name>:<https_port>/api/api-explorer)
- Step 2** Click on `Download Spec` in the upper right corner. Depending on your browser configuration, you will either be given a prompt to save the file, or be shown the file directly.
- Step 3** Save the file. Be sure to note the destination and filename.
-

**What to do next**

Run the CodeGen utility on the downloaded file.

## Generating Sample Code with the CodeGen Utility

The Swagger CodeGen utility allows you to generate sample code from an Open API Spec. This sample code can be in a variety of languages including Java, HTML, Python, and Perl.

**Before you begin**

Download the Swagger CodeGen Utility. It can be found at <https://repo1.maven.org/maven2/io/swagger/swagger-codegen-cli/>

Have a Java Runtime Environment installed on your computer

Download the Firepower Management Center REST API Open API Spec

Set environment variables to allow you to run the CodeGen utility

---

From the command line, run the command `java -jar ./swagger-codegen-cli-<VERSION>.jar generate -o <OUTPUT_PATH> -l <LANGUAGE> -i <OPEN_API_SPEC_FILE>`

**Example:**

```
java -jar ./swagger-codegen-cli-2.3.1.jar generate -o C:\work\code\api_schema\html -l html -i fmc_swagger.json
```

<VERSION> is the specific version of the CodeGen utility you are using. It must match the filename of the CodeGen .jar file.

<OUTPUT\_PATH> is the path to which you want to output the generated code.

<LANGUAGE> is the language which you want CodeGen to generate. Suggested options include `html`, `java`, `perl`, and `python`. Other options are possible, check the CodeGen documentation for the complete list of choices.

<OPEN\_API\_SPEC\_FILE> is the Open API Spec file which you downloaded. This is the source from which CodeGen is generating example code. Without it, CodeGen cannot provide output.

---

**What to do next**

Find the generated code in the output path and use as desired. Generated code should be considered an example, and may not perform as desired unless modified to meet your needs.

## Viewing API Parameters

Each resource has a set of parameters and fields associated with it. You can view the parameters and fields by performing any of the supported operations for that resource within API Explorer.

**Before you begin**

You must have a configured Firepower Management Center and an account on that center with the permissions required to use the desired REST API functions.

---

**Step 1** Select the desired resource.

**Step 2** Select one of the supported operations for that resource.

---





## CHAPTER 3

# Connecting with a Client

You can access the REST API using any REST API client. Typically REST API clients are available as browser plugins, but any REST API client is allowed.



**Note** If connecting to the REST API for the first time, you will receive a certificate warning. You need to accept the certificate in order to use the REST API.

- [Authentication from a REST API Client, on page 9](#)

## Authentication from a REST API Client


**Cisco recommends that you use different accounts for interfacing with the API and the Firepower User Interface.** Credentials cannot be used for both interfaces simultaneously, and will be logged out without warning if used for both.

The first time you connect to the REST API you may receive an error that the connection is not secure due to an invalid certificate. Add an exception in your browser to use the certificate and accept the connection.

With Token Based Authentication you obtain a token by providing your username and password. You use this token to access an HTTP service for a limited time period without the need for the username and password with every request. In other words, to eliminate the need for authenticating with your username and password with each request, you replace user credentials with a uniquely generated access token, which you use for accessing resources for up to 30 minutes and can refresh up to three times.

The diagram below illustrates the concept of token-based authentication:

**Token-Based Authentication**



## Requesting an Authentication Token

The Token Generation Utility provides an authentication token which can be used in your REST API client.

### Before you begin

You must have a configured Firepower Management Center and an account on that center with credentials to use the REST API. You must also have a REST API Client which can perform basic authentication.

- 
- Step 1** Open your REST API Client.
- Step 2** Set the client to make a POST command to the following URL:  
`https://<management_center_IP_or_name>/api/fmc_platform/v1/auth/generatetoken.`
- Step 3** Include the username and password as a basic authentication header. The POST body should be blank.
- 

#### What to do next

Add the header `X-auth-access-token:<authentication token value>` in requests to the API.

Add the headers `X-auth-access-token:<authentication token value>` and `X-auth-refresh-token:<refresh token value>` in requests to refresh the token as described in [Authentication from a REST API Client, on page 9](#)

Use the `Domain_UUID` from the authentication token in all REST requests to the server.

## Refreshing an Authentication Token

Firepower Management Center REST API authentication tokens are valid for 30 minutes, and can be refreshed up to three times.

#### Before you begin

Obtain valid authentication and refresh tokens from the Firepower Management Center REST API. Ensure these tokens have been refreshed less than three times.

- 
- Step 1** Open your REST API Client.
- Step 2** Set the client to make a POST command to the following URL:  
`https://<management_center_IP_or_name>/api/fmc_platform/v1/auth/refresh token` with the headers `X-auth-access-token:<authentication token value>` and `X-auth-refresh-token:<refresh token value>`.
- 

#### What to do next

Add the header `X-auth-access-token:<new authentication token value>` in requests to the API.

Add the header `X-auth-refresh-token:<new refresh token value>` in requests to refresh the token.





## CHAPTER 4

# Objects in the REST API

---

- [Request Structure](#), on page 13
- [Bulk Rule Posting](#), on page 15
- [Response Structure](#), on page 16
- [Rate Limiting](#), on page 18
- [Payload Limiting](#), on page 18
- [Object Overrides](#), on page 18
- [Audit Services](#), on page 19
- [Deployment Services](#), on page 19
- [Device Group Services](#), on page 20
- [Device Clusters](#), on page 21
- [Device HA Pair Services](#), on page 21
- [Device Services](#), on page 24
- [Intelligence Services](#), on page 35
- [Integration Services](#), on page 39
- [Object Services](#), on page 41
- [Policy Services](#), on page 69
- [Policy Assignment Services](#), on page 80
- [Status Services](#), on page 81
- [System Information](#), on page 81
- [Update Packages](#), on page 81

## Request Structure

Request Structure:

Requests are sent to the Firepower Management Center as HTTPS requests with the Uniform Resource Identifier (URI) of the form described below:

```
https://<management_center_IP_or_name>:<https_port>/<object_URL>/object_UUIDoptions
```

Where:

- `<management_center_IP_or_name>`  
is the IP address or Fully Qualified Domain Name of the Firepower Management Center
- `<https_port>`

is the port number used by the Firepower Management Center for HTTPS connections. This port is always 443.

- `<object_URL>`

is the specific URL for the desired resource. These URLs are unique for each resource and are given below.

- *options*

are the options given with the request. Options can be used to modify the output and filter results.

- *{UUID}*

Many URLs contain one or more UUIDs which must be specified. Most URIs include the domain UUID, which can be found in the Authentication Token. When deleting or modifying an object, or requesting information about a specific object, the URI will end with the object UUID.

Available request methods are:

- GET

– Retrieves data from the specified object. GET is a read-only operation.

- PUT

– Adds the supplied information to the specified object; returns a 404 Resource Not Found error if the object does not exist.




---

**Note** Currently PUT may be used to create a new object, but this ability may be removed in later releases. Use POST to create new objects and PUT to modify existing objects.

---

- POST

– Creates the object with the supplied information. POST operations should be followed with a payload consisting of the JSON object to be created, enclosed in braces:

```
{object}
```




---

**Note** The maximum number of rules you can use depends on memory of the device. There is no set limit, because complex rules use more memory. For rule performance and optimization guidelines, see the Firepower Management Center Configuration Guide.

---

- DELETE

– Deletes the specified object.

- PATCH

– **Not supported.**

The API supports query parameters for almost all requests. For GET requests, the following query parameters can be used to control the number of returned objects and the pagination:

- `expanded`
  - This is a True/False value which indicates whether you get a full listing of an item in a list or only a reference. Some fields will only show if this flag is set to true.
- `offset`
  - Indicates the position in the list where you want to start.
- `limit`
  - Indicates the number of items you want to retrieve in a page.

The API supports filtering on the basis of query parameters passed with a request. Filtering can be done based on specific attributes in a model. The parameters available for filtering vary by object, and are listed with the request below.

## Bulk Rule Posting

Multiple access control rules can be added with a POST command using the bulk insert feature. This feature allows as many as 1,000 rules to be added at once.

This feature is only available for access rules.

The URL for this feature is:

```
https://{fmc_ip_or_name}:{https_port}/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{policy_UUID}/accessrules?bulk=true
```

The option:

```
?bulk=true
```

indicates that that multiple rules will be used in the payload of this request.

All objects in the payload of the bulk POST request must be of the same type. You cannot mix different objects in the same bulk request.

Unlike a normal POST operation, the bulk POST requires a list of JSON objects. This list may have as many as 1,000 objects or as few as one. The individual JSON objects must be enclosed in braces. Each object must be separated by commas, and the entire list is enclosed in brackets:

```
[{object}]
[{object1},{object2},{object3},{object4},{object5} ...]
```

The following query parameters are supported in bulk POST requests:

- `bulk=true`
  - This parameter specifies that the bulk POST feature is being used in the query. This parameter is **required** for bulk rule posting.
- `section=mandatory/default`
  - This parameter specifies the section into which the rules will be added. If this parameter is not used the section will be the default section. Only `mandatory` and `default` are allowed values. If a section is specified it must exist or the request will fail. If a section is specified, a category cannot be specified.
- `category=<Name of the category>`
  - This parameter specifies the category into which the rules will be added. If a category is specified it must exist or the request will fail. If a category is specified, a section cannot be specified.

- `insertAfter=<Index of rule>`

This parameter specifies that the rules will be inserted after the specified rule index. If no section or category is specified, the rules will be added to the section or category after the insertion point.

- `insertBefore=<Index of rule>`

This parameter specifies that the rules will be inserted before the specified rule index. If no section or category is specified, the rules will be added to the section or category before the insertion point. `insertBefore` takes precedence over `insertAfter` - if both are specified, the `insertBefore` parameter will apply.

When a rule or group of rules are inserted at an index which is part of either a section or a category, the category or section parameter can be used along with index to specify the insertion location of the rule(s). If an index is given along with a section or category, but the index is not in that section or category, you will receive an error.

If no index is specified, rules will be inserted after the end of the access policy. If a category or section is specified but no index is specified, rules will be inserted at the end of the category or section.

In any given POST all of the rules will be inserted at a single point. You cannot specify multiple insertion locations in a POST request.




---

**Note** Rule order affects how orders are parsed by the Firepower Management Center.

---

## Response Structure




---

**Note** The REST API will serve only 25 results per page. This can be increased up to 1000 using the limit query parameter.

---

The response structure can be:

- **LOCATION** – Newly created resource ID; for POST only—holds the new resource ID (as a URI representation).
- **CONTENT-TYPE** – Media type describing the response message body; describes the representation and syntax of the response message body.
- Each response includes an HTTP status or error code. Available codes fall into these categories:
  - **20x** - A two-hundred series code indicates successful operation, including:
    - **200 OK**
      - Standard response for successful requests.
    - **201 Created**
      - Request completed; new resource created.
    - **202 Accepted**

- Request accepted, but processing not complete.
- 204 No Content
  - Server successfully processed request; no content is being returned.
- 4xx - A four-hundred series code indicates a client-side error, including:
  - 400 Bad Request
    - Invalid query parameters, including unrecognized parameters, missing parameters, or invalid values.
    - This can indicate that the object was edited or deleted via REST API such that the corresponding policy is invalidated.
  - 404 Not Found
    - The provided URL does not match an existing resource. For example, an HTTP DELETE may fail because the resource is unavailable.
  - 405 Method not Allowed
    - An HTTP request was presented that is not allowed on the resource; for example, a POST on a read-only resource.
  - 422 Unprocessable Entity
    - The payload is too large. This will occur when you send a payload greater than 2048000 bytes.
    - The payload contains an unprocessable or unreadable entity such as a invalid attribut name or incorrect JSON syntax.
  - 429 Too Many Requests
    - Too many requests were sent to the API. This error will occur if you send more than 120 requests per minute.
    - Too many concurrent requests. The system cannot accept more than 10 parallel requests from all clients.
    - Too many write operations per server. The API will only allow one PUT, POST, or DELETE request per user on a server at a time.
- 5xx - A five-hundred series code indicates a server-side error.

In the case of an error, in addition to the error code, the return response may include an error object containing more details about the error. The JSON error/warning response schema is as follows:

```
{
  "error": {
    "category": "FRAMEWORK",
    "messages": [
      {
        "description": "Action is mandatory to be specified."
      }
    ],
    "severity": "ERROR"
  }
}
```

```
}

```

where the object properties are:

**Table 1: Object Properties**

Property	Type	Description
messages	List of Dictionaries	List of error or warning messages
code	String	Error/Warning/Info code
details	String	Detailed message corresponding to Error/Warning/Info

## Rate Limiting

The Firepower Management Center REST API implements rate limiting to reduce network load.

The API will accept no more than 120 messages per minute from an individual IP address. It will only allow 10 simultaneous connections per IP address. These are not configurable parameters.

If a client exceeds these limits, the API will give an HTTP 429 error.

## Payload Limiting

The API cannot accept a message with a payload greater than 2048000 bytes. This applies to both the REST API and to API Explorer. This is not a configurable parameter.

If a message exceeds this limit, the API will give an HTTP 422 error.

## Object Overrides

An override defines an alternate value for an object, which the system uses for the device or domain specified. In a single request user can create multiple overrides for multiple objects using bulk operation.

When an object is overridden, the alternate values will be provided for that object when it is requested. This does not overwrite the original values, which will return if the override is removed. The override gives alternate values for all fields in the object except for the `Name` and `Description` fields.

The URL for this feature is:

```
https://{fmc_ip_or_name}:{https_port}/api/fmc_config/v1/domain/{Domain_uuid} /object/hosts
```

Request payload to create an override for object “testhost” on domain “Global \ RETAIL” with the override value being “1.2.3.5”:

```
{
  "type": "Host",
  "value": "1.2.3.5",
  "overrides": {
    "parent": {
      "id": <Parent UUID>
      "type": "Host"
    }
  }
}
```

```

    },
    "target": {
      "name": "Global \\ RETAIL",
      "id": <target domain UUID>,
      "type": "Domain"
    }
  },
  "overridable": true,
  "description": " ",
  "name": "testhost",
}

```

Optional:

?bulk=true

indicates the override creation for more than one object.

GET:

URL to list all overrides on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts/{host\_UUID}/overrides

URL for override for an object on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts/{host\_UUID}?overrideTargetId={target\_UUID}

URL for all the overrides on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/hosts?overrideTargetId={target\_UUID}




---

**Note** When overridden, the parent object value will never change.

---

## Audit Services

### GET auditrecords

Request Type: **GET**

Description: Retrieves audit records.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/audit/auditrecords

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/audit/auditrecords/{objectID}

Permissions: System > Monitoring > Audit

Parameters available for filtering: username, subsystem, source, starttime, endtime

## Deployment Services

### GET deployabledevices

Request Type: **GET**

Description: Retrieves list of all devices with configuration changes, ready to be deployed.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deployabledevices

Permissions: Deploy Configuration to Devices

Parameters available for filtering: name

## POST deploymentrequests

Request Type: **POST**

Description: Creates a request for deploying configuration changes to the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/deployment/deploymentrequests/{object\_UUID}

Permissions: Deploy Configuration to Devices

## Device Group Services

### DELETE devicegrouprecords

Request Type: **DELETE**

Description: Deletes a device group with the specified object ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

### PUT devicegrouprecords

Request Type: **PUT**

Description: Modifies a device group with the specified object ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

### POST devicegrouprecords

Request Type: **POST**

Description: Creates a device group with the specified object ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicegroups/devicegrouprecords

Permissions: Devices > Device Management > Modify Devices

### GET devicegrouprecords

Request Type: **GET**

Description: Retrieves the device group associated with the specified ID. If no ID is specified, retrieves list of all device groups.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devicegroups/devicegrouprecords`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devicegroups/devicegrouprecords/{object_UUID}`

Permissions: Devices > Device Management > View Devices

## Device Clusters

### GET ftddevicecluster

Request Type: **GET**

Description: Retrieves or modifies the FTD Cluster record associated with the specified ID. If no ID is specified for a GET, retrieves list of all FTD Clusters.

URL: `/api/fmc_config/v1/domain/{domainUUID}/deviceclusters/ftddevicecluster/`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domainUUID}/deviceclusters/ftddevicecluster/{objectId}`

Permissions: Devices > Device Management > View Devices

## Device HA Pair Services

### DELETE ftddevicehapair

Request Type: **DELETE**

Description: Deletes a device high availability pair with the specified object ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/{object_UUID}`

Permissions: Devices > Device Management > Modify Devices



---

**Note** Run the `configure high-availability disable` command to remove the failover configurations from FTD devices.

---

### PUT ftddevicehapair

Request Type: **PUT**

Description: Sets any one of the following actions for the Firepower Threat Defense high availability device:

- Sets the failover trigger criteria for the device
- Switches states within the device

- Breaks or force-breaks the device

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/{ha_container_UUID}
```

Permissions: Devices > Device Management > Modify Devices

## POST ftddevicehapairs

Request Type: **POST**

Description: Creates a high availability device pair with the specified primary and secondary object IDs. Do not perform the POST operation for more than one high availability pair at a time. Ensure that the current POST operation is completed successfully before proceeding to the next POST operation.



### Note

Typically, the first POST operation responds within 60 seconds. Cisco recommends that you perform subsequent POST operations at least 120 seconds after the first POST operation was initiated. The response of the POST operation includes a task object, with a task ID and task status. You can monitor the completion of the task by performing a GET operation on the task object with its task ID. For more information, see [GET taskstatus](#), on page 81.

---

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicehapairs/ftddevicehapairs

Permissions: Devices > Device Management > Modify Devices

## GET ftddevicehapairs

Request Type: **GET**

Description: Retrieves the details associated with the specified high availability container ID. If no ID is specified, retrieves a list of all high availability container objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devicehapairs/ftddevicehapairs

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/{ha_container_UUID}
```

Permissions: Devices > Device Management > Modify Devices

## DELETE failoverinterfacemacaddressconfigs

Request Type: **DELETE**

Description: Deletes the Firepower Threat Defense high availability failover policy interface MAC addresses record associated with the specified Firepower Threat Defense high availability pair.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/{hacontainer_UUID}/failoverinterfacemacaddressconfigs
```

Permissions: Devices > Device Management > Modify Devices

## GET failoverinterfacemacaddressconfigs

Request Type: **GET**

Description: Retrieves the Firepower Threat Defense high availability failover policy interface MAC addresses record associated with the specified FTD HA pair. If no ID is specified for a GET, it retrieves the list of all Firepower Threat Defense high availability failover policy interface MAC addresses records.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/failoverinterfacemacaddressconfigs
```

URL for GET by ID :

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/failoverinterfacemacaddressconfigs/{object_UUID}
```

Permissions: Devices > Device Management

## POST failoverinterfacemacaddressconfigs

Request Type: **POST**

Description: Creates the Firepower Threat Defense high availability failover policy interface MAC addresses record associated with the specified Firepower Threat Defense high availability pair.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/failoverinterfacemacaddressconfigs
```

Permissions: Devices > Device Management > Modify Devices

## PUT failoverinterfacemacaddressconfigs

Request Type: **PUT**

Description: Modifies the Firepower Threat Defense high availability failover policy interface MAC addresses record associated with the specified Firepower Threat Defense high availability pair.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/failoverinterfacemacaddressconfigs/{object_UUID}
```

Permissions: Devices > Device Management > Modify Devices

## GET monitoredinterfaces

Request Type: **GET**

Description: Retrieves the Firepower Threat Defense high availability Monitored interface policy record associated with the specified FTD HA pair. If no ID is specified for a GET, it retrieves the list of all Firepower Threat Defense high availability monitored interface policy records.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/monitoredinterfaces
```

URL for GET by ID :

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/monitoredinterfaces/{object_UUID}
```

Permissions: Devices > Device Management

## PUT monitoredinterfaces

Request Type: **PUT**

Description: Modifies the Firepower Threat Defense high availability Monitored interface policy record associated with the specified Firepower Threat Defense high availability pair.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/devicehapairs/ftddevicehapairs/  
{hacontainer_UUID}/monitoredinterfaces
```

Permissions: Devices > Device Management > Modify Devices

## Device Services

### POST copyconfigrequests

Request Type: **POST**

Description: Copies device configuration to the specified Firepower Threat Defense device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/copyconfigrequests

Permissions: Devices > Device Management > Modify Devices

### DELETE devicerecords

Request Type: **DELETE**

Description: Unregisters the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

### PUT devicerecords

Request Type: **PUT**

Description: Modifies the device record associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

## POST devicerecords

Request Type: **POST**

Description: Registers the specified device to the Firepower Management Center.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords`

Permissions: Devices > Device Management > Modify Devices

## GET devicerecords

Request Type: **GET**

Description: Retrieves device information. If a device ID is specified, the information for the specified device is retrieved. If no ID is specified, retrieves information for all devices.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{object_UUID}`

Permissions: Devices > Device Management

Parameters available for filtering: hostName

## PUT fpphysicalinterfaces

Request Type: **PUT**

Description: Modifies a physical interface on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{containerUUID}/fpphysicalinterfaces/{object_UUID}`

Permissions: Devices > Device Management > Modify Device

## GET fpphysicalinterfaces

Request Type: **GET**

Description: Retrieves information on the physical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all physical interfaces associated with the specified NGIPS device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/fpphysicalinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/fpphysicalinterfaces/{object_UUID}`

Permissions: Devices > Device Management

Parameters available for filtering: name

## DELETE fplogicalinterfaces

Request Type: **DELETE**

Description: Deletes logical interfaces on the specified device.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/fplogicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## PUT fplogicalinterfaces

Request Type: **PUT**

Description: Modifies a logical interface on the specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/fplogicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## POST fplogicalinterfaces

Request Type: **POST**

Description: Creates logical interfaces on the specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/fplogicalinterfaces

Permissions: Devices > Device Management > Modify Device

## GET fplogicalinterfaces

Request Type: **GET**

Description: Retrieves the logical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all logical interfaces associated with the specified NGIPS device ID.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/fplogicalinterfaces

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/fplogicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

## DELETE inlinesets

Request Type: **DELETE**

Description: Deletes inline sets on the specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/inlinesets/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## PUT inlinesets

Request Type: **PUT**

Description: Modifies an inline set on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/inlinesets/{object_UUID}`

Permissions: Devices > Device Management > Modify Device

## POST inlinesets

Request Type: **POST**

Description: Creates inline sets on the specified device.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/inlinesets`

Permissions: Devices > Device Management > Modify Device

## GET inlinesets

Request Type: **GET**

Description: Retrieves information on the inline set associated with the specified NGIPS device ID and inline set ID. If no inline set ID is specified, retrieves list of all inline sets associated with the specified NGIPS device ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/inlinesets`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/inlinesets/{object_UUID}`

Permissions: Devices > Device Management

Parameters available for filtering: name

## GET staticroutes

Request Type: **GET**

Description: Retrieves list of all IPv4 and IPv6 Static Routes associated with the specified device.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/staticroutes`

URL for GET ID::

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/staticroutes/{object_UUID}`

Permissions: Devices > Devices Management

## DELETE ipv4staticroutes

Request Type: **DELETE**

Description: Deletes the IPv4 Static Route associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv4staticroutes/{object_UUID}`

Permissions: Devices > Devices Management > Modify Devices

## PUT ipv4staticroutes

Request Type: **PUT**

Description: Modifies the IPv4 Static Route associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv4staticroutes/{object_UUID}`

Permissions: Devices > Devices Management > Modify Devices

## POST ipv4staticroutes

Request Type: **POST**

Description: Creates an IPv4 Static Route.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv4staticroutes`

Permissions: Devices > Device Management > Modify Devices

## GET ipv4staticroutes

Request Type: **GET**

Description: Retrieves the IPv4 Static Route associated with the specified ID. If no ID is specified, retrieves list of all IPv4 Static Routes.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv4staticroutes`

URL for GET ID::

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv4staticroutes/{object_UUID}`

Permissions: Devices > Devices Management

## DELETE ipv6staticroutes

Request Type: **DELETE**

Description: Deletes the IPv6 Static Route associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv6staticroutes/{object_UUID}`

Permissions: Devices > Device Management > Modify Devices

## PUT ipv6staticroutes

Request Type: **PUT**

Description: Modifies the IPv6 Static Route associated with the specified ID.

URL:

/api/fmc\_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv6staticroutes/{object\_UUID}

Permissions: Devices > Device Management > Modify Devices

## POST ipv6staticroutes

Request Type: **POST**

Description: Creates an IPv6 Static Route.

URL:

/api/fmc\_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv6staticroutes

Permissions: Devices > Device Management > Modify Devices

## GET ipv6staticroutes

Request Type: **GET**

Description: Retrieves the IPv6 Static Route associated with the specified ID. If no ID is specified, retrieves list of all IPv6 Static Routes.

URL:

/api/fmc\_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv6staticroutes

URL for GET ID:

/api/fmc\_config/v1/domain/{domainUUID}/devices/devicerecords/{containerUUID}/routing/ipv6staticroutes/{object\_UUID}

Permissions: Devices > Device Management

## DELETE virtualswitches

Request Type: **DELETE**

Description: Deletes a virtual switch on the specified device.

**This method is only available on a Firepower 1010 device.**

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/virtualswitches/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## PUT virtualswitches

Request Type: **PUT**

Description: Modifies a virtual switch on the specified device.

**This method is only available on a Firepower 1010 device.**

URL:

/api/fmc\_config/v1/domain/{UUID}/devices/devicerecords/{containerUUID}/virtualswitches/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## POST virtualswitches

Request Type: **POST**

Description: Creates a virtual switch on the specified device.

**This method is only available on a Firepower 1010 device.**

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/virtualswitches

Permissions: Devices > Device Management > Modify Device

## GET virtualswitches

Request Type: **GET**

Description: Retrieves virtual switch associated with the specified NGIPS device ID and virtual switch ID. If no virtual switch ID is specified, retrieves list of all virtual switches associated with the specified NGIPS device ID.

**This method is only available on a Firepower 1010 device.**

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/virtualswitches

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/virtualswitches/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering: name

## PUT fpphysicalinterfaces

Request Type: **PUT**

Description: Modifies a physical interface on the specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{containerUUID}/fpphysicalinterfaces/{object\_UUID}

Permissions: Devices > Device Management > Modify Device

## GET fpphysicalinterfaces

Request Type: **GET**

Description: Retrieves information on the physical interface associated with the specified NGIPS device ID and interface ID. If no ID is specified, retrieves list of all physical interfaces associated with the specified NGIPS device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/fpphysicalinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/fpphysicalinterfaces/{object_UUID}`

Permissions: Devices > Device Management

Parameters available for filtering: name

## PUT physicalinterfaces

Request Type: **PUT**

Description: Modifies physical interfaces on a specified device.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/physicalinterfaces`

Permissions: Devices > Device Management > Modify Device

## GET physicalinterfaces

Request Type: **GET**

Description: Retrieves the physical interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all physical interfaces associated with the specified NGFW device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/physicalinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/physicalinterfaces/{object_UUID}`

Permissions: Devices > Device Management

## GET bridgegroupinterfaces

Request Type: **GET**

Description: Retrieves the bridge group interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all bridge group interfaces associated with the specified NGFW device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/bridgegroupinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/bridgegroupinterfaces/{object_UUID}`

Permissions: Devices > Device Management

## POST bridgegroupinterfaces

Request Type: **POST**

Description: Creates bridge group interfaces associated with the specified NGFW device ID and interface ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/bridgegroupinterfaces`

Permissions: Devices > Device Management > Modify Device

## PUT bridgegroupinterfaces

Request Type: **PUT**

Description: Modifies a bridge group interface on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/bridgegroupinterfaces`

Permissions: Devices > Device Management > Modify Device

## DELETE bridgegroupinterfaces

Request Type: **DELETE**

Description: Deletes a bridge group interface associated with the specified NGFW device ID and interface ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/bridgegroupinterfaces`

Permissions: Devices > Device Management > Modify Device

## GET redundantinterfaces

Request Type: **GET**

Description: Retrieves the redundant interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all redundant interfaces associated with the specified NGFW device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/redundantinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/redundantinterfaces/{object_UUID}`

Permissions: Devices > Device Management

## POST redundantinterfaces

Request Type: **POST**

Description: Creates redundant interfaces on a specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/redundantinterfaces

Permissions: Devices > Device Management

## PUT redundantinterfaces

Request Type: **PUT**

Description: Modifies redundant interfaces on a specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/redundantinterfaces

Permissions: Devices > Device Management > Modify Device

## DELETE redundantinterfaces

Request Type: **DELETE**

Description: Removes redundant interfaces on a specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/redundantinterfaces

Permissions: Devices > Device Management

## GET etherchannelinterfaces

Request Type: **GET**

Description: Retrieves the ethernet channel interface associated with the specified NGFW device ID and interface ID. If no ID is specified, retrieves list of all ethernet channel interfaces associated with the specified NGFW device ID.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/etherchannelinterfaces

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/etherchannelinterfaces/{object\_UUID}

Permissions: Devices > Device Management

Parameters available for filtering:

## POST etherchannelinterfaces

Request Type: **POST**

Description: Creates ethernet channel interfaces on the specified device.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/devices/devicerecords/{container\_UUID}/etherchannelinterfaces

Permissions: Devices > Device Management > Modify Device

## PUT etherchannelinterfaces

Request Type: **PUT**

Description: Modifies an ethernet channel interfaces on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{containerUUID}/ethernetchannelinterfaces/`

Permissions: Devices > Device Management > Modify Device

## DELETE etherchannelinterfaces

Request Type: **DELETE**

Description: Removes ethernet channel interfaces from a specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/ethernetchannelinterfaces`

Permissions: Devices > Device Management

## GET subinterfaces

Request Type: **GET**

Description: Retrieves the sub-interface associated with the specified NGFW device ID and interface ID. If no interface ID is specified, retrieves list of all sub-interfaces associated with the specified NGFW device ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/subinterfaces`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/subinterfaces/{object_UUID}`

Permissions: Devices > Device Management

## POST subinterfaces

Request Type: **POST**

Description: Creates sub interfaces on a specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/subinterfaces`

Permissions: Devices > Device Management

## PUT subinterfaces

Request Type: **PUT**

Description: Modifies a sub interface on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/subinterfaces/`

Permissions: Devices > Device Management > Modify Device

## DELETE subinterfaces

Request Type: **DELETE**

Description: Deletes sub interfaces on a specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/subinterfaces`

Permissions: Devices > Device Management

## GET fpinterfacestatistics

Request Type: **GET**

Description: Retrieves list of statistics for all interfaces associated with the specified NGIPS device ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/fpinterfacestatistics`

Permissions: Devices > Device Management

Parameters available for filtering: name

## POST interfaceevents

Request Type: **POST**

Description: Creates netmod events on the specified device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/interfaceevents`

Permissions: Devices > Device Management > Modify Device

## GET interfaceevents

Request Type: **GET**

Description: Retrieves list of all netmod events on the device.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/devices/devicerecords/{container_UUID}/interfaceevents`

Permissions: Devices > Device Management

# Intelligence Services

## POST collections

Request Type: **POST**

Description: Adds a collections from a TAXII source.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/taxiiconfig/collections`

Permissions: Intelligence

## POST discoveryinfo

Request Type: **POST**

Description: Adds information about TAXII collections available from a source.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/taxiiconfig/discoveryinfo`

Permissions: Intelligence

## GET element

Request Type: **GET**

Description: Retrieves the intelligence-enabled sensor associated with the specified ID. If no ID is specified, retrieves list of all intelligence-enabled sensors.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/element`

URL for GET by ID: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/element/{object_UUID}`

Permissions: Intelligence

## DELETE incident

Request Type: **DELETE**

Description: Deletes an incident.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/taxiiconfig/incident/{object_UUID}`

Permissions: Intelligence

## PUT incident

Request Type: **PUT**

Description: Modifies an intelligence incident with the specified object ID.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/incident/{object_UUID}`

Permissions: Intelligence

## GET incident

Request Type: **GET**

Description: Retrieves the intelligence incident associated with the specified ID. If no ID is specified, retrieves list of all intelligence incidents. By default 25 results will be displayed on each page, this can be increased up to 40 using the `limit` parameter.

URL: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/incident

URL for GET by ID: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/incident/{object\_UUID}

Permissions: Intelligence

## PUT indicator

Request Type: **PUT**

Description: Modifies an indicator with the specified object ID.

URL: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/indicator/{object\_UUID}

Permissions: Intelligence

## GET indicator

Request Type: **GET**

Description: Retrieves the indicator associated with the specified ID. If no ID is specified, retrieves list of all indicators. By default 25 results will be displayed on each page, this can be increased up to 40 using the `limit` parameter.

URL: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/indicator

URL for GET by ID: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/indicator/{object\_UUID}

Permissions: Intelligence

## PUT observable

Request Type: **PUT**

Description: Modifies an observable with the specified object ID.

URL: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/observable/{object\_UUID}

Permissions: Intelligence

## GET observable

Request Type: **GET**

Description: Retrieves the observable associated with the specified ID. If no ID is specified, retrieves list of all observables. By default 25 results will be displayed on each page, this can be increased up to 40 using the `limit` parameter.

URL: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/observable

URL for GET by ID: /api/fmc\_tid/v1/domain/{domain\_UUID}/tid/observable/{object\_UUID}

Permissions: Intelligence

## PUT settings

Request Type: **PUT**

Description: Activates or deactivates an intelligence setting.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/settings/{value}`

Permissions: Intelligence

## GET settings

Request Type: **GET**

Description: Retrieves the on/off settings for the specified value. If no ID is specified, retrieves list of all TID settings.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/settings`

URL for GET by value: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/settings/{value}`

Permissions: Intelligence

## DELETE source

Request Type: **DELETE**

Description: Deletes an intelligence source from the device.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/taxiiconfig/source/{object_UUID}`

Permissions: Intelligence

## PUT source

Request Type: **PUT**

Description: Modifies an intelligence source with the specified object ID.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/source/{object_UUID}`

Permissions: Intelligence

## POST source

Request Type: **POST**

Description: Adds a source for intelligence information.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/source`

Permissions: Intelligence

## GET source

Request Type: **GET**

Description: Retrieves the intelligence source associated with the specified ID. If no ID is specified, retrieves list of all intelligence sources. By default 25 results will be displayed on each page, this can be increased up to 40 using the `limit` parameter.

URL: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/source`

URL for GET by ID: `/api/fmc_tid/v1/domain/{domain_UUID}/tid/source/{object_UUID}`

Permissions: Intelligence

## Integration Services

### PUT cloudeventsconfigs

Request Type: **PUT**

Description: Modifies the cloud event configuration associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domainUUID}/integration/cloudeventsconfigs/{objectId}`

Permissions: Object Manager > Modify Object Manager

### GET cloudeventsconfigs

Request Type: **GET**

Description: Retrieves the cloud event configuration associated with the specified ID. If no ID is specified for a GET, retrieves a list of all cloud event configuration objects.

URL for listing: `/api/fmc_config/v1/domain/{domainUUID}/integration/cloudeventsconfigs`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domainUUID}/integration/cloudeventsconfigs/{objectId}`

Permissions: Object Manager

### DELETE externallookups

#### **DELETE externallookups**

Description: Deletes the external lookup objects with the specified UUID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/integration/externallookups/{object_UUID}`

Permissions: Object Manager>Modify Object Manager

### PUT externallookups

Request Type: **PUT**

Description: Modifies externallookups objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/integration/externallookups/{object_UUID}`

Permissions: Object Manager>Modify Object Manager

## POST externallookups

### POST externallookups

Description: Creates externallookups objects with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/integration/externallookups

Permissions: Object Manager>Modify Object Manager

## GET externallookups

### GET externallookups

Retrieves the externallookups object associated with the specified ID. If no ID, retrieves list of all externallookups objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/integration/externallookups

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/integration/externallookups/{object\_UUID}

Permissions: Object Manager>Modify Object Manager

Parameters available for filtering:

## DELETE packetanalyzerdevices

Request Type: **DELETE**

Description: Deletes the packet analyzer object with the specified UUID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/integration/packetanalyzerdevices/{object\_UUID}

Permissions: Object Manager>Modify Object Manager

## PUT packetanalyzerdevices

Request Type: **PUT**

Description: Modifies the packet analyzer object with the specified UUID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/integration/packetanalyzerdevices/{object\_UUID}

Permissions: Object Manager>Modify Object Manager

## POST packetanalyzerdevices

Request Type: **POST**

Description: Creates PKI enrollments objects with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/packetanalyzerdevices

Permissions: Object Manager

## GET packetanalyzerdevices

Request Type: **GET**

Description: Retrieves the packetanalyzerdevices object associated with the specified ID. If no ID, retrieves list of all packetanalyzerdevices objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/integration/packetanalyzerdevices

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/integration/packetanalyzerdevices/{object\_UUID}

Permissions: Object Manager>Modify Object Manager

Parameters available for filtering:

## Object Services

### GET anyprotocolportobjects

Request Type: **GET**

Description: Retrieves the any protocol port object associated with the specified ID. If no ID is specified, retrieves list of all protocol port objects with the protocol set to All.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/anyprotocolportobjects

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/anyprotocolportobjects/{object\_UUID}

Permissions: Object Manager

### GET applicationcategories

Request Type: **GET**

Description: Retrieves the application category object associated with the specified ID. If no ID is specified, retrieves list of all application category objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationcategories

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationcategories/{object\_UUID}

Permissions: Object Manager

### GET applicationfilters

Request Type: **GET**

Description: Retrieves the application filter object associated with the specified ID. If no ID is specified, retrieves list of all application filter objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationfilters

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationfilters/{object\_UUID}

Permissions: Object Manager

## GET applicationproductivities

Request Type: **GET**

Description: Retrieves the application productivity object associated with the specified ID. If no ID is specified, retrieves list of all application productivity objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationproductivities

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationproductivities/{object\_UUID}

Permissions: Object Manager

## GET applicationrisks

Request Type: **GET**

Description: Retrieves the application risk object associated with the specified ID. If no ID is specified, retrieves list of all application risk objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationrisks

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationrisks/{object\_UUID}

Permissions: Object Manager

## GET applications

Request Type: **GET**

Description: Retrieves the application object associated with the specified ID. If no ID is specified, retrieves list of all application objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applications

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applications/{object\_UUID}

Permissions: Object Manager

## GET applicationtags

Request Type: **GET**

Description: Retrieves the application tag object associated with the specified ID. If no ID is specified, retrieves list of all application tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/applicationtags

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/applicationtags/{object_UUID}`

Permissions: Object Manager

## GET applicationtypes

Request Type: **GET**

Description: Retrieves the application type object associated with the specified ID. If no ID is specified, retrieves list of all application type objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/applicationtypes`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/applicationtypes/{object_UUID}`

Permissions: Object Manager

## GET certenrollments

Request Type: **GET**

Description: Retrieves the PKI enrollments object associated with the specified ID. If no ID is specified for a GET, retrieves list of all PKI enrollment objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/devicegroups/certenrollments`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/devicegroups/certenrollments/{parent_object_UUID}`

Permissions: Devices > Device Management > View Devices

## GET continents

Request Type: **GET**

Description: Retrieves the continent object associated with the specified ID. If no ID is specified, retrieves list of all continent objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/continents`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/continents/{object_UUID}`

Permissions: Object Manager

## GET countries

Request Type: **GET**

Description: Retrieves the country object associated with the specified ID. If no ID is specified, retrieves list of all country objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/countries`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/countries/{object_UUID}`

Permissions: Object Manager

## DELETE dnsservergroups

Request Type: **DELETE**

Description: Deletes a DNS server group with the specified object ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/dnsservergroups/{object_UUID}`

Permissions: Devices > Device Management > Modify Devices

## PUT dnsservergroups

Request Type: **PUT**

Description: Modifies a DNS server group with the specified object ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/dnsservergroups`

Permissions: Devices > Device Management > Modify Devices

## POST dnsservergroups

Request Type: **POST**

Description: Creates a DNS server group group with the specified object ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/dnsservergroups`

Permissions: Devices > Device Management > Modify Devices

## GET dnsservergroups

Request Type: **GET**

Description: Retrieves the DNS server group associated with the specified ID. If no ID is specified, retrieves list of all dns server groups.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/dnsservergroups`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/dnsservergroups/{object_UUID}`

Permissions: Devices > Device Management > View Devices

## GET endpointdevicetypes

Request Type: **GET**

Description: Retrieves the endpoint device type object associated with the specified ID. If no ID is specified, retrieves list of all endpoint device type objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/endpointdevicetypes`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/endpointdevicetypes/{object_UUID}`

Permissions: Object Manager

## GET extendedaccesslist

Request Type: **GET**

Description: Retrieves extended access list associated with the specified ID. If no ID is specified, retrieves list of all extended access lists.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/extendedaccesslist`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/extendedaccesslist/{object_UUID}`

Permissions: Devices > Device Management > View Devices

## DELETE fqdns

Request Type: **DELETE**

Description: Deletes the FQDN object associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT fqdns

Request Type: **PUT**

Description: Modifies the FQDN object associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST fqdns

Request Type: **POST**

Description: Creates or overrides the FQDN objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET fqdns

Request Type: **GET**

Description: Retrieves the FQDN object associated with the specified ID. If no ID is specified for a GET, retrieves list of all FQDN objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{fqdn_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/fqdns/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## GET geolocation

Request Type: **GET**

Description: Retrieves the geolocation object associated with the specified ID. If no ID is specified, retrieves list of all geolocation objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/geolocations`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/geolocations/{object_UUID}`

Permissions: Object Manager

## DELETE hosts

Request Type: **DELETE**

Description: Deletes the specified host object.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT hosts

Request Type: **PUT**

Description: Modifies a host object.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST hosts

Request Type: **POST**

Description: Creates or overrides the host objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET hosts

Request Type: **GET**

Description: Retrieves the host object associated with the specified ID. If no ID is specified, retrieves list of all host objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/hosts?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{host_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/hosts/{host_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## DELETE icmpv4objects

Request Type: **DELETE**

Description: Deletes the specified ICMPv4 port.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT icmpv4objects

Request Type: **PUT**

Description: Modifies ICMPv4 port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST icmpv4objects

Request Type: **POST**

Description: Creates or overrides the ICMPv4 port objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects`

URL for Bulk Post : `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET icmpv4objects

Request Type: **GET**

Description: Retrieves the ICMPv4 object associated with the specified ID. If no ID, retrieves list of all ICMPv4 objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmp4objects?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv4objects/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmp4objects/{icmpv4object_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmp4objects/{icmp4object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## DELETE icmpv6objects

Request Type: **DELETE**

Description: Deletes the specified ICMPv6 port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT icmpv6objects

Request Type: **PUT**

Description: Modifies ICMPv6 port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST icmpv6objects

Request Type: **POST**

Description: Creates or overrides the ICMPv6 port objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET icmpv6objects

Request Type: **GET**

Description: Retrieves the ICMPv6 object associated with the specified ID. If no ID is specified, retrieves list of all ICMPv6 objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{icmpv6object_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/icmpv6objects/{icmpv6object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## DELETE ikev1ipsecproposals

Request Type: **DELETE**

Description: Deletes the IKEv1 IPsec Proposal associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ikev1ipsecproposals/{ikev1ipsecproposal_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT ikev1ipsecproposals

Request Type: **PUT**

Description: Modifies the IKEv1 IPsec Proposal associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ikev1ipsecproposals/{ikev1ipsecproposal_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST ikev1ipsecproposals

Request Type: **POST**

Description: Creates the IKEv1 IPsec Proposal associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev1ipsecproposals

Permissions: Object Manager > Modify Object Manager

## GET ikev1ipsecproposals

Request Type: **GET**

Description: Retrieves the IKEv1 IPsec Proposal associated with the specified ID. If no ID is specified for a GET, retrieves list of all IKEv1 IPsec Proposal objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ikev1ipsecproposals

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev1ipsecproposals/{ikev1ipsecproposal\_UUID}

Permissions: Object Manager

## DELETE ikev1policies

Request Type: **DELETE**

Description: Deletes the IKEv1 policy object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev1policies/{ikev1policy\_UUID}

Permissions: Object Manager > Modify Object Manager

## PUT ikev1policies

Request Type: **PUT**

Description: Modifies the IKEv1 policy object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev1policies/{ikev1policy\_UUID}

Permissions: Object Manager > Modify Object Manager

## POST ikev1policies

Request Type: **POST**

Description: Creates the IKEv1 policy object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev1policies

Permissions: Object Manager > Modify Object Manager

## GET ikev1policies

Request Type: **GET**

Description: Retrieves the IKEv1 policy object associated with the specified ID. If no ID is specified for a GET, retrieves list of all IKEv1 policy objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ikev1policies`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ikev1policies/{ikev1policy_UUID}`

Permissions: Object Manager

## DELETE ikev2ipsecproposals

Request Type: **DELETE**

Description: Deletes the IKEv2 IPsec Proposal associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ikev2ipsecproposals/{ikev2ipsecproposal_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT ikev2ipsecproposals

Request Type: **PUT**

Description: Modifies the IKEv2 IPsec Proposal associated with the specified ID.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ikev2ipsecproposals/{ikev2ipsecproposal_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST ikev2ipsecproposals

Request Type: **POST**

Description: Creates the IKEv2 IPsec Proposal associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ikev2ipsecproposals`

Permissions: Object Manager > Modify Object Manager

## GET ikev2ipsecproposals

Request Type: **GET**

Description: Retrieves the IKEv2 IPsec Proposal associated with the specified ID. If no ID is specified for a GET, retrieves list of all IKEv2 IPsec Proposal objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ikev2ipsecproposals`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ikev2ipsecproposals/{ikev2ipsecproposal_UUID}`

Permissions: Object Manager

## DELETE ikev2policies

Request Type: **DELETE**

Description: Deletes the IKEv2 object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev2policies/{ikev2policy\_UUID}

Permissions: Object Manager > Modify Object Manager

## PUT ikev2policies

Request Type: **PUT**

Description: Modifies the IKEv2 object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev2policies/{ikev2policy\_UUID}

Permissions: Object Manager > Modify Object Manager

## POST ikev2policies

Request Type: **POST**

Description: Creates the IKEv2 object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev2policies

Permissions: Object Manager > Modify Object Manager

## GET ikev2policies

Request Type: **GET**

Description: Retrieves the IKEv2 object associated with the specified ID. If no ID is specified for a GET, retrieves list of all IKEv2 IPsec Proposal objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ikev2policies

URL for GET by ID:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/ikev2policies/{ikev2policy\_UUID}

Permissions: Object Manager

## DELETE interfacegroups

Request Type: **DELETE**

Description: Deletes the Interface group objects associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/interfacegroups/{object\_UUID}

URL on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/interfacegroups/{object\_UUID}?overrideTargetId={target\_UUID}

Permissions: Object Manager > Modify Object Manager

## PUT interfacegroups

Request Type: **PUT**

Description: Modifies the Interface group objects associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST interfacegroups

Request Type: **POST**

Description: Creates or overrides the Interface group objects associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET interfacegroups

Request Type: **GET**

Description: Retrieves the Interface group objects associated with the specified ID. If no ID is specified for a GET, retrieves list of all interface group objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups/{interfacegroups_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/interfacegroups/{interfacegroups_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## GET interfaceobjects

Request Type: **GET**

Description: Retrieves list of all the interface objects both security zones and interface groups.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/interfaceobjects`

URL for all the overrides on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/interfaceobjects?overrideTargetId={target_UUID}
```

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/interfaceobjects/{object_UUID}
```

URL to list all overrides on a particular object::

```
/api/fmc_config/v1/domain/{domain_UUID}/object/interfaceobjects/{interfaceobjects_UUID}/overrides
```

URL for override for an object on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/interfaceobjects/{interfaceobjects_UUID}?overrideTargetId={target_UUID}
```

Permissions: Object Manager

## GET isecuritygroupstags

Request Type: **GET**

Description: Retrieves the ISE security group tag object with the specified ID. If no ID is specified, retrieves list of all ISE security group tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/isecuritygroupstags

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/isecuritygroupstags/{object_UUID}
```

Permissions: Object Manager

## GET keychain

Request Type: **GET**

Description: Retrieves the keychain object associated with the specified ID. If no ID is specified for a GET, retrieves list of all keychain objects.

URL for listing: /api/fmc\_config/v1/domain/{domain\_UUID}/object/keychains

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/keychains/{keychain\_UUID}

URL to list all overrides on a particular object. If the object ID is not specified, displays all keychain objects:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychains_UUID}/overrides/{objectId}
```

URL for all the overrides on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/keychains?overrideTargetId={target_UUID}
```

URL for override for an object on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychain_UUID}?overrideTargetId={target_UUID}
```




---

**Note** The target UUID could be that of a domain or a device.

---

Permissions: Object Manager

## DELETE keychain

Request Type: **DELETE**

Description: Deletes the keychain object associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychain_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychain_UUID}?overrideTargetId={target_UUID}`




---

**Note** The target UUID could be that of a domain or a device.

---

Permissions: Object Manager > Modify Object Manager

## PUT keychain

Request Type: **PUT**

Description: Modifies the keychain object associated with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychain_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/keychains/{keychain_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST keychain

Request Type: **POST**

Description: Creates or overrides the keychain objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/keychains`

URL for Bulk Post:

`/api/fmc_config/v1/domain/{domain_UUID}/object/keychains?bulk=true`

URL to create an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/keychains`




---

**Attention** If override was not set when creating the key chain object:

1. Using PUT, update the override property of the key chain object to "true".
  2. Create the POST override for the key chain object.
- 

Permissions: Object Manager > Modify Object Manager

## GET networkaddresses

Request Type: **GET**

Description: Retrieves list of all network and host objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkaddresses`

Permissions: Object Manager

## DELETE networkgroups

Request Type: **DELETE**

Description: Deletes the specified Network Group.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT networkgroups

Request Type: **PUT**

Description: Modifies a Network Group.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST networkgroups

Request Type: **POST**

Description: Creates or overrides the network group with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET networkgroups

Request Type: **GET**

Description: Retrieves the network group object associated with the specified ID. If no ID is specified, retrieves list of all network group objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{networkgroups_UUID}/overrides`

URL for override for an object on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/networkgroups/{networkgroups_UUID}?overrideTargetId={target_UUID}
```

Permissions: Object Manager

## DELETE networks

Request Type: **DELETE**

Description: Deletes the specified network objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID}

URL to DELETE overrides on a particular object:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/networks/{object_UUID}?overrideTargetId={target_UUID}
```

Permissions: Object Manager > Modify Object Manager

## PUT networks

Request Type: **PUT**

Description: Modifies network objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID}

URL to edit or update an override on a particular object:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/networks/{parent_object_UUID}
```

Permissions: Object Manager > Modify Object Manager

## POST networks

Request Type: **POST**

Description: Creates or overrides the network objects with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks

URL for Bulk Post: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks?bulk=true

Permissions: Object Manager > Modify Object Manager

## GET networks

Request Type: **GET**

Description: Retrieves the network objects associated with the specified ID. If no ID is specified, retrieves list of all network objects.

URL for listing: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks

URL for all the overrides on a particular domain or device:

```
/api/fmc_config/v1/domain/{domain_UUID}/object/networks?overrideTargetId={target_UUID}
```

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/networks/{object\_UUID}

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networks/{network_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/networks/{network_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## DELETE portobjectgroups

Request Type: **DELETE**

Description: Deletes the specified port object groups.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT portobjectgroups

Request Type: **PUT**

Description: Modifies port object groups.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST portobjectgroups

Request Type: **POST**

Description: Creates or overrides the port object groups with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET portobjectgroups

Request Type: **GET**

Description: Retrieves the port object group object associated with the specified ID. If no ID is specified, retrieves list of all port object group objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups?overrideTargetId={target_UUID}`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{portobjectgroup_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/portobjectgroups/{portobjectgroup_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## GET ports

Request Type: **GET**

Description: Retrieves list of all port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ports`

Permissions: Object Manager

## DELETE protocolportobjects

Request Type: **DELETE**

Description: Deletes the specified protocol port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT protocolportobjects

Request Type: **PUT**

Description: Modifies protocol port objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST protocolportobjects

Request Type: **POST**

Description: Creates or overrides the protocol port objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET protocolportobjects

Request Type: **GET**

Description: Retrieves the protocol port object associated with the specified ID. If no ID is specified, retrieves list of all protocol port objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects?overrideTargetId={target_UUID}`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{protocolportobject_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/protocolportobjects/{protocolportobject_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## DELETE ranges

Request Type: **DELETE**

Description: Deletes the specified address range.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT ranges

Request Type: **PUT**

Description: Modifies an address range.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST ranges

Request Type: **POST**

Description: Creates or overrides an address range with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET ranges

Request Type: **GET**

Description: Retrieves the address range object associated with the specified ID. If no ID is specified, retrieves list of all address range objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ranges?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{range_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/ranges/{range_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## GET realms

Request Type: **GET**

Description: Retrieves the realm object associated with the specified ID. If no ID is specified, retrieves list of all realm objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/realms`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/realms/{object_UUID}`

Permissions: Object Manager

## GET realmusergroups

Request Type: **GET**

Description: Retrieves the realm user group object associated with the specified ID. If no ID is specified, retrieves list of all realm user group objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/realmusergroups`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/realmusergroups/{object_UUID}`

Permissions: Object Manager

Parameters available for filtering: realmUuid



---

**Note** This is a required parameter.

---

## GET realmusers

Request Type: **GET**

Description: Retrieves the realm user object associated with the specified ID. If no ID is specified, retrieves list of all realm user objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/realmusers`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/realmusers/{object_UUID}`

Permissions: Object Manager

Parameters available for filtering: realmUuid



---

**Note** This is a required parameter.

---

## GET securitygrouptags

Request Type: **GET**

Description: Retrieves the custom security group tag object associated with the specified ID. If no ID is specified, retrieves list of all custom security group tag objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/securitygrouptags`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/object/securitygrouptags/{object_UUID}`

Permissions: Object Manager

Parameters available for filtering: name

## DELETE securityzones

Request Type: **DELETE**

Description: Deletes the specified securityzone objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones/{object_UUID}`

Permissions: Object Manager>Modify Object Manager

## PUT securityzones

Request Type: **PUT**

Description: Modifies a securityzone object.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones/{object_UUID}`

Permissions: Object Manager>Modify Object Manager

## POST securityzones

Request Type: **POST**

Description: Creates or overrides the securityzone objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET securityzones

Request Type: **GET**

Description: Retrieves the security zone objects associated with the specified ID. If no ID is specified, retrieves list of all security zone objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/securityzones/{object_UUID}`

Permissions: Object Manager

Parameters available for filtering: name

## GET siurlfeeds

Request Type: **GET**

Description: Retrieves the Security Intelligence url feed object associated with the specified ID. If no ID is specified, retrieves list of all Security Intelligence url feed objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/siurlfeeds`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/siurlfeeds/{object_UUID}`

Permissions: Object Manager

## GET siurllists

Request Type: **GET**

Description: Retrieves the Security Intelligence url list object associated with the specified ID. If no ID is specified, retrieves list of all Security Intelligence url list objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/siurllists`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/siurllists/{object_UUID}`

Permissions: Object Manager

## DELETE slamonitors

Request Type: **DELETE**

Description: Deletes the sla monitor object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors/{object\_UUID}

Permissions: Object Manager > Modify Object Manager

## PUT slamonitors

Request Type: **PUT**

Description: Modifies the sla monitor object associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors/{object\_UUID}

Permissions: Object Manager > Modify Object Manager

## POST slamonitors

Request Type: **POST**

Description: Creates or overrides a SLA monitor with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors

URL for Bulk Post: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors?bulk=true

Permissions: Object Manager > Modify Object Manager

## GET slamonitors

Request Type: **GET**

Description: Retrieves the SLA Monitors associated with the specified ID. If no ID is specified, retrieves list of all SLA Monitors.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors

URL by GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/slamonitors/{object\_UUID}

Permissions: Object Manager

## GET tunneltags

Request Type: **GET**

Description: Retrieves the tunnel tag object associated with the specified ID. If no ID is specified, retrieves list of all tunnel tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/tunneltags

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/tunneltags/{object\_UUID}

Permissions: Object Manager

## GET urlcategories

Request Type: **GET**

Description: Retrieves the url category object associated with the specified ID. If no ID is specified, retrieves list of all url category objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlcategories`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlcategories/{object_UUID}`

Permissions: Object Manager

## DELETE urlgroups

Request Type: **DELETE**

Description: Deletes the specified urlgroup objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT urlgroups

Request Type: **PUT**

Description: Modifies urlgroup objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST urlgroups

Request Type: **POST**

Description: Creates or overrides the urlgroup objects with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups`

URL for Bulk Post: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET urlgroups

Request Type: **GET**

Description: Retrieves the url group objects associated with the specified ID. If no ID is specified, retrieves list of all url group objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{urlgroup_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urlgroups/{urlgroup_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## DELETE urls

Request Type: **GET**

Description: Deletes the specified URL.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT urls

Request Type: **PUT**

Description: Modifies a URL.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{parent_object_UUID}`

Permissions: Object Manager

## POST urls

Request Type: **POST**

Description: Creates or overrides the URLs with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/urls`

URL for Bulk Post : `/api/fmc_config/v1/domain/{domain_UUID}/object/urls?bulk=true`

Permissions: Object Manager > Modify Object Manager

## GET urls

Request Type: **GET**

Description: Retrieves the url objects associated with the specified ID. If no ID is specified, retrieves list of all url objects.

URL for listing: `/api/fmc_config/v1/domain/{domain_UUID}/object/urls`

URL for all the overrides on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urls?overrideTargetId={target_UUID}`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{object_UUID}`

URL to list all overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{url_UUID}/overrides`

URL for override for an object on a particular domain or device:

`/api/fmc_config/v1/domain/{domain_UUID}/object/urls/{url_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager

## GET variablesets

Request Type: **GET**

Description: Retrieves the variable set object associated with the specified ID. If no ID is specified, retrieves list of all variable set objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/variablesets`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/object/variablesets/{object_UUID}`

Permissions: Object Manager

## DELETE vlangrouptags

Request Type: **DELETE**

Description: Deletes the specified vlangrouptag objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/vlangrouptags/{object_UUID}`

URL to DELETE overrides on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/vlangrouptags/{object_UUID}?overrideTargetId={target_UUID}`

Permissions: Object Manager > Modify Object Manager

## PUT vlangrouptags

Request Type: **PUT**

Description: Modifies vlangrouptag objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/object/vlangrouptags/{object_UUID}`

URL to edit or update an override on a particular object:

`/api/fmc_config/v1/domain/{domain_UUID}/object/vlangrouptags/{parent_object_UUID}`

Permissions: Object Manager > Modify Object Manager

## POST vlangrouptags

Request Type: **POST**

Description: Creates or overrides the VLAN group tags with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags

URL for Bulk Post : /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags?bulk=true

Permissions: Object Manager > Modify Object Managers

## GET vlangrouptags

Request Type: **GET**

Description: Retrieves the vlan group tag objects associated with the specified ID. If no ID is specified, retrieves list of all vlan group tag objects.

URL for listing: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags

URL for all the overrides on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags?overrideTargetId={target\_UUID}

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{object\_UUID}

URL to list all overrides on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{vlangrouptag\_UUID}/overrides

URL for override for an object on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlangrouptags/{vlangrouptag\_UUID}?overrideTargetId={target\_UUID}

Permissions: Object Manager > Modify Object Manager

## DELETE vlantags

Request Type: **DELETE**

Description: Deletes the specified VLAN tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID}

URL to DELETE overrides on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID}?overrideTargetId={target\_UUID}

Permissions: Object Manager > Modify Object Manager

## PUT vlantags

Request Type: **PUT**

Description: Modifies VLAN tag objects.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID}

URL to edit or update an override on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{parent\_object\_UUID}

Permissions: Object Manager > Modify Object Manager

## POST vlantags

Request Type: **POST**

Description: Creates or overrides the VLAN tags with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags

URL for Bulk Post : /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags?bulk=true

Permissions: Object Manager > Modify Object Manager

## GET vlantags

Request Type: **GET**

Description: Retrieves the vlantag objects associated with the specified ID. If no ID is specified, retrieves list of all vlantag objects.

URL for listing: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags

URL for all the overrides on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags?overrideTargetId={target\_UUID}

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{object\_UUID}

URL to list all overrides on a particular object:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{vlantag\_UUID}/overrides

URL for override for an object on a particular domain or device:

/api/fmc\_config/v1/domain/{domain\_UUID}/object/vlantags/{vlantag\_UUID}?overrideTargetId={target\_UUID}

Permissions: Object Manager

## Policy Services

### DELETE accesspolicies

Request Type: **DELETE**

Description: Deletes the access control policy with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{object\_UUID}

Permissions: Policies>Access Control Policy>Modify Access Control Policy

### PUT accesspolicies

Request Type: **PUT**

Description: Modifies an access control policy.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/accesspolicies/{object\_UUID}

Permissions: Policies>Access Control Policy>Modify Access Control Policy

### POST accesspolicies

Request Type: **POST**

Description: Creates an access control policy with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies`

Permissions: Policies>Access Control Policy>Modify Access Control Policy

## GET accesspolicies

Request Type: **GET**

Description: Retrieves the access control policy associated with the specified ID. If no ID is specified, retrieves a list of all access control policies.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{object_UUID}`

Permissions: Policies

## DELETE accessrules

Request Type: **DELETE**

Description: Deletes an access control rule in the specified access control policy.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/accessrules/{object_UUID}`

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

## PUT accessrules

Request Type: **PUT**

Description: Modifies an access control rule in the specified access control policy.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/accessrules/{object_UUID}`

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

## POST accessrules

Request Type: **POST**

Description: Creates an access control rule in the specified access control policy.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/accessrules`

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

## GET accessrules

Request Type: **GET**

Description: Retrieves the access control rule associated with the specified policy ID and rule ID. If no rule ID is specified, retrieves list of all access rules associated with the specified policy ID.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/accessrules
```

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/accessrules/{object_UUID}
```

Permissions: Policies>Access Control>Access Control Policy

## PUT defaultactions

Request Type: **PUT**

Description: Modifies the default action associated with the specified access control policy ID and default action ID.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/defaultactions/{object_UUID}
```

Permissions: Policies>Access Control>Access Control Policy>Modify Access Control Policy

## GET defaultactions

Request Type: **GET**

Description: Retrieves the default action associated with the specified access control policy ID and default action ID. If no default action ID is specified, retrieves list of all default actions associated with the specified access control policy ID.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/defaultactions
```

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/accesspolicies/{container_UUID}/defaultactions/{object_UUID}
```

Permissions: Policies>Access Control>Access Control Policy

## GET loggingsettings

Request Type: **GET**

Description: Retrieves the logging setting associated with the specified access control policy ID and default action ID. If no default action ID is specified, retrieves list of all default actions associated with the specified access control policy ID.

URL:

```
/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/loggingsettings
```

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/loggingsettings/{object_UUID}
```

Permissions: Policies

## PUT loggingsettings

Request Type: **PUT**

Description: Modifies the logging setting associated with the specified access control policy ID and default action ID.

URL:

`/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/loggingsettings/{objectId}`

Permissions: Policies>Access Control Policy>Modify Access Control Policy

## GET filepolicies

Request Type: **GET**

Description: Retrieves the file policy object associated with the specified ID. If no ID is specified, retrieves list of all file policy objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/filepolicies`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/policy/filepolicies/{object_UUID}`

Permissions: Policies>Access Control>Malware & File Policy

## DELETE ftdnatpolicies

Request Type: **DELETE**

Description: Deletes the Firepower Threat Defense NAT policy with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{object_UUID}`

Permissions: Devices>NAT>NAT List >Modify NAT policy

## PUT ftdnatpolicies

Request Type: **PUT**

Description: Modifies an Firepower Threat Defense NAT policy with the specified ID.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{object_UUID}`

Permissions: Devices>NAT>NAT List >Modify NAT policy

## POST ftdnatpolicies

Request Type: **POST**

Description: Creates a Firepower Threat Defense device NAT policy with the specified parameters.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies`

Permissions: Devices>NAT>NAT List >Modify NAT policy

## GET ftdnatpolicies

Request Type: **GET**

Description: Retrieves the Firepower Threat Defense NAT policy associated with the specified ID. If no ID is specified, retrieves a list of all Firepower Threat Defense NAT policies.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies/{object\_UUID}

Permissions: Devices>NAT>NAT List

## DELETE ftds2svpns

Request Type: **DELETE**

Description: Deletes the Firepower Threat Defense Site to Site VPN topology associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpns/{topology\_UUID}

Permissions: Devices > VPN > Modify VPN

## PUT ftds2svpns

Request Type: **PUT**

Description: Modifies a Firepower Threat Defense Site to Site VPN topology associated with the specified ID.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpns/{topology\_UUID}

Permissions: Devices > VPN > Modify VPN

## POST ftds2svpns

Request Type: **POST**

Description: Creates a Firepower Threat Defense Site to Site VPN topology with the specified parameters.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpns

Permissions: Devices > VPN > Modify VPN

## GET ftds2svpns

Request Type: **GET**

Description: Retrieves the Firepower Threat Defense Site to Site VPN topology associated with the specified ID. If no ID is specified, retrieves a list of all Firepower Threat Defense Site to Site VPN topologies.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpns

URL for GET by ID: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpns/{topology\_UUID}

Permissions: Devices > VPN

## PUT advancedsettings

Request Type: **PUT**

Description: Modifies advanced settings inside a VPN Site to Site Topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpn/{topology_UUID}/advancedsettings/{advancedsetting_UUID}`

Permissions: Devices > VPN > Modify VPN

## GET advancedsettings

Request Type: **GET**

Description: Retrieves an advanced settings inside a VPN Site to Site Topology. If no ID is specified for a GET, retrieves list containing a single AdvancedSettings entry of the topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpn/{topology_UUID}/advancedsettings`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpn/{topology_UUID}/advancedsettings/{advancedSetting_UUID}`

Permissions: Devices > VPN

## DELETE endpoints

Request Type: **DELETE**

Description: Deletes all endpoints in a topology or a specific endpoint associated with the specified ID inside a VPN Site to Site Topology.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpn/{topology_UUID}/endpoints/{endpoint_UUID}`

Permissions: Devices > VPN > Modify VPN

## PUT endpoints

Request Type: **PUT**

Description: Modifies all endpoints in a topology or a specific endpoint associated with the specified ID inside a VPN Site to Site Topology.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpn/{topology_UUID}/endpoints/{endpoint_UUID}`

Permissions: Devices > VPN > Modify VPN

## POST endpoints

Request Type: **POST**

Description: Creates all endpoints in a topology or a specific endpoint associated with the specified ID inside a VPN Site to Site Topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/endpoints`

Permissions: Devices > VPN > Modify VPN

## GET endpoints

Request Type: **GET**

Description: Retrieves all endpoints in a topology or a specific endpoint associated with the specified ID inside a VPN Site to Site Topology. If no ID is specified for a GET, retrieves list of all Endpoints of a topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/endpoints`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/endpoints/{endpoint_UUID}`

Permissions: Devices > VPN

## PUT ikesettings

Request Type: **PUT**

Description: Modifies the IKE Settings associated with the specified ID inside a VPN Site to Site Topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/ikesettings/{ikesetting_UUID}`

Permissions: Devices > VPN > Modify VPN

## GET ikesettings

Request Type: **GET**

Description: Retrieves the IKE Settings associated with the specified ID inside a VPN Site to Site Topology. If no ID is specified for a GET, retrieves IKE Settings of a topology.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/ikesettings`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/ikesettings/{ikesetting_UUID}`

Permissions: Devices > VPN

## PUT ipsecsettings

Request Type: **PUT**

Description: Modifies an IPsec Proposal settings inside a VPN Site to Site Topology.

URL:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/ftds2svpns/{topology_UUID}/ipsecsettings/{ipsecsetting_UUID}`

Permissions: Devices > VPN > Modify VPN

## GET ipsecsettings

Request Type: **GET**

Description: Retrieves an IPsec Proposal Settings inside a VPN Site To Site Topology. If no ID is specified for a GET, retrieves list containing a single IPsec Settings entry of the topology.

URL: /api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftds2svpn/{topology\_UUID}/ipsecsettings

URL for GET by ID: /api/fmc\_config/v1/domain/DomainUUID/policy/ftds2svpn/{topology\_UUID}/ipsecsettings/{ipsecsetting\_UUID}

Permissions: Devices > VPN

## DELETE autonatrules

Request Type: **DELETE**

Description: Deletes a NAT rule with the specified parameters.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies/{container\_UUID}/autonatrules/{object\_UUID}

Permissions: Devices>NAT>NAT List >Modify NAT policy

## PUT autonatrules

Request Type: **PUT**

Description: Modifies a NAT rule with the specified parameters.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies/{container\_UUID}/autonatrules/{autonatrule\_UUID}

Permissions: Devices>NAT>NAT List >Modify NAT policy

## POST autonatrules

Request Type: **POST**

Description: Creates a NAT policy with the specified parameters.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies/{container\_UUID}/autonatrules

Permissions: Devices>NAT>NAT List >Modify NAT policy

## GET autonatrules

Request Type: **GET**

Description: Retrieves the NAT rule associated with the specific ID. If no ID is specified, retrieves a list of all NAT rules.

URL:

/api/fmc\_config/v1/domain/{domain\_UUID}/policy/ftdnatpolicies/{container\_UUID}/autonatrules

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/autonatrules/{object_UUID}
```

Permissions: Devices>NAT>NAT List

## DELETE manualnatrules

Request Type: **POST**

Description: Deletes a manual NAT rule in the specified NAT policy.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/manualnatrules/{object_UUID}
```

Permissions: Devices>NAT>NAT List >Modify NAT policy

## PUT manualnatrules

Request Type: **PUT**

Description: Modify a manual NAT rule in the specified NAT policy.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/manualnatrules/{object_UUID}
```

Permissions: Devices>NAT>NAT List >Modify NAT policy

## POST manualnatrules

Request Type: **POST**

Description: Creates manual NAT rules with the specified parameters.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/manualnatrules
```

Permissions: Devices>NAT>NAT List >Modify NAT policy

## GET manualnatrules

Request Type: **GET**

Description: Retrieves the manual NAT rule associated with the specified ID. If no ID is specified, retrieves a list of all manual NAT rules.

URL:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/manualnatrules
```

URL for GET by ID:

```
/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/manualnatrules/{object_UUID}
```

Permissions: Devices>NAT>NAT List

## GET natrules

Request Type: **GET**

Description: Retrieves the list of all NAT rules (manual and auto) associated with the specified NAT policy.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/ftdnatpolicies/{container_UUID}/natrules`

Permissions: Devices>NAT>NAT List

## GET intrusionpolicies

Request Type: **GET**

Description: Retrieves the intrusion policy associated with the specified ID. If no ID is specified, retrieves list of all intrusion policies.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/intrusionpolicies`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/policy/intrusionpolicies/{object_UUID}`

Permissions: Policies>Access Control>Intrusion Policy

## GET prefilterpolicies

Request Type: **GET**

Description: Retrieves the prefilter policy associated with the specified ID. If no ID is specified, retrieves a list of all prefilter policies.

URL: `/api/fmc_config/v1/domain/{domainUUID}/policy/prefilterpolicies`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domainUUID}/policy/prefilterpolicies/{object_UUID}`

Permissions: Policies > Access Control > Prefilter Policy

## DELETE hitcounts

Request Type: **DELETE**

Description: Deletes the hit count information and resets the hit count to zero for an assigned policy or rule in a device, from the Firepower Management Center.

Note that the DELETE operation returns a 200 (OK) message upon successful completion of the operation.

URLs:

- `/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`
- `/api/fmc_config/v1/domain/{domainUUID}/policy/prefilterpolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`

Permissions:

- Policies>Access Control Policy>Modify Access Control Policy
- Policies>Prefilter Policy>Modify Prefilter Policy

## PUT hitcounts

Request Type: **PUT**

Description: Retrieves the latest hit count information for a device against an assigned policy, and stores it in the Firepower Management Center.

URLs:

- `/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`
- `/api/fmc_config/v1/domain/{domainUUID}/policy/prefilterpolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`

Permissions:

- Policies>Access Control Policy>Modify Access Control Policy
- Policies>Prefilter Policy>Modify Prefilter Policy

## GET hitcounts

Request Type: **GET**

Description: Retrieves the last collected hit count information for a device against an assigned policy or its rules, from the Firepower Management Center.

Note that during the GET operation, hit counts will be automatically pre-fetched from the device if it is the first retrieval being done against a specific device.

URLs:

- `/api/fmc_config/v1/domain/{domainUUID}/policy/accesspolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`
- `/api/fmc_config/v1/domain/{domainUUID}/policy/prefilterpolicies/{containerUUID}/operational/hitcounts?filter="{filterString}"`

Permissions:

- Policies>Access Control Policy>Modify Access Control Policy
- Policies>Prefilter Policy>Modify Prefilter Policy

## GET snmpalerts

Request Type: **GET**

Description: Retrieves the SNMP alert object associated with the specified ID. If no ID is specified, retrieves a list of all SNMP alert objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/snmpalerts`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/policy/snmpalerts/{object_UUID}`

Permissions: Policies > Actions > Alerts > View Alerts

## GET syslogalerts

Request Type: **GET**

Description: Retrieves the syslog alert object associated with the specified ID. If no ID is specified, retrieves a list of all syslog alert objects.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/policy/syslogalerts`

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/policy/syslogalerts/{object_UUID}`

Permissions: Policies > Actions > Alerts

## Policy Assignment Services

### PUT policyassignments

Request Type: **PUT**

Description: Modifies an assigned access policy to add a new device or a new device group.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/assignment/policyassignments/{object_UUID}`

Permissions:

### POST policyassignments

Request Type: **POST**

Description: Assigns an unassigned access policy to devices or device groups.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/assignment/policyassignments`

Permissions:

### GET policyassignments

Request Type: **GET**

Description: Retrieves the policy assignment associated with the specified ID. If no ID is specified, retrieves a list of all policy assignments to target devices.

URL: `/api/fmc_config/v1/domain/{domain_UUID}/assignment/policyassignments`

URL for GET by ID:

`/api/fmc_config/v1/domain/{domain_UUID}/assignment/policyassignments/{object_UUID}`

Permissions:

Parameters available for filtering: name

# Status Services

## GET taskstatuses

Description: Retrieves information about a previously submitted pending job/task with the specified ID. This is currently supported for device registration and deployment jobs.

URL for GET by ID: `/api/fmc_config/v1/domain/{domain_UUID}/job/taskstatuses/{object_UUID}`

Permissions: Modify Devices/Deployment

# System Information

## GET serverversion

Request Type: **GET**

Description: Requests version information for the server. If no ID is specified, retrieves a list of all servers.

URL: `/api/fmc_platform/v1/info/serverversion`

URL for GET by ID: `/api/fmc_platform/v1/info/serverversion/{objectID}`

Permissions:

# Update Packages

## DELETE upgradepackages

Request Type: **DELETE**

Description: Deletes a specific Firepower Threat Defense upgrade package from the managing Firepower Management Center.

URL: `/api/fmc_platform/v1/updates/upgradepackages/{package_UUID}`

## GET upgradepackages

Request Type: **GET**

Description: Retrieves a list of locally available Firepower Threat Defense upgrade packages, including major upgrades, maintenances release upgrades, and hotfixes.

URL: `/api/fmc_platform/v1/updates/upgradepackages`

URL for GET by ID: `/api/fmc_platform/v1/updates/upgradepackages/{package_UUID}`

## GET listapplicabledevices

Request Type: **GET**

Description: Lists registered device containers that support the specific upgrade package.

URL: `/api/fmc_platform/v1/updates/upgradepackages/{container_UUID}/applicabledevices`

## POST upgradepackage

Request Type: **POST**

Description: Dependent on the parameters, this POST operation either pushes available software upgrade packages to applicable devices running Firepower Threat Defense or initiates the upgrade process for applicable devices running Firepower Threat Defense. This process is applicable for standalone, clustered, or high availability pairs with the following limitations:

- For all configurations, ensure that the current POST operation is completed successfully before proceeding to the next POST operation.
- Perform the POST operation on the primary node of a high availability pair. Do not perform the POST operation for more than one high availability pair at a time.
- Perform the POST operation on the



### Note

Typically, the first POST operation responds within 60 seconds. Cisco recommends that you perform subsequent POST operations at least 120 seconds after the first POST operation was initiated. The response of the POST operation includes a task object, with a task ID and task status. You can monitor the completion of the task by performing a GET operation on the task object with its task ID. For more information, see [GET taskstatuses, on page 81](#).

URL: `/api/fmc_platform/v1/updates/upgrades/`

## GET upgradepackages: Monitor

Request Type: **GET**

Description: Monitors the upgrade process once you have executed the POST upgrade task.

URL: `/api/fmc_platform/v1/domain/{domain_UUID}/job/taskstatuses/{task_ID}`