



O Commands

This chapter describes the Cisco Nexus 1000V commands that begin with the letter O.

option exporter-stats timeout

To specify a timeout period for resending NetFlow flow exporter data, use the **option exporter-stats timeout** command. To remove the timeout period, use the **no** form of this command.

option exporter-stats timeout *time*

no option exporter-stats timeout

Syntax Description

| | |
|-------------|--|
| <i>time</i> | A time period between 1 and 86400 seconds. |
|-------------|--|

Defaults

None

Command Modes

Netflow flow exporter version 9 configuration (**config-flow-exporter-version-9**)

Supported User Roles

network-admin

Command History

| Release | Modification |
|--------------|------------------------------|
| 4.0(4)SV1(1) | This command was introduced. |

Examples

This example shows how to configure a 3600-second timeout period for resending NetFlow flow exporter data:

```
n1000v# config t
n1000v(config)# flow exporter ExportTest
n1000v(config-flow-exporter)# version 9
n1000v(config-flow-exporter-version-9)# option exporter-stats timeout 3600
```

Send document comments to nexus1k-docfeedback@cisco.com.

This example shows how to remove the timeout period for resending NetFlow flow exporter data:

```
n1000v# config t
n1000v(config)# flow exporter ExportTest
n1000v(config-flow-exporter)# version 9
n1000v(config-flow-exporter-version-9)# no option exporter-stats timeout
n1000v(config-flow-exporter)#
```

Related Commands

| Command | Description |
|---------------------------------------|---|
| version 9 | Designates NetFlow export version 9 in the NetFlow exporter. |
| option interface-table timeout | Specifies a timeout period for resending the NetFlow flow exporter interface table. |
| template data timeout | Specifies a timeout period for resending NetFlow flow exporter template data. |
| flow exporter | Creates a Flexible NetFlow flow exporter. |
| flow record | Creates a Flexible NetFlow flow record. |
| flow monitor | Creates a Flexible NetFlow flow monitor. |
| show flow exporter | Displays information about the NetFlow flow exporter. |
| show flow record | Displays information about NetFlow flow records. |
| show flow monitor | Displays information about the NetFlow flow monitor. |

[Send document comments to nexus1k-docfeedback@cisco.com.](mailto:nexus1k-docfeedback@cisco.com)

option interface-table timeout

To specify the timeout period for resending the NetFlow flow exporter interface table, use the **option interface-table timeout** command. To remove the timeout period, use the **no** form of this command.

option interface-table timeout *time*

no option interface-table timeout

| Syntax Description | <i>time</i> | A time period between 1 and 86400 seconds. |
|--------------------|-------------|--|
|--------------------|-------------|--|

| Defaults | None |
|----------|------|
|----------|------|

| Command Modes | Netflow flow exporter version 9 configuration (config-flow-exporter-version-9) |
|---------------|--|
|---------------|--|

| Supported User Roles | network-admin |
|----------------------|---------------|
|----------------------|---------------|

| Command History | Release | Modification |
|-----------------|--------------|------------------------------|
| | 4.0(4)SV1(1) | This command was introduced. |

Examples This example shows how to configure a 3600 second timeout period for resending the NetFlow flow exporter interface table:

```
n1000v# config t
n1000v(config)# flow exporter ExportTest
n1000v(config-flow-exporter)# version 9
n1000v(config-flow-exporter-version-9)# option exporter-stats timeout 3600
```

This example shows how to remove the timeout period for resending the NetFlow flow exporter interface table:

```
n1000v# config t
n1000v(config)# flow exporter ExportTest
n1000v(config-flow-exporter)# version 9
n1000v(config-flow-exporter-version-9)# no option exporter-stats timeout
n1000v(config-flow-exporter)#
```

| Related Commands | Command | Description |
|------------------|--------------------------------------|--|
| | version 9 | Designates NetFlow export version 9 in the NetFlow exporter. |
| | option exporter-stats timeout | Specifies a timeout period for resending NetFlow flow exporter data. |

Send document comments to nexus1k-docfeedback@cisco.com.

| Command | Description |
|------------------------------|---|
| template data timeout | Specifies a timeout period for resending NetFlow flow exporter template data. |
| flow exporter | Creates a Flexible NetFlow flow exporter. |
| flow record | Creates a Flexible NetFlow flow record. |
| flow monitor | Creates a Flexible NetFlow flow monitor. |
| show flow exporter | Displays information about the NetFlow flow exporter. |
| show flow record | Displays information about NetFlow flow records. |
| show flow monitor | Displays information about the NetFlow flow monitor. |