

# Cisco E メール セキュリティ アプライアンスで、特定のドメインまたはホストに配信レートの制限を設定するにはどうしますか。

## 目次

[はじめに](#)  
[解決策](#)

## 概要

この資料にある特定のドメインかホストにレートリミット配信にどのように記述されています。

## 解決策

CLI の *destconfig* コマンドか GUI のメール *Policies* タブの宛先管理テーブルは特定のドメインかホストに Cisco E メール セキュリティ アプライアンスで制限する配達レートを設定するのに使用することができます。このオプションがリモートホストを overloading 防ぐことを可能にすることは時々推奨されます。

方法の CLI 例はドメイン「example.com」にレート配信を制限する下記にあります。

```
mail.example.com> destconfig
There are currently 2 entries configured.
Choose the operation you want to perform:
- NEW - Create a new entry.
- EDIT - Modify an entry.
- DELETE - Remove an entry.
- DEFAULT - Change the default.
- PRINT - Display all entries.
- CLEAR - Remove all entries.
[ ]> new
Enter the domain you wish to limit.
[ ]> example.com
Do you wish to configure a concurrency limit for example.com? [Y]>
Enter the max concurrency limit for "example.com".
[500]> 100
Do you wish to apply a recipient limit to this domain? [N]> y
Enter the number of minutes used to measure the recipient limit.
[60]> 60
Enter the max number of recipients per 60 minutes for "example.com".
[ ]> 1000
Select how you want to apply the limits for example.com:
1. One limit applies to the entire domain example.com
```

2. Separate limit for each mail exchanger IP address

[1]>

Select how the limits will be enforced:

1. System Wide

2. Per Virtual Gateway(tm)

[1]>

Do you wish to apply a specific TLS setting for this domain? [N]>

Do you wish to apply a specific bounce verification address tagging setting for this domain?

[N]>

Do you wish to apply a specific bounce profile to this domain? [N]>

There are currently 3 entries configured

Choose the operation you want to perform:

- NEW - Create a new entry.

- EDIT - Modify an entry.

- DELETE - Remove an entry.

- DEFAULT - Change the default.

- PRINT - Display all entries.

- CLEAR - Remove all entries.

[ ]>

mail.example.com> commit