

Configurar el router a router, el Pre-shared del IPSec, sobrecarga NAT entre un soldado y una red pública

Contenido

[Introducción](#)

[prerrequisitos](#)

[Requisitos](#)

[Componentes Utilizados](#)

[Convenciones](#)

[Configurar](#)

[Diagrama de la red](#)

[Configuraciones](#)

[Verificación](#)

[Ejemplo de resultado del comando show](#)

[Troubleshooting](#)

[Comandos para resolución de problemas](#)

[Información Relacionada](#)

[Introducción](#)

Esta configuración de ejemplo muestra cómo cifrar el tráfico entre una red privada (10.103.1.x) y una red pública (98.98.98.x) con el uso de IPSec. La red 98.98.98.x conoce a la red 10.103.1.x por las direcciones privadas. La red 10.103.1.x conoce a la red 98.98.98.x por las direcciones públicas.

[prerrequisitos](#)

[Requisitos](#)

Este documento requiere una comprensión básica del protocolo IPSec Si desea más información sobre IPSec, consulte [Introducción al encriptación de seguridad IP \(IPSec\)](#).

[Componentes Utilizados](#)

La información que contiene este documento se basa en las siguientes versiones de software y hardware.

- Software Release 12.3(5) de Cisco IOS®
- Routers Cisco 3640

La información que contiene este documento se creó a partir de los dispositivos en un ambiente de laboratorio específico. Todos los dispositivos que se utilizan en este documento se pusieron en funcionamiento con una configuración verificada (predeterminada). Si la red está funcionando, asegúrese de haber comprendido el impacto que puede tener cualquier comando.

Convenciones

Para obtener más información sobre las convenciones del documento, consulte [Convenciones de Consejos Técnicos de Cisco](#).

Configurar

En esta sección encontrará la información para configurar las funciones descritas en este documento.

Nota: Para obtener información adicional sobre los comandos que se utilizan en este documento, use la Command Lookup Tool (solo para clientes [registrados](#)).

Diagrama de la red

Este documento utiliza la configuración de red que se muestra en el siguiente diagrama.

Configuraciones

En este documento, se utilizan estas configuraciones:

- [router "público" 3640-2b](#)
- [Router "privado" 3640-6a](#)

```
router "público" 3640-2b
rp-3640-2b#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-2b ! ip subnet-
zero ! ! !--- Defines the Internet Key Exchange (IKE)
policies. crypto isakmp policy 1 !--- Defines an IKE
policy. Use the crypto isakmp policy !--- command in
global configuration mode. IKE policies !--- define a
set of parameters !--- that are used during the IKE
phase I negotiation. hash md5 authentication pre-share
!--- Specifies preshared keys as the authentication
method. crypto isakmp key cisco123 address 95.95.95.2 !-
-- Configures a preshared authentication key, used in !-
-- global configuration mode. ! crypto ipsec transform-
set rtpset esp-des esp-md5-hmac !--- Defines a
transform-set. This is an acceptable !--- combination of
security protocols and algorithms, !--- which has to be
matched on the peer router. ! crypto map rtp 1 ipsec-
isakmp !--- Indicates that IKE is used to !--- establish
the IPSec security associations (SAs) that protect !---
the traffic specified by this crypto map entry. set peer
95.95.95.2 !--- Sets the IP address of the remote end.
set transform-set rtpset !--- Configures IPSec to use
the transform-set !--- "rtpset" defined earlier. match
```

```

address 115 !--- This is used to assign an extended
access list to a !--- crypto map entry which is used by
IPSec !--- to determine which traffic should be
protected !--- by crypto and which traffic does not !---
need crypto protection. ! interface Ethernet0/0 ip
address 98.98.98.1 255.255.255.0 no ip directed-
broadcast ! interface Ethernet0/1 ip address 99.99.99.2
255.255.255.0 no ip directed-broadcast no ip route-cache
!--- Enable process switching for !--- IPSec to encrypt
outgoing packets. !--- This command disables fast
switching. no ip mroute-cache crypto map rtp !---
Configures the interface to use !--- the crypto map
"rtp" for IPSec. ! . . !--- Output suppressed. . . ip
classless ip route 0.0.0.0 0.0.0.0 99.99.99.1 !---
Default route to the next hop address. no ip http server
! access-list 115 permit ip 98.98.98.0 0.0.0.255
10.103.1.0 0.0.0.255 !--- This access-list option causes
all IP traffic !--- that matches the specified
conditions to be !--- protected by IPSec using the
policy described by !--- the corresponding crypto map
command statements. access-list 115 deny ip 98.98.98.0
0.0.0.255 any ! line con 0 transport input none line aux
0 line vty 0 4 login ! end

```

Router "privado" 3640-6a

```

rp-3640-6a#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-6a ! ! ip subnet-
zero !--- Defines the IKE policies. ! crypto isakmp
policy 1 !--- Defines an IKE policy. !--- Use the crypto
isakmp policy !--- command in global configuration mode.
IKE policies !--- define a set of parameters !--- that
are used during the IKE phase I negotiation. hash md5
authentication pre-share !--- Specifies preshared keys
as the authentication method. crypto isakmp key cisco123
address 99.99.99.2 !--- Configures a preshared
authentication key, !--- used in global configuration
mode. ! crypto ipsec transform-set rtpset esp-des esp-
md5-hmac !--- Defines a transform-set. This is an !---
acceptable combination of security protocols and
algorithms, !--- which has to be matched on the peer
router. crypto map rtp 1 ipsec-isakmp !--- Indicates
that IKE is used to establish !--- the IPSec SAs that
protect the traffic !--- specified by this crypto map
entry. set peer 99.99.99.2 !--- Sets the IP address of
the remote end. set transform-set rtpset !--- Configures
IPSec to use the transform-set !--- "rtpset" defined
earlier. match address 115 !--- Used to assign an
extended access list to a !--- crypto map entry which is
used by IPSec !--- to determine which traffic should be
protected !--- by crypto and which traffic does not !---
need crypto protection. . . !--- Output suppressed. . .
! interface Ethernet3/0 ip address 95.95.95.2
255.255.255.0 no ip directed-broadcast ip nat outside !-
- Indicates that the interface is !--- connected to the
outside network. no ip route-cache !--- Enable process
switching for !--- IPSec to encrypt outgoing packets. !-
- This command disables fast switching. no ip mroute-
cache crypto map rtp !--- Configures the interface to
use the !--- crypto map "rtp" for IPSec. ! interface
Ethernet3/2 ip address 10.103.1.75 255.255.255.0 no ip
directed-broadcast ip nat inside !--- Indicates that the
interface is connected to !--- the inside network (the

```

```

network subject to NAT translation). ! ip nat pool FE30
95.95.95.10 95.95.95.10 netmask 255.255.255.0 !--- Used
to define a pool of IP addresses for !--- NAT. Use the
ip nat pool command in !--- global configuration mode.
ip nat inside source route-map nonat pool FE30 overload
!--- Used to enable NAT of !--- the inside source
address. Use the ip nat inside source !--- command in
global configuration mode. !--- The 'overload' option
enables the router to use one global !--- address for
many local addresses. ip classless ip route 0.0.0.0
0.0.0.0 95.95.95.1 !--- Default route to the next hop
address. no ip http server ! access-list 110 deny ip
10.103.1.0 0.0.0.255 98.98.98.0 0.0.0.255 access-list
110 permit ip 10.103.1.0 0.0.0.255 any !--- Addresses
that match this ACL are NATed while !--- they access the
Internet. They are not NATed !--- if they access the
98.98.98.0 network. access-list 115 permit ip 10.103.1.0
0.0.0.255 98.98.98.0 0.0.0.255 !--- This access-list
option causes all IP traffic that !--- matches the
specified conditions to be !--- protected by IPsec using
the policy described !--- by the corresponding crypto
map command statements. access-list 115 deny ip
10.103.1.0 0.0.0.255 any route-map nonat permit 10 match
ip address 110 !! line con 0 line vty 0 4 ! end

```

Verificación

En esta sección encontrará información que puede utilizar para confirmar que su configuración esté funcionando correctamente.

La herramienta [Output Interpreter](#) (sólo para clientes [registrados](#)) permite utilizar algunos comandos “show” y ver un análisis del resultado de estos comandos.

Para verificar esta configuración, intente un comando extended ping originado de la interfaz de Ethernet en el router privado 10.103.1.75, destinado a la interfaz de Ethernet en el router público 98.98.98.1

- [ping](#) — Se utiliza para diagnosticar la conectividad básica de la red. `rp-3640-6a#ping Protocol [ip]: Target IP address: 98.98.98.1 Repeat count [5]: Datagram size [100]: Timeout in seconds [2]: Extended commands [n]: y Source address or interface: 10.103.1.75 Type of service [0]: Set DF bit in IP header? [no]: Validate reply data? [no]: Data pattern [0xABCD]: Loose, Strict, Record, Timestamp, Verbose[none]: Sweep range of sizes [n]: Type escape sequence to abort. Sending 5, 100-byte ICMP Echos to 98.98.98.1, timeout is 2 seconds: !!!!! Success rate is 100 percent (5/5), round-trip min/avg/max = 64/64/68 ms`
- [muestre IPsec crypto sa](#) — Muestra las configuraciones usadas por (IPsec) los SA actuales.
- [show crypto isakmp sa](#) — Muestra todas las IKE SAs actuales en un par.
- [show crypto engine](#) — Muestra un resumen de la información de la configuración para los motores de criptografía. Utilice el comando `show crypto engine` en el modo EXEC privilegiado.

Ejemplo de resultado del comando show

Esta salida es del comando `show crypto ipsec sa` publicado en el router de eje de conexión.

```

rp-3640-6a#show crypto ipsec sa interface: Ethernet0/0 Crypto map tag: rtp, local addr.
95.95.95.2 protected vrf: local ident (addr/mask/prot/port): (10.103.1.0/255.255.255.0/0/0)

```

```
remote ident (addr/mask/prot/port): (98.98.98.0/255.255.255.0/0/0) current_peer: 99.99.99.2:500
PERMIT, flags={origin_is_acl,} #pkts encaps: 5, #pkts encrypt: 5, #pkts digest 5 #pkts decaps:
14, #pkts decrypt: 14, #pkts verify 14 #pkts compressed: 0, #pkts decompressed: 0 #pkts not
compressed: 0, #pkts compr. failed: 0 #pkts not decompressed: 0, #pkts decompress failed: 0
#send errors 0, #recv errors 0 local crypto endpt.: 95.95.95.2, remote crypto endpt.: 99.99.99.2
path mtu 1500, media mtu 1500 current outbound spi: 75B6D4D7 inbound esp sas: spi:
0x71E709E8(1910966760) transform: esp-des esp-md5-hmac , in use settings ={Tunnel, } slot: 0,
conn id: 2000, flow_id: 1, crypto map: rtp sa timing: remaining key lifetime (k/sec):
(4576308/3300) IV size: 8 bytes replay detection support: Y inbound ah sas: inbound pcp sas:
outbound esp sas: spi: 0x75B6D4D7(1974916311) transform: esp-des esp-md5-hmac , in use settings
={Tunnel, } slot: 0, conn id: 2001, flow_id: 2, crypto map: rtp sa timing: remaining key
lifetime (k/sec): (4576310/3300) IV size: 8 bytes replay detection support: Y outbound ah sas:
outbound pcp sas:
```

Este comando muestra las SA IPsec generadas entre peers. El túnel encriptado se construye entre 95.95.95.2 y 99.99.99.2 para el tráfico que va entre las redes 98.98.98.0 y 10.103.1.0. Puede ver las dos SA de carga de seguridad de encapsulación (ESP) generadas en sentido entrante y saliente. El Encabezado de autenticación SA no se utiliza puesto que no hay AH.

[Troubleshooting](#)

En esta sección encontrará información que puede utilizar para solucionar problemas de configuración.

[Comandos para resolución de problemas](#)

La herramienta [Output Interpreter](#) (sólo para clientes [registrados](#)) permite utilizar algunos comandos “show” y ver un análisis del resultado de estos comandos.

Nota: Antes de ejecutar un comando debug, consulte [Información Importante sobre Comandos Debug](#).

- **debug crypto ipsec sa** — Utilizado para ver los IPsec Negotiations de la fase 2.
- **debug crypto isakmp sa** — Utilizado para ver negociaciones ISAKMP de la fase 1.
- **motor del debug crypto** — Utilizado para visualizar a las sesiones encriptadas.

[Información Relacionada](#)

- [Orden de Funcionamiento de NAT](#)
- [Resolución de problemas de seguridad de IP – Información y uso de los comandos de depuración](#)
- [Página de soporte de IPsec](#)
- [Página de Soporte de NAT](#)
- [Soporte Técnico - Cisco Systems](#)