

# プライベート ネットワークとパブリック ネットワーク間の IPSec ルータ相互間、事前共有、NAT オーバーロードの設定

## 目次

[概要](#)

[前提条件](#)

[要件](#)

[使用するコンポーネント](#)

[表記法](#)

[設定](#)

[ネットワーク図](#)

[設定](#)

[確認](#)

[show コマンドの出力例](#)

[トラブルシューティング](#)

[トラブルシューティングのためのコマンド](#)

[関連情報](#)

## 概要

ここでは、IPSec を使用して、プライベート ネットワーク ( 10.103.1.x ) とパブリック ネットワーク ( 98.98.98.x ) 間のトラフィックを暗号化する場合の設定例を紹介します。98.98.98.x ネットワークは、プライベートアドレスにより10.103.1.xネットワークを認識します。10.103.1.x ネットワークは、パブリックアドレスにより98.98.98.xネットワークを認識します。

## 前提条件

### 要件

このドキュメントの内容は、IPsec プロトコルに関する基本的知識が前提となっています。IPSec の詳細については、『[IP Security \( IPSec \) 暗号化の概要](#)』を参照してください。

### 使用するコンポーネント

このドキュメントの情報は、次のソフトウェアとハードウェアのバージョンに基づくものです。

- Cisco IOS® ソフトウェア リリース 12.3(5)
- Cisco 3640ルータ

このドキュメントの情報は、特定のラボ環境にあるデバイスに基づいて作成されたものです。こ

のドキュメントで使用するすべてのデバイスは、クリアな ( デフォルト ) 設定で作業を開始しています。 ネットワークが稼働中の場合は、コマンドが及ぼす潜在的な影響を十分に理解しておく必要があります。

## 表記法

ドキュメント表記の詳細は、『[シスコ テクニカル ティップスの表記法](#)』を参照してください。

## 設定

この項では、このドキュメントで説明する機能の設定に必要な情報を提供します。

注: このドキュメントで使用されているコマンドの詳細を調べるには、[Command Lookup Tool](#) ( [登録ユーザ専用](#) ) を使用してください。

## ネットワーク図

このドキュメントでは、次の図で示されるネットワーク構成を使用しています。

## 設定

このドキュメントでは、次の設定を使用します。

- [3640-2b 「公共」ルータ](#)
- [3640-6a "プライベート"ルータ](#)

### 3640-2b 「公共」ルータ

```
rp-3640-2b#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-2b ! ip subnet-
zero ! ! --- Defines the Internet Key Exchange (IKE)
policies. crypto isakmp policy 1 ! --- Defines an IKE
policy. Use the crypto isakmp policy ! --- command in
global configuration mode. IKE policies ! --- define a
set of parameters ! --- that are used during the IKE
phase I negotiation. hash md5 authentication pre-share
! --- Specifies preshared keys as the authentication
method. crypto isakmp key cisco123 address 95.95.95.2 !-
- Configures a preshared authentication key, used in !-
- global configuration mode. ! crypto ipsec transform-
set rtpset esp-des esp-md5-hmac ! --- Defines a
transform-set. This is an acceptable ! --- combination of
security protocols and algorithms, ! --- which has to be
matched on the peer router. ! crypto map rtp 1 ipsec-
isakmp ! --- Indicates that IKE is used to ! --- establish
the IPSec security associations (SAs) that protect ! ---
the traffic specified by this crypto map entry. set peer
95.95.95.2 ! --- Sets the IP address of the remote end.
set transform-set rtpset ! --- Configures IPSec to use
the transform-set ! --- "rtpset" defined earlier. match
address 115 ! --- This is used to assign an extended
access list to a ! --- crypto map entry which is used by
IPSec ! --- to determine which traffic should be
```

```

protected !--- by crypto and which traffic does not !---
need crypto protection. ! interface Ethernet0/0 ip
address 98.98.98.1 255.255.255.0 no ip directed-
broadcast ! interface Ethernet0/1 ip address 99.99.99.2
255.255.255.0 no ip directed-broadcast no ip route-cache
!--- Enable process switching for !--- IPsec to encrypt
outgoing packets. !--- This command disables fast
switching. no ip mroute-cache crypto map rtp !---
Configures the interface to use !--- the crypto map
"rtp" for IPsec. ! . . !--- Output suppressed. . . ip
classless ip route 0.0.0.0 0.0.0.0 99.99.99.1 !---
Default route to the next hop address. no ip http server
! access-list 115 permit ip 98.98.98.0 0.0.0.255
10.103.1.0 0.0.0.255 !--- This access-list option causes
all IP traffic !--- that matches the specified
conditions to be !--- protected by IPsec using the
policy described by !--- the corresponding crypto map
command statements. access-list 115 deny ip 98.98.98.0
0.0.0.255 any ! line con 0 transport input none line aux
0 line vty 0 4 login ! end

```

### 3640-6a "プライベート"ルータ

```

rp-3640-6a#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-6a ! ! ip subnet-
zero !--- Defines the IKE policies. ! crypto isakmp
policy 1 !--- Defines an IKE policy. !--- Use the crypto
isakmp policy !--- command in global configuration mode.
IKE policies !--- define a set of parameters !--- that
are used during the IKE phase I negotiation. hash md5
authentication pre-share !--- Specifies preshared keys
as the authentication method. crypto isakmp key cisco123
address 99.99.99.2 !--- Configures a preshared
authentication key, !--- used in global configuration
mode. ! crypto ipsec transform-set rtpset esp-des esp-
md5-hmac !--- Defines a transform-set. This is an !---
acceptable combination of security protocols and
algorithms, !--- which has to be matched on the peer
router. crypto map rtp 1 ipsec-isakmp !--- Indicates
that IKE is used to establish !--- the IPsec SAs that
protect the traffic !--- specified by this crypto map
entry. set peer 99.99.99.2 !--- Sets the IP address of
the remote end. set transform-set rtpset !--- Configures
IPsec to use the transform-set !--- "rtpset" defined
earlier. match address 115 !--- Used to assign an
extended access list to a !--- crypto map entry which is
used by IPsec !--- to determine which traffic should be
protected !--- by crypto and which traffic does not !---
need crypto protection. . . !--- Output suppressed. . .
! interface Ethernet3/0 ip address 95.95.95.2
255.255.255.0 no ip directed-broadcast ip nat outside !-
- Indicates that the interface is !--- connected to the
outside network. no ip route-cache !--- Enable process
switching for !--- IPsec to encrypt outgoing packets. !-
- This command disables fast switching. no ip mroute-
cache crypto map rtp !--- Configures the interface to
use the !--- crypto map "rtp" for IPsec. ! interface
Ethernet3/2 ip address 10.103.1.75 255.255.255.0 no ip
directed-broadcast ip nat inside !--- Indicates that the
interface is connected to !--- the inside network (the
network subject to NAT translation). ! ip nat pool FE30
95.95.95.10 95.95.95.10 netmask 255.255.255.0 !--- Used
to define a pool of IP addresses for !--- NAT. Use the

```

```
ip nat pool command in !--- global configuration mode.
ip nat inside source route-map nonat pool FE30 overload
!--- Used to enable NAT of !--- the inside source
address. Use the ip nat inside source !--- command in
global configuration mode. !--- The 'overload' option
enables the router to use one global !--- address for
many local addresses. ip classless ip route 0.0.0.0
0.0.0.0 95.95.95.1 !--- Default route to the next hop
address. no ip http server ! access-list 110 deny ip
10.103.1.0 0.0.0.255 98.98.98.0 0.0.0.255 access-list
110 permit ip 10.103.1.0 0.0.0.255 any !--- Addresses
that match this ACL are NATed while !--- they access the
Internet. They are not NATed !--- if they access the
98.98.98.0 network. access-list 115 permit ip 10.103.1.0
0.0.0.255 98.98.98.0 0.0.0.255 !--- This access-list
option causes all IP traffic that !--- matches the
specified conditions to be !--- protected by IPsec using
the policy described !--- by the corresponding crypto
map command statements. access-list 115 deny ip
10.103.1.0 0.0.0.255 any route-map nonat permit 10 match
ip address 110 !! line con 0 line vty 0 4 ! end
```

## 確認

このセクションでは、設定が正常に動作しているかどうかを確認する際に役立つ情報を提供しています。

特定の **show** コマンドは、[Output Interpreter Tool](#) ( [登録ユーザ専用](#) ) によってサポートされています。このツールを使用すると、**show** コマンド出力の分析を表示できます。

この設定を確認するために、公共ルータ 98.98.98.1 でイーサネットインターフェイスに向かう私用ルータ 10.103.1.75 でイーサネットインターフェイスからソースをたどられる拡張pingコマンドを試して下さい

- [ping : 基本的なネットワークの接続性を診断するのに使用します。](#) rp-3640-6a#ping Protocol [ip]: Target IP address: 98.98.98.1 Repeat count [5]: Datagram size [100]: Timeout in seconds [2]: Extended commands [n]: y Source address or interface: 10.103.1.75 Type of service [0]: Set DF bit in IP header? [no]: Validate reply data? [no]: Data pattern [0xABCD]: Loose, Strict, Record, Timestamp, Verbose[none]: Sweep range of sizes [n]: Type escape sequence to abort. Sending 5, 100-byte ICMP Echos to 98.98.98.1, timeout is 2 seconds: !!!!! Success rate is 100 percent (5/5), round-trip min/avg/max = 64/64/68 ms
- [show crypto ipsec sa : 現在の \( IPsec \) SA で使用されている設定を表示します。](#)
- [show crypto isakmp sa : 現在ピアにあるすべての IKE SA を表示します。](#)
- [show crypto engine](#) —暗号化エンジンのための構成情報の要約を表示します。特権EXECモードで **show crypto engine** コマンドを使用して下さい。

## show コマンドの出力例

この出力は、ハブルータ上で発行された **show crypto ipsec sa** コマンドからのものです。

```
rp-3640-6a#show crypto ipsec sa interface: Ethernet0/0 Crypto map tag: rtp, local addr.
95.95.95.2 protected vrf: local ident (addr/mask/prot/port): (10.103.1.0/255.255.255.0/0/0)
remote ident (addr/mask/prot/port): (98.98.98.0/255.255.255.0/0/0) current_peer: 99.99.99.2:500
PERMIT, flags={origin_is_acl,} #pkts encaps: 5, #pkts encrypt: 5, #pkts digest 5 #pkts decaps:
14, #pkts decrypt: 14, #pkts verify 14 #pkts compressed: 0, #pkts decompressed: 0 #pkts not
compressed: 0, #pkts compr. failed: 0 #pkts not decompressed: 0, #pkts decompress failed: 0
```

```
#send errors 0, #recv errors 0 local crypto endpt.: 95.95.95.2, remote crypto endpt.: 99.99.99.2
path mtu 1500, media mtu 1500 current outbound spi: 75B6D4D7 inbound esp sas: spi:
0x71E709E8(1910966760) transform: esp-des esp-md5-hmac , in use settings ={Tunnel, } slot: 0,
conn id: 2000, flow_id: 1, crypto map: rtp sa timing: remaining key lifetime (k/sec):
(4576308/3300) IV size: 8 bytes replay detection support: Y inbound ah sas: inbound pcp sas:
outbound esp sas: spi: 0x75B6D4D7(1974916311) transform: esp-des esp-md5-hmac , in use settings
={Tunnel, } slot: 0, conn id: 2001, flow_id: 2, crypto map: rtp sa timing: remaining key
lifetime (k/sec): (4576310/3300) IV size: 8 bytes replay detection support: Y outbound ah sas:
outbound pcp sas:
```

このコマンドは、ピア間で構築された IPsec SA を表示します。ネットワーク 98.98.98.0 および 10.103.1.0 の間で行く暗号化されたトンネルはトラフィックのための 95.95.95.2 と 99.99.99.2 の間で構築されます。着信側および発信側で構築された 2 つの Encapsulating Security Payload ( ESP ) SA を確認できます。AH がないので Authentication Header ( AH ) SA は使用されません。

## [トラブルシューティング](#)

ここでは、設定のトラブルシューティングに役立つ情報について説明します。

### [トラブルシューティングのためのコマンド](#)

特定の show コマンドは、[Output Interpreter Tool](#) ( [登録ユーザ専用](#) ) によってサポートされています。このツールを使用すると、show コマンド出力の分析を表示できます。

注: debug コマンドを使用する前に、『[debug コマンドに関する重要な情報](#)』を参照してください。

- debug crypto ipsec sa —フェーズ2 の IPsec ネゴシエーションを見るのに使用しました。
- debug crypto isakmp sa —フェーズ1 の ISAKMP ネゴシエーションを見るのに使用しました。
- debug crypto engine — 暗号化されたセッションを表示するのに使用しました。

## [関連情報](#)

- [NAT の処理順序](#)
- [IP Security のトラブルシューティング : debug コマンドの説明と使用](#)
- [IPsec に関するサポート ページ](#)
- [NAT に関するサポートページ](#)
- [テクニカルサポート - Cisco Systems](#)