

Configurando o roteador para roteador, o Pre-shared do IPsec, sobrecarga NAT entre um privado e uma rede pública

Índice

[Introdução](#)

[Pré-requisitos](#)

[Requisitos](#)

[Componentes Utilizados](#)

[Convenções](#)

[Configurar](#)

[Diagrama de Rede](#)

[Configurações](#)

[Verificar](#)

[Exemplo de saída de show](#)

[Troubleshooting](#)

[Comandos para Troubleshooting](#)

[Informações Relacionadas](#)

[Introdução](#)

Esta configuração de exemplo mostra como criptografar o tráfego entre uma rede privada (10.103.1.x) e uma rede pública (98.98.98.x) com o uso de IPsec. A rede 98.98.98.x conhece a rede 10.103.1.x pelos endereços particulares. A rede 10.103.1.x conhece a rede 98.98.98.x via endereços públicos.

[Pré-requisitos](#)

[Requisitos](#)

Este documento requer uma compreensão básica do protocolo de IPsec. Para saber mais sobre o IPsec, consulte [Uma introdução à criptografia de segurança de IP \(IPSec\)](#).

[Componentes Utilizados](#)

As informações neste documento são baseadas nestas versões de software e hardware:

- Software Release 12.3(5) de Cisco IOS®
- Cisco 3640 Routers

As informações neste documento foram criadas a partir de dispositivos em um ambiente de

laboratório específico. Todos os dispositivos utilizados neste documento foram iniciados com uma configuração (padrão) inicial. Se a sua rede estiver ativa, certifique-se de que entende o impacto potencial de qualquer comando.

Convenções

Para obter mais informações sobre convenções de documento, consulte as [Convenções de dicas técnicas Cisco](#).


Configurar

Nesta seção, você encontrará informações para configurar os recursos descritos neste documento.

Nota: Para localizar informações adicionais sobre os comandos usados neste documento, utilize a Ferramenta Command Lookup (somente clientes [registrados](#)).

Diagrama de Rede

Este documento utiliza a configuração de rede mostrada neste diagrama.



Configurações

Este documento utiliza as seguintes configurações:

- [roteador 3640-2b "público"](#)
- [Roteador "privado" 3640-6a](#)

roteador 3640-2b "público"

```
rp-3640-2b#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-2b ! ip subnet-
zero ! ! !--- Defines the Internet Key Exchange (IKE)
policies. crypto isakmp policy 1 !--- Defines an IKE
policy. Use the crypto isakmp policy !--- command in
global configuration mode. IKE policies !--- define a
set of parameters !--- that are used during the IKE
phase I negotiation. hash md5 authentication pre-share
!--- Specifies preshared keys as the authentication
method. crypto isakmp key cisco123 address 95.95.95.2 !-
-- Configures a preshared authentication key, used in !-
-- global configuration mode. ! crypto ipsec transform-
set rtpset esp-des esp-md5-hmac !--- Defines a
```

```

transform-set. This is an acceptable !--- combination of
security protocols and algorithms, !--- which has to be
matched on the peer router. ! crypto map rtp 1 ipsec-
isakmp !--- Indicates that IKE is used to !--- establish
the IPSec security associations (SAs) that protect !---
the traffic specified by this crypto map entry. set peer
95.95.95.2 !--- Sets the IP address of the remote end.
set transform-set rtpset !--- Configures IPSec to use
the transform-set !--- "rtpset" defined earlier. match
address 115 !--- This is used to assign an extended
access list to a !--- crypto map entry which is used by
IPSec !--- to determine which traffic should be
protected !--- by crypto and which traffic does not !---
need crypto protection. ! interface Ethernet0/0 ip
address 98.98.98.1 255.255.255.0 no ip directed-
broadcast ! interface Ethernet0/1 ip address 99.99.99.2
255.255.255.0 no ip directed-broadcast no ip route-cache
!--- Enable process switching for !--- IPSec to encrypt
outgoing packets. !--- This command disables fast
switching. no ip mroute-cache crypto map rtp !---
Configures the interface to use !--- the crypto map
"rtp" for IPSec. ! . . !--- Output suppressed. . . ip
classless ip route 0.0.0.0 0.0.0.0 99.99.99.1 !---
Default route to the next hop address. no ip http server
! access-list 115 permit ip 98.98.98.0 0.0.0.255
10.103.1.0 0.0.0.255 !--- This access-list option causes
all IP traffic !--- that matches the specified
conditions to be !--- protected by IPSec using the
policy described by !--- the corresponding crypto map
command statements. access-list 115 deny ip 98.98.98.0
0.0.0.255 any ! line con 0 transport input none line aux
0 line vty 0 4 login ! end

```

Roteador "privado" 3640-6a

```

rp-3640-6a#show running config Building configuration...
Current configuration: ! version 12.3 service timestamps
debug uptime service timestamps log uptime no service
password-encryption ! hostname rp-3640-6a ! ! ip subnet-
zero !--- Defines the IKE policies. ! crypto isakmp
policy 1 !--- Defines an IKE policy. !--- Use the crypto
isakmp policy !--- command in global configuration mode.
IKE policies !--- define a set of parameters !--- that
are used during the IKE phase I negotiation. hash md5
authentication pre-share !--- Specifies preshared keys
as the authentication method. crypto isakmp key cisco123
address 99.99.99.2 !--- Configures a preshared
authentication key, !--- used in global configuration
mode. ! crypto ipsec transform-set rtpset esp-des esp-
md5-hmac !--- Defines a transform-set. This is an !---
acceptable combination of security protocols and
algorithms, !--- which has to be matched on the peer
router. crypto map rtp 1 ipsec-isakmp !--- Indicates
that IKE is used to establish !--- the IPSec SAs that
protect the traffic !--- specified by this crypto map
entry. set peer 99.99.99.2 !--- Sets the IP address of
the remote end. set transform-set rtpset !--- Configures
IPSec to use the transform-set !--- "rtpset" defined
earlier. match address 115 !--- Used to assign an
extended access list to a !--- crypto map entry which is
used by IPSec !--- to determine which traffic should be
protected !--- by crypto and which traffic does not !---
need crypto protection. . . !--- Output suppressed. . .
! interface Ethernet3/0 ip address 95.95.95.2
255.255.255.0 no ip directed-broadcast ip nat outside !-

```

```

-- Indicates that the interface is !--- connected to the
outside network. no ip route-cache !--- Enable process
switching for !--- IPsec to encrypt outgoing packets. !-
-- This command disables fast switching. no ip mroute-
cache crypto map rtp !--- Configures the interface to
use the !--- crypto map "rtp" for IPsec. ! interface
Ethernet3/2 ip address 10.103.1.75 255.255.255.0 no ip
directed-broadcast ip nat inside !--- Indicates that the
interface is connected to !--- the inside network (the
network subject to NAT translation). ! ip nat pool FE30
95.95.95.10 95.95.95.10 netmask 255.255.255.0 !--- Used
to define a pool of IP addresses for !--- NAT. Use the
ip nat pool command in !--- global configuration mode.
ip nat inside source route-map nonat pool FE30 overload
!--- Used to enable NAT of !--- the inside source
address. Use the ip nat inside source !--- command in
global configuration mode. !--- The 'overload' option
enables the router to use one global !--- address for
many local addresses. ip classless ip route 0.0.0.0
0.0.0.0 95.95.95.1 !--- Default route to the next hop
address. no ip http server ! access-list 110 deny ip
10.103.1.0 0.0.0.255 98.98.98.0 0.0.0.255 access-list
110 permit ip 10.103.1.0 0.0.0.255 any !--- Addresses
that match this ACL are NATed while !--- they access the
Internet. They are not NATed !--- if they access the
98.98.98.0 network. access-list 115 permit ip 10.103.1.0
0.0.0.255 98.98.98.0 0.0.0.255 !--- This access-list
option causes all IP traffic that !--- matches the
specified conditions to be !--- protected by IPsec using
the policy described !--- by the corresponding crypto
map command statements. access-list 115 deny ip
10.103.1.0 0.0.0.255 any route-map nonat permit 10 match
ip address 110 !! line con 0 line vty 0 4 ! end

```

Verificar

Esta seção fornece informações que você pode usar para confirmar se sua configuração está funcionando adequadamente.

A [Output Interpreter Tool \(somente clientes registrados\)](#) oferece suporte a determinados comandos show, o que permite exibir uma análise da saída do comando show.

Para verificar esta configuração, tente um comando extended ping originado da interface Ethernet no roteador privado 10.103.1.75, destinado à interface Ethernet no roteador público 98.98.98.1

- [sibilo](#) — Usado para diagnosticar a conectividade de rede básica.
 rp-3640-6a#ping Protocol [ip]: Target IP address: 98.98.98.1 Repeat count [5]: Datagram size [100]: Timeout in seconds [2]: Extended commands [n]: y Source address or interface: 10.103.1.75 Type of service [0]: Set DF bit in IP header? [no]: Validate reply data? [no]: Data pattern [0xABCD]: Loose, Strict, Record, Timestamp, Verbose[none]: Sweep range of sizes [n]: Type escape sequence to abort. Sending 5, 100-byte ICMP Echos to 98.98.98.1, timeout is 2 seconds: !!!!! Success rate is 100 percent (5/5), round-trip min/avg/max = 64/64/68 ms
- [mostre IPsec cripto sa](#) — Mostra os ajustes usados (IPsec) por SA atuais.
- [mostre isakmp cripto sa](#) — Mostra todo o IKE atual SA em um par.
- [show crypto engine](#) — Mostra um sumário da informação de configuração para as crypto-engines. Use o comando show crypto engine no modo de exec privilegiado.

Exemplo de saída de show

Esta saída é do comando `show crypto ipsec sa` emitido no roteador de hub.

```
rp-3640-6a#show crypto ipsec sa interface: Ethernet0/0 Crypto map tag: rtp, local addr.
95.95.95.2 protected vrf: local ident (addr/mask/prot/port): (10.103.1.0/255.255.255.0/0/0)
remote ident (addr/mask/prot/port): (98.98.98.0/255.255.255.0/0/0) current_peer: 99.99.99.2:500
PERMIT, flags={origin_is_acl,} #pkts encaps: 5, #pkts encrypt: 5, #pkts digest 5 #pkts decaps:
14, #pkts decrypt: 14, #pkts verify 14 #pkts compressed: 0, #pkts decompressed: 0 #pkts not
compressed: 0, #pkts compr. failed: 0 #pkts not decompressed: 0, #pkts decompress failed: 0
#send errors 0, #recv errors 0 local crypto endpt.: 95.95.95.2, remote crypto endpt.: 99.99.99.2
path mtu 1500, media mtu 1500 current outbound spi: 75B6D4D7 inbound esp sas: spi:
0x71E709E8(1910966760) transform: esp-des esp-md5-hmac , in use settings ={Tunnel, } slot: 0,
conn id: 2000, flow_id: 1, crypto map: rtp sa timing: remaining key lifetime (k/sec):
(4576308/3300) IV size: 8 bytes replay detection support: Y inbound ah sas: inbound pcp sas:
outbound esp sas: spi: 0x75B6D4D7(1974916311) transform: esp-des esp-md5-hmac , in use settings
={Tunnel, } slot: 0, conn id: 2001, flow_id: 2, crypto map: rtp sa timing: remaining key
lifetime (k/sec): (4576310/3300) IV size: 8 bytes replay detection support: Y outbound ah sas:
outbound pcp sas:
```

Este comando mostra o IPsec SAs construído entre peers. O túnel criptografado é construído entre 95.95.95.2 e 99.99.99.2 para o tráfego que vai entre redes 98.98.98.0 e 10.103.1.0. Você pode ver as duas SAs de Payload de Segurança de Encapsulamento (ESP) desenvolvidas interna e externamente. O Authentication Header (AH) SA não é usado desde que não há nenhum AH.

Troubleshooting

Esta seção fornece informações que podem ser usadas para o troubleshooting da sua configuração.

Comandos para Troubleshooting

A [Output Interpreter Tool \(somente clientes registrados\)](#) oferece suporte a determinados comandos show, o que permite exibir uma análise da saída do comando show.

Nota: Antes de emitir comandos debug, consulte [Informações importantes sobre comandos debug](#).

- `debug crypto ipsec sa` — Usado para ver as negociações de IPSEC de fase 2.
- `debug crypto isakmp sa` — Usado para ver as negociações de ISAKMP de fase 1.
- `motor do debug crypto` — Usado para indicar as sessões de criptografia.

Informações Relacionadas

- [Ordem de Operação NAT](#)
- [Troubleshooting de Segurança de IP - Entendendo e Utilizando Comandos debug](#)
- [Página de suporte do IPSec](#)
- [Página de suporte de NAT](#)
- [Suporte Técnico - Cisco Systems](#)