



## Preparing to Use Campus Manager

---

This chapter describes the various administrator and application setup tasks that you must perform after installing Campus Manager 4.0.

This chapter contains:

- [Overview of Campus Setup Tasks](#)
- [Accessing the CiscoWorks Server`](#)
- [Performing Administrator Tasks](#)
- [Setting Up Campus Manager Applications](#)
- [Logging Out as Administrator](#)

# Overview of Campus Setup Tasks

Table 3-1 provides an overview of the Campus Manager 4.0 setup tasks and references to more detailed information about each task.

**Table 3-1 Overview of Campus Setup Tasks**

Task	Steps	References
1. Access the server.	Access the CiscoWorks Server.	<a href="#">“Accessing the CiscoWorks Server” section on page 3-2</a>
2. Perform administrator setup tasks.	Log in to the server as administrator.	<a href="#">“Logging In as Administrator” section on page 3-3</a>
3. Set up applications.	Launch and configure applications.	<a href="#">“Setting Up Campus Manager Applications” section on page 3-3</a>
4. Log out.	Log out of the server.	<a href="#">“Logging Out as Administrator” section on page 3-12</a>

## Accessing the CiscoWorks Server

You must set up the client before using Campus. See *Installation and Setup Guide for CiscoWorks Common Services 3.0 (Includes Ciscoview) on Solaris* for configuring browser and client systems.

To access Campus Manager, enter the URL of the CiscoWorks Server in your web browser:

```
http://server_name:1741
https://server_name:1742 (for SSL mode)
```

where *server\_name* is the name of the CiscoWorks Server. If you were prompted to supply a port number for the CiscoWorks Server during the installation, use that port number in the URL. The default port number is 1741 (1742 if SSL is enabled).

If you cannot access the CiscoWorks Server or the CiscoWorks Home page is not displayed correctly, refer to [Appendix A, “Troubleshooting the Installation.”](#) In addition, see the troubleshooting chapter in *User Guide for Campus Manager 4.0*.

After you access the CiscoWorks Server, see the [“Performing Administrator Tasks”](#) section on page 3-3.

## Performing Administrator Tasks

After accessing the CiscoWorks Server, you must log in as the administrator and set up the server for other users.

### Logging In as Administrator

To log in as administrator:

- 
- Step 1** Enter the system administrator username and password in the Login Manager dialog box.
  - Step 2** Click **Connect**.

The Login Manager dialog box leads you to the CiscoWorks homepage.

---

After you log in as the administrator, continue to the [“Setting Up Campus Manager Applications”](#) section on page 3-3.

To log out the CiscoWorks Server, see the [“Logging Out as Administrator”](#) section on page 3-12 for information.

## Setting Up Campus Manager Applications

This section describes the tasks that you must perform to set up the Campus Manager 4.0 applications. See the online help for individual applications for troubleshooting information.

This section contains:

- [Setting Up Your Network](#)
- [Configuring Device Discovery](#)
- [Setting Up Topology Services](#)
- [Setting Up User Tracking](#)
- [Setting Up Path Analysis](#)
- [Starting Up VLAN Port Assignment](#)
- [Setting Up Discrepancy Reports](#)



**Note**

Many tasks require the administrator login.

## Setting Up Your Network

To ensure that the ANI Server successfully discovers the devices in your network, you must set up your network correctly. [Table 3-2](#) lists the required tasks for each application, marked by x.

See the *User Guide for Campus Manager 4.0* for more information.

**Table 3-2** Network Setup Tasks

Network Setup Requirement	Topology Services	User Tracking	Path Analysis	VLAN Port Assignment	Discrepancy Reports
Connect to seed device.	x	x	x	x	x
Enable Simple Network Management Protocol (SNMP).	x	x	x	x	x
Enable Cisco Discovery Protocol (CDP).	x	x	x	x	x
Enable Call Detail Record (CDR).	—	—	x	—	—
Set a unique sysName variable on devices.	x	x	x	x	—

**Table 3-2** Network Setup Tasks (continued)

Network Setup Requirement	Topology Services	User Tracking	Path Analysis	VLAN Port Assignment	Discrepancy Reports
Enable Integrated Local Management Interface (ILMI) on ATM devices.	x	x	x	x	x
Configure DNS.	x	x	x	x	x
Configure VLAN Trunk Protocol (VTP).	x	x	x	x	x
Configure VLAN trunks on Fast Ethernet and Gigabit Ethernet.	x	x	x	x	x
Create the default configuration server for ATM LAN Emulation (LANE).	x	x	x	x	x
Enable source routing.	—	—	x	—	—

After you set up your network, continue to the [“Configuring Device Discovery” section on page 3-5](#).

## Configuring Device Discovery

To Configure Device Discovery:

- 
- Step 1** From CiscoWorks Home page, select **Campus Manager > Administration**.  
A new Administration window opens.
  - Step 2** Click on **Discovery > Seed devices**.
  - Step 3** Specify the seed device and IP address range.
  - Step 4** Click **OK** to start Device Discovery.
- 

If IP address range is not specified, Device Discovery will try to discover as many devices as it can based on the community strings and connectivity.

For more information, see [Specifying Seed Device](#) online help.

After you set up your network, continue to the [“Configuring Data Collection” section on page 3-6](#).

## Configuring Data Collection

To configure Data Collection:

- 
- Step 1** From CiscoWorks Home page, select **Campus Manager> Administration**.  
A new Administration window opens.
  - Step 2** Click on **Campus Data Collection> Data Collection Filters**.
  - Step 3** Select IP Address Range, Click **Configure**  
The IP Range Filter dialog box appears.
  - Step 4** Specify the IP Address Range, Click **Apply**.  
A confirmation dialog box appears.
  - Step 5** Click **OK** to start Data Collection. Click **Cancel** to apply the changes.
- 

If the IP address range is not specified, ANI takes all devices from the Device and Credential Repository.

See [Using ANI Data Collection Administration](#) online help for assistance in performing these tasks.

After you configure Data Collection, see the [“Setting Up Your Network” section on page 3-4](#).

**Note**

The number of devices that can be data collected depends upon your licence limit.

## Setting Up Topology Services

To set up Topology Services:

- 
- Step 1** Verify that the ANI Server is running.
  - Step 2** Make sure the ANI Server has managed the devices from Discovery Metrics page.
  - Step 3** From CiscoWorks home page select **Campus Manager > Topology Services** to start the application.

For more information, see the Topology Services online help.

---

## Configuring Network Discrepancies

You can configure the network discrepancies that you would like to be reported by selecting and deselecting the listed discrepancies. To do this, select **Campus Manager > Administration > Network Discrepancy**.

See *User Guide for Campus Manager 4.0* for more information.

## Verifying Topology Services

To verify that Topology Services is working properly:

- 
- Step 1** Verify that all devices and interfaces are discovered.  
Properly discovered devices and interfaces appear in green in the Topology Services window.
  - Step 2** Verify that devices displayed in red are reachable and have correct community strings.
  - Step 3** Verify that all VLANs and ELANs are discovered and that their port assignments are correct.

The devices will be shown in Topology services only after data collection.

For more information, see the Topology Services online help.

---

## Setting Up User Tracking

To set up User Tracking:

- 
- Step 1** Start User Tracking.
- Step 2** Confirm that the Ping Sweep option is enabled.
- If you enable User and Host Acquisition, perform the tasks outlined in the [“Supporting User Name Collection” section on page 3-8](#).
- For more information, see the User Tracking online help.
- 

## Supporting User Name Collection

To have the ANI Server automatically retrieve user names for User Tracking, you must enable user and host acquisition and install appropriate scripts. See the ANI Server online help for more information.

## Verifying User Tracking

To verify that User Tracking is working properly, see that the Ping Sweep option is enabled. To verify:

- 
- Step 1** From CiscoWorks Home page, select **Campus Manager > User Tracking**.  
A new User Tracking window opens.
- Step 2** Click on **Admin > Discovery** to verify that the Ping Sweep option is enabled.
-

## Setting Up Path Analysis

To set up Path Analysis:

- 
- Step 1** Install and configure a DNS server on your network.  
A DNS server is required for Campus Manager. For devices with multiple IP addresses, there should be a single DNS entry that includes all IP addresses.
  - Step 2** Specify correct read community strings on all devices.
  - Step 3** Specify correct write community strings for multi-layer switching shortcut path determination on Catalyst 5000 devices.
  - Step 4** Edit the VLAN/ELAN Mapping Table, which provides mapping of VLANs and ELANs to subnets.

These mappings are auto-discovered based on information gathered by Topology Services and User Tracking.

In some cases, the information might be incomplete. In these cases, you can edit a VLAN/ELAN mapping table to supplement the Topology Services and User Tracking information. If subnet mappings are not correct, Layer 2 traces on those subnets might fail.

- Step 5** Enable Cisco Discovery Protocol (CDP) on all Cisco devices.  
If CDP is not enabled, these devices will not appear on Layer 2 path traces.
- Step 6** Enable source routing on your network.

This is required if you plan to run path traces outside of the domain known to Topology Services.

For more information, see the Path Analysis online help.

---

## Verifying Path Analysis

To verify that Path Analysis is working properly:

- 
- Step 1** Start Topology Services and make sure that all devices, interfaces, and links are managed properly.  
Properly managed devices appear in green in the Topology Services window.

- Step 2** Verify that all VLANs and ELANs are managed with correct port assignments.
- Step 3** Start User Tracking and run Discovery with a Ping Sweep option enabled to verify that all end-user stations are managed.
- Step 4** Run **nslookup** on several known devices in the command shell.
- Step 5** Verify that DNS lookup works and takes one second or less.
- Step 6** Verify the Subnet Mapping table entries.
- Each VLAN and ELAN entry should have any corresponding subnets listed. Any subnets that do not correspond to a VLAN or ELAN should be in a Subnet row.
- Step 7** Run a few traces between endpoints known to User Tracking or Topology Services and verify that the trace completed successfully.
- For troubleshooting information, see the Path Analysis online help.
- 

## Starting Up VLAN Port Assignment

To start VLAN Port Assignment:

- 
- Step 1** Verify that your network is set up properly.
- Step 2** Verify that the ANI Server is set up properly and running.
- Step 3** From the CiscoWorks Homepage, select **Campus Manager > VLAN Port Assignment**.
- 

If you are prompted to install the Java plug-in, download and install the plug-in using the displayed installation screens. The next time you start the application, it will automatically use the plug-in.

See Online help for ANI Server, for information about setting up your network and the ANI Server.

## Displaying Topology Views and Attribute Summaries

To highlight devices, VLANs in a VTP domain, or a VTP domain map, or to display attribute summaries for devices, Topology Services must be running. See the VLAN Port Assignment online help for more information.

## Verifying VLAN Port Assignment

To verify that VLAN Port Assignment is working properly:

- 
- Step 1** Check the status bar to verify that the ANI Server is running properly.
  - Step 2** Perform a Port Summary for a VTP Domain.  
The table is populated with that domain's port information.
  - Step 3** Select a port, preferably unconnected, and move it to a different VLAN.  
The port information is updated.  
See the VLAN Port Assignment online help for more information.
- 

## Setting Up Discrepancy Reports

To set up Discrepancy Reports:

- 
- Step 1** Select **Campus Manager > Administration > Network Discrepancies**.  
The Configuring Network Discrepancies windows appears.
  - Step 2** To include a discrepancy in the Discrepancy Reports, check the box next to it.  
Check all the boxes for a report displaying all discrepancies in the network.
  - Step 3** To exclude a discrepancy from the Discrepancy Reports, uncheck the box.
  - Step 4** Click **Apply**
-

You can use the filters to display discrepancy reports for specific devices, link or network types. This makes it easy to find a particular discrepancy for a particular type.

For more information, see the Discrepancy Reports online help.

## Verifying Discrepancy Reports

To verify that Discrepancy Reports is working properly, check the status bar to verify that the ANI Server is running properly.

# Logging Out as Administrator

To end your administrator tasks, you must log out of Campus Manager.

- 
- Step 1** Close all secondary browser windows. You should have only one browser window opened displaying the Campus Manager interface.
- Step 2** Click **Logout**.
- The Login Manager dialog box replaces the navigation tree.
-